

SMC Structure Strategy

Every setting explained in plain English: what it does, an example, and the value to use for automated XAUUSD trading on FxPro.

SCRIPT

SMC_Structure_Strategy_v5.0.txt

BUILT FOR

XAUUSD, 1-minute chart, OANDA feed

EXAMPLE ACCOUNT

10,000 USD, 50 base risk

PLATFORM

TradingView, Pine Script v6

EXECUTED AT

FxPro (MT4/MT5) via a webhook bridge

BROKER COSTS USED

28 per lot per side, spread 0.16

This handbook describes what the code does, checked line by line and in a simulator. It is not financial advice, and no backtest guarantees future results. Run it on a demo account first.

CONTENTS

What is in this handbook

Read chapters 1 to 3 once. Use the rest as a reference: every setting has its own card with the default, the value to use and the reason.

1	Start here What the strategy does, in one page	3
2	Your recommended setup Every setting on one page, with the value to use	4
3	How one trade works From a CHOCH on the chart to an order at FxPro, with real numbers	6
4	Group 20 - Entries, session, targets Signals, entry rules, target, stop, time filters	8
5	Group 21 - Position size and risk Sizing, lot rounding, leverage cap, Rule A and Rule B	11
6	Group 22 - Webhook message What is sent to your broker bridge	15
7	Group 23 - Commission How broker charges change size and target	16
8	Group 24 - Safety Daily limits, stop filters, weekend	17
9	Groups 25 to 28 - News, spread, profit target, news dates Blackout windows, spread model, stopping at a profit, news only on chosen dates	18
10	The Properties tab The ten TradingView fields and what to put in each	21
11	The counter table What every row means and the sums that must add up	22
12	Automation Alert set-up, messages, keeping live close to the backtest	24
13	Before you go live The checklist	25
14	Questions and problems Answers to the questions that have come up so far	26
15	Glossary Every term used in this handbook	27

Start here

The strategy watches market structure on your chart, turns main-tier CHOCH or BOS signals into limit orders with a stop and a target, and sends each fill to your broker through a webhook.

What it does, in five lines

- 1 **It finds structure.** The same engine as the SMC Market Structure indicator (v17.3) marks pivots, BOS and CHOCH. The strategy trades only the **main tier**, not internal or inner structure.
- 2 **A signal arms a setup.** A CHOCH (or BOS, if you allow it) gives a direction, a stop at the opposite structure level, an entry level and a target.
- 3 **It waits for price.** The entry is a limit order at a pullback level (Rule 1) or at the pivot that was just broken (Rule 2). No chasing at market.
- 4 **It sizes for your risk.** The size is worked out so that a stop-out loses your risk amount *including* commission and spread, rounded to 0.01 lots, capped by leverage.
- 5 **It sends the fill to your broker.** When TradingView fills the order, one alert sends buy or sell with the stop and target to your bridge, and FxPro opens the trade.

What it will not do

- Hold a long and a short at the same time. One position at a time, which is a TradingView limit.
- Move the stop to breakeven or trail it. The stop and target are set at entry and stay there.
- Add to a position. Pyramiding is zero.
- Invent a stop. If there is no opposite structure level, there is no trade.
- Protect you from a recovery ladder (Rule A or B) that you switch on. Only the hard cap does that.

The files

File	What it is
<code>SMC_Structure_Strategy_v5.0.txt</code>	The strategy. Paste it into the Pine Editor, save, add to chart.
<code>SMC_Structure_Strategy_v5.0_NOTES.txt</code>	The full notes: every feature, every bug ever found and fixed, how each version was tested.
<code>SMC_Structure_Strategy_v5.0_HANDBOOK.pdf</code>	This handbook: every setting, with an example and the value to use.

Three settings outside the Inputs tab decide whether live matches the backtest

- **Properties** → **Script execution:** "On bar close" only. Untick "On realtime bar tick".
- **Properties** → **Long / Short leverage:** 100x, so TradingView never simulates a margin call.
- **After any change to Inputs or Properties:** delete the alert and create it again. An alert keeps the settings it was created with.

Words you will see everywhere

Risk	The money you lose if the stop is hit, after commission and spread. Your base risk is 50.
CHOCH* level	The live structure level on the other side of the trade. The stop goes just beyond it.
Lot / ounce	1 lot of gold = 100 ounces. TradingView counts ounces (a size of 5 = 0.05 lots). Your broker counts lots.
Costs per ounce	Commission 28 + 28 per lot = 0.56 per ounce, plus spread 0.16 = 0.72 per ounce for a complete trade.

Your recommended setup

One page with every setting and the value to use for XAUUSD on a 1-minute OANDA chart, a 10,000 USD FxPro account, 28 per lot per side commission and a spread of 0.08 to 0.16. Each value is explained on its setting card later in the handbook.

Setting	Set to	Why, in one line
Group 20 - Entries, session, targets		
Enable trading	ON	Master switch for new trades.
RULE 1 - pullback % entry	ON	Takes the signals the higher timeframe disagrees with.
RULE 2 - broken pivot, HTF must agree	ON	Takes the signals the higher timeframe agrees with.
Take trades on	CHOCH only	Fewest, cleanest signals. Test CHOCH and BOS in a backtest.
RULE 1 pullback %	25 (yours)	Lower fills more often at worse prices; 50 fills less at better prices.
Target - R multiple	3 (yours)	A win pays 3 times the risk, after costs.
Stop buffer	1.0 (yours)	Keeps the stop beyond the level plus the spread.
Opposite signal: close and reverse	ON	A structure change against you ends the trade.
Entry order handling	Compare both	Keep the better one after costs; Send once if they are close.
Higher timeframe for RULE 2	Auto	1m chart reads 15m.
Time-of-day filters	Auto	On for intraday charts, off for daily and above.
Session timezone	Asia/Kolkata	Every hour setting is read in this zone.
Entries from / stop at / force-close	6 / 23 / 2	No trades 02:00 to 06:00 IST (thin market, rollover).
Group 21 - Position size and risk		
Position size	Risk-based off the stop	Every stop-out costs the same money.
BASE risk per trade	50	0.5% of a 10,000 account.
Round to lot step	0.01	FxPro takes 0.01-lot steps.
Rounding may raise risk by at most	25	Stops tiny trades rounding up into big risk.
Max leverage	30	Never above the leverage FxPro gives you on gold.
Loss-recovery sizing	Off	Safest. If you use one, Rule A is gentler at 1:3.
HARD CAP on risk per trade	500	5% of the account. Never 100,000.
When the cap is reached	Stop for the rest of the day	Draws a line under a bad run.
Group 22 - Webhook		
Attach a webhook message	ON (live only)	No effect on the backtest.
Message format	What your bridge reads	JSON unless the bridge needs another.
Minimum lot your broker accepts	0.01	Skips orders FxPro would reject.
Quantity to send	Lots	Raw units would be 100 times too big on MT5.

Setting	Set to	Why, in one line
Group 23 - Commission		
Commission model	Auto - per lot	Detects 100 ounces per gold lot.
Charge per LOT, ONE side	28	Your FxPro commission.
Push the target out to cover commission	ON	A win still nets the full 3R.
Group 24 - Safety		
Cancel an unfilled order on any new signal	ON	Old levels do not linger.
Cancel an unfilled order after N bars	0	Optional; 30 to 60 on 1m if stale fills bother you.
Skip if the stop is CLOSER than	3.0	Below 3 points costs eat more than 19% of the risk.
Skip if the stop is FURTHER than	0 (off)	Optional.
Max trades per day	0 or 10	Optional brake on choppy days.
Stop for the day after losing	150	Three base losses and the day is over.
Stop PERMANENTLY after drawdown %	20	Last line of defence.
Flatten before the weekend	ON, Friday, 21	No trade carries the weekend gap.
Trade 24/7	OFF	Only for crypto.
Groups 25 to 28		
News windows	ON for big USD news	For example 17:50-18:20 IST on CPI and NFP days.
When a window starts	Close any open trade	A news spike can jump your stop.
Broker spread	0.16	Top of the FxPro range you measured.
Profit target	Optional	For example Each day, 150 to 200.
News windows only on chosen dates	ON, this month's news days	Windows block only on CPI, NFP, FOMC days, not every day.
Properties tab		
Initial capital	Your real balance	The leverage cap and drawdown use it.
Script execution	On bar close only	Live then acts only on finished candles, like the backtest.
Commission	Cash per contract, 0.36	Copy the table's 'Paste into Properties' row.
Long / Short leverage	100x	Stops simulated margin calls.
Slippage	0	The spread setting already covers it.
Limit order execution / delay	Requested price / One tick	Standard behaviour.

How one trade works

One long trade from start to finish with your settings and real numbers: pullback 25%, R multiple 3, stop buffer 1.0, base risk 50, commission 28 per lot per side, spread 0.16.

1. The signal

A bullish CHOCH prints. The move runs from the CHOCH* low at **4300.00** up to **4312.00**. The higher timeframe (15m) is not bullish, so this signal goes to **Rule 1**. If it were bullish, Rule 2 would enter at the pivot the CHOCH broke instead.

2. The setup

Item	How it is worked out	Value
Entry (Rule 1, 25%)	$4312.00 - 25\% \times (4312.00 - 4300.00)$	4309.00
Stop	CHOCH* low 4300.00 – buffer 1.00	4299.00
Stop distance	$4309.00 - 4299.00$	10.00
Costs per ounce	commission 0.56 + spread 0.16	0.72
Size	$50 \div (10.00 + 0.72) = 4.66 \text{ oz} = 0.0466 \text{ lots}$, rounded to the 0.01 step	0.05 lots
Real risk	$5 \text{ oz} \times 10.72$ (7.2% over 50, inside the 25% limit)	53.60
Target	$4309.00 + 3 \times 10.00 + 0.72 \times (3 + 1)$ cost push-out	4341.88
Leverage check	$5 \text{ oz} \times 4309 = 21,545$, far under $10,000 \times 30 = 300,000$	OK

If the stop is hit: -53.60. If the target is hit: $5 \times 32.88 - 5 \times 0.72 = \mathbf{+160.80}$, exactly 3×53.60 . Costs are inside both numbers.

3. Waiting for the fill

The buy limit sits **inside TradingView** at 4309.00. Nothing is sent to FxPro yet. Two different moments matter:

- **The level is recalculated at each candle close.** In Continuous mode, if the move makes a new high, the level moves up to 25% below the new high at that close. In Send once mode it stays at 4309.00.
- **The fill happens in real time.** On the tick where price touches the level, in the middle of a candle, TradingView fills the order and the alert fires on that same tick.

4. The message and the broker

```
{"id":"","action":"buy","side":"long","symbol":"XAUUSD","qty":0.05,"entry":4309.000,"sl":4299.000,"tp":4341.880}
```

Your bridge receives this and FxPro opens **0.05 lots at market** with SL 4299.00 and TP 4341.88, usually within a second or two. From now on FxPro holds the stop and target itself.

5. The exit

How it ends	What happens at FxPro
Stop or target is hit	FxPro closes it with its own SL / TP. TradingView also sends a close message, which finds nothing to close.
Opposite signal	TradingView closes at the next candle open and sends <code>close</code> . The bridge closes the position.

How it ends	What happens at FxPro
02:00 force-close, weekend cutoff, news window	Same: a <code>close</code> message at that moment.

Continuous or Send once? The same trade both ways

At 10:01 price makes a new high at 4316.00. At 10:04 it dips to 4311.80 and turns up.

	Continuous	Send once
10:01 close	Moves to 4312.00, 0.04 lots, target 4353.88	Stays at 4309.00, 0.05 lots
10:04 dip to 4311.80	Fills at 4312.00	No fill (2.80 above the order)
Price runs away without coming back	Wins at its target	Never fills: 0
Price falls straight to 4299	Stopped out	Fills at 4309, then stopped out
Price dips to 4308.50, then rallies to 4342	Still open, target not reached	Fills and wins at 4341.88

Both risk about 50 and both win 3R when they win. Continuous gets **more fills** and catches strong moves. Send once gets **fewer fills at better prices**. For how closely live copies the backtest they are almost the same once the spread is set: in the simulator the gap was +0.43 per trade for Continuous and +1.18 for Send once. Keep the one with the better backtest after costs.

Group 20 - Entries, session, targets

Which signals are traded, how the entry is placed, where the stop and target go, and at what hours.

Enable trading

Default: ON

Set: ON

- WHAT IT DOES** The master switch for new trades. OFF: no new setups and no new orders. The table keeps counting signals, and the 02:00 force-close still flattens an open trade.
- WHY THIS VALUE** Turn it OFF to pause without removing the strategy. Remember an alert keeps the settings it was made with, so re-create the alert after switching it back on.

RULE 1 - pullback % entry

Default: ON

Set: ON

- WHAT IT DOES** Entry at a pullback of the move, measured from the CHOCH* level to the move's extreme. Used for signals where the higher timeframe does **not** agree.
- **Rule 1 alone** (Rule 2 off): every signal is entered this way. The higher timeframe is not even loaded, so the script is faster.
 - **Both on**: the strategy chooses per signal.

RULE 2 - entry at the broken pivot, higher timeframe must AGREE

Default: ON

Set: ON

- WHAT IT DOES** Entry at the pivot the signal just broke, as a retest, used only when the higher-timeframe trend points the same way as the signal.
- **Rule 2 alone** (Rule 1 off): a signal is traded **only** when the higher timeframe agrees. Everything else is skipped.
 - **Both off**: no trades at all. The table says NONE in red.
- EXAMPLE** Bullish CHOCH breaks a pivot at 4312.00 and the 15m trend is up: Rule 2 places a buy limit at 4312.00. If the 15m trend were down, Rule 1 would place it at the 25% pullback instead.
- WHY THIS VALUE** With both on, you trade every signal but choose the entry type by the higher timeframe. The table's rows 'by ENTRY RULE 1' and 'by ENTRY RULE 2' show how many trades each rule took.

Take trades on

Default: CHOCH only

Set: CHOCH only

- WHAT IT DOES**
- **CHOCH only**: change of character, the reversal signal. Fewest trades.
 - **BOS only**: break of structure, the continuation signal.
 - **CHOCH and BOS**: both, several times more signals.
- Signals you switch off are invisible to the strategy: they do not arm a setup, do not reverse a trade and do not cancel a waiting order.
- WHY THIS VALUE** Start with CHOCH only and compare against CHOCH and BOS in a backtest with the costs set. More signals are not better if each one pays costs.

RULE 1 pullback %

Default: 50

Set: 25 (your current)

WHAT IT DOES How deep the pullback must be before a Rule 1 entry fills. The level is $\text{extreme} - \% \times (\text{extreme} - \text{CHOCH* Level})$ for a long.

In Continuous mode it **ratchets**: every new extreme moves the level up at the next candle close. A candle against the move leaves it alone.

EXAMPLE Move 4300 to 4312: at 25% the level is 4309.00; at 50% it is 4306.00. A pullback that stops at 4307 fills the 25% order but not the 50% order.

WHY THIS VALUE **Smaller %**: fills more often, but closer to the top, so the stop is further away and the size smaller. **Larger %**: fewer fills at better prices. 25 is your choice; test 25 against 50 with costs on.

Target - R multiple

Default: 1.0

Set: 3.0 (your current)

WHAT IT DOES The target distance as a multiple of the entry-to-stop distance. With 'Push the target out' ON, a target hit nets exactly $R \times$ the real risk after costs.

EXAMPLE Stop 10 points away, R 3: target 30 points away, plus 2.88 for costs. Win +160.80 on a 53.60 risk.

WHY THIS VALUE At 3R you win less often but each win pays three losses. It also makes Rule A much gentler (chapter 5).

Stop buffer beyond the CHOCH* level

Default: 0.0

Set: 1.0 (your current)

WHAT IT DOES Extra distance, in price, between the structure level and your stop. For a long the stop is the CHOCH* low minus the buffer.

WHY THIS VALUE Keep it at least your spread (0.16) so a stop is not taken by the spread alone. 1.0 on gold is fine. A bigger buffer means a wider stop and a smaller size.

Opposite signal while in a trade: close and reverse

Default: ON

Set: ON

WHAT IT DOES A TradingView strategy holds one position. ON: an opposite signal closes the running trade at the next candle open and arms the new direction. OFF: the new signal is ignored until the current trade ends.

The **close** works even when trading is halted (daily limit, risk cap, news, weekend). The **reversal** waits until the halt lifts.

WHY THIS VALUE A CHOCH against you means the structure has turned. Staying in rarely helps.

Entry order handling

Default: Continuous - follow the level

Set: Compare both

WHAT IT DOES

- **Continuous**: while a setup waits, the entry, stop and size are recalculated at every candle close and the order follows the level.
- **Send once**: the entry, stop, target and size are fixed when the order is first placed.

Neither changes how many messages your broker gets: an alert is sent only when an order **fills**.

EXAMPLE See 'Continuous or Send once?' at the end of chapter 3.

WHY THIS VALUE Run the backtest both ways with Properties commission set and keep the better net profit. If they are close, Send once is easier to check against the chart.

Higher timeframe for RULE 2

Default: Auto - paired with the chart

Set: Auto

WHAT IT DOES Which timeframe must agree for Rule 2. Auto pairs it with the chart: 1m → 15m, 5m → 1h, 15m → 4h, 1h → 1D, 4h → 1W, 1D → 1M. The trend comes from the last **closed** higher-timeframe candle, so the backtest and live see the same value.

WHY THIS VALUE If you pick a timeframe that is not above the chart's, it is ignored and every signal goes to Rule 1.

Time-of-day filters

Default: Auto - off on daily charts and above

Set: Auto

WHAT IT DOES Switches the session window, the force-close hour and the weekend cutoff together. **Auto**: on for intraday charts, off on 1D and above. **Always apply**: on everywhere. **Never apply**: no time rules at all.

WHY THIS VALUE A daily candle carries a single time of day, so an hour filter on a daily chart would block every trade. Auto prevents that.

Session timezone

Default: Asia/Kolkata

Set: Asia/Kolkata

WHAT IT DOES The timezone every hour setting is read in: session hours, force-close, weekend cutoff, news windows, and the start of each day and week for the daily limits and the profit target.

Take entries from / Stop taking entries at (hour)

Default: 6 / 23

Set: 6 / 23

WHAT IT DOES New trades only between these hours. An order still waiting when the window closes is cancelled; an open trade is not closed by this setting.

EXAMPLE 6 and 23 in IST: entries from 06:00 to 23:00. A window may cross midnight, for example 22 to 4.

Force-close any open trade at (hour)

Default: 2

Set: 2

WHAT IT DOES At this hour any open trade is closed at market and any waiting order is cancelled. From this hour until 'Take entries from' the strategy stays flat.

WHY THIS VALUE 02:00 to 06:00 IST covers the daily rollover, when gold spreads widen and liquidity is thin.

Draw levels / Show the counter table / table position

Default: ON / ON / Bottom right

Set: ON / ON / any

WHAT IT DOES Draws the pending entry (orange), the stop (red) and the target (teal), and shows the counter table (chapter 11). Display only; trading is not affected.

Group 21 - Position size and risk

How big each trade is, and what happens to the size after losses.

The sizing formula

size in ounces = risk ÷ (stop distance + costs per ounce)
 costs per ounce = commission for a complete trade + spread = 0.56 + 0.16 = 0.72
 then: round to 0.01 lots → check the rounding limit → cut by Max leverage

Stop distance	Ounces (50 risk)	Lots sent	Real risk	Costs share of risk
2 points	18.4	0.18	48.96	26%
3 points	13.4	0.13	48.36	19%
5 points	8.7	0.09	51.48	13%
10 points	4.7	0.05	53.60	7%
25 points	1.9	0.02	51.44	3%

Tighter stops mean bigger positions and a larger share lost to costs. That is why chapter 8 recommends skipping stops closer than 3 points.

Position size

Default: Risk-based off the stop

Set: Risk-based off the stop

- WHAT IT DOES**
- **Risk-based:** the formula above. Every stop-out costs the same money on any instrument.
 - **Fixed quantity:** always the same number of units (ounces on gold).
 - **Fixed cash per trade:** always the same position value.

WHY THIS VALUE Only risk-based makes the loss recovery rules, the table's risk rows and the hard cap mean anything.

BASE risk per trade

Default: 50

Set: 50

WHAT IT DOES The money lost when the stop is hit, after commission and spread. Loss recovery (Rule A / B) works in multiples of this number.

WHY THIS VALUE 0.25% to 1% of the account is normal. 50 is 0.5% of 10,000. The 'Last trade risk' row shows what each trade really risked.

Fixed quantity / Fixed cash per trade

Default: 1 / 1000

Set: not used

WHAT IT DOES Only read in those two sizing modes. Ignored with risk-based sizing.

Round the size to the broker's lot step

Default: 0.01

Set: 0.01

WHAT IT DOES Rounds the size to what your broker accepts, so the backtest trades the sizes you really get. Normal rounding: 0.0828 → 0.08; 0.0850 and 0.0899 → 0.09. If rounding reaches zero the setup is skipped, not sent empty. 0 = off.

WHY THIS VALUE Your real risk is then a little above or below 50. That was always true at the broker; now the backtest shows it.

Never let rounding raise the risk by more than (%)

Default: 25

Set: 25

WHAT IT DOES If rounding **up** would push the real risk more than this % over your risk amount, the size is rounded **down** instead.

EXAMPLE 0.0066 lots would round up to 0.01, which is 52% more risk. Above the 25% limit, so it rounds down to 0 and the setup is skipped.

Max leverage (position value / equity)

Default: 30

Set: 30

WHAT IT DOES Caps every trade at equity × this number. When it cuts a trade, the size is rounded down to the lot step and the table row 'Trades cut by leverage cap' counts it.

EXAMPLE Equity 10,000 × 30 = 300,000 of gold, about 0.69 lots at 4,340. Rule B asked for 1.5 lots on one of your trades; this cap cut it to 0.70.

WHY THIS VALUE Keep it at or **below** the leverage FxPro really gives you on gold, or FxPro may reject trades the backtest takes. Keep the Properties leverage (chapter 10) at least 3 times higher.

Loss recovery: how Rule A and Rule B work

Both rules share one number, **losses carried**. After every closed trade:

```
losses carried = losses carried - the trade's result (after commission and spread)
a loss adds to it, a profit takes off from it, it never goes below 0
```

Rule	Next trade risks	With your settings (base 50, R 3)
Off	always the base	50
Rule A	(losses carried + base) ÷ R multiple	(carried + 50) ÷ 3
Rule B	2 × losses carried, never less than the base	2 × carried, at least 50

When losses carried is 0, both go back to 50. A win that only pays off part of the carried losses keeps the ladder going from what is left.

Rule A: three stops, then a target

Risk	Result	Carried
50.00	stop -50.00	50.00
33.33	stop -33.33	83.33
44.44	stop -44.44	127.78
59.26	target +177.78	0

Run ends +50: every loss back plus one base. At 1:3 the risk after the first loss is **lower** than 50, because a win pays three times.

Rule B: three stops, then a target

Risk	Result	Carried
50	stop -50	50
100	stop -100	150
300	stop -300	450
900	target +2,700	0

Run ends +2,250, but needs 900 of risk. With the hard cap at 500 the 900 trade is blocked: the day stops and you restart at 50 tomorrow, 450 down.

Rule A: a partial win in the middle

Risk	Result	Carried
50.00	stop -50.00	50.00
33.33	stop -33.33	83.33
44.44	opposite signal +30.00	53.33
34.44	target +103.33	0

Rule B: early exits, like your trades 13 to 16

Risk	Result	Carried
50	opposite signal -20	20
50	opposite signal -15	35
70	stop -70	105
210	opposite signal +100	5
50	target +150	0

Why Rule B does not look like "doubling" in your List of Trades

It doubles the **total carried**, not the last trade. Opposite-signal exits lose less than the full risk, so the carried amount grows slowly. And once Rule B asks for more than Max leverage allows, the size is cut: on your trade 19 it asked for 1,607 of risk and the cap allowed 736.

Your trades 13 to 20, rebuilt from your List of Trades

#	Carried before	Rule B asked	Lots	How it closed	Result	Carried after
13	0	50	0.04	opposite signal	-22.27	22.27
14	22.27	50 (base)	0.03	opposite signal	-12.57	34.84
15	34.84	69.68	0.04	stop	-66.88	101.72
16	101.72	203.44	0.17	stop	-202.72	304.44
17	304.44	608.88	0.23	opposite signal	-307.19	611.63
18	611.63	1,223.26	0.64	opposite signal	-192.13	803.76
19	803.76	1,607.52	0.70 (cap)	stop	-736.75	1,540.51
20	1,540.51	3,081.02	0.64 (cap)	opposite signal	+795.14	745.37

Stops lost almost exactly what was asked (trades 15 and 16; the gap is 0.01-lot rounding). Early exits lost less. Trades 19 and 20 were cut by Max leverage 30. With the hard cap at 500, trading would have stopped for the day before trade 17.

Loss-recovery sizing

Default: Off

Set: Off (recommended)

WHAT IT DOES Off, Rule A or Rule B, as explained above.

WHY THIS VALUE Both rules grow the position after losses, the fastest known way to empty an account. Rule B from a 50 base: 50, 100, 300, 900, 2,700, 8,100. After five full losses in a row the next trade would risk 81% of a 10,000 account, and at 1:3 you only need to win one trade in four to break even, so long losing streaks are normal. If you use a rule, Rule A is far gentler at 1:3.

HARD CAP on risk per trade / when the cap is reached

Default: 500 / Stop for the day

Set: 500 / Stop for the day

WHAT IT DOES	The most the recovery ladder may ask for on one trade. If the next risk would be higher: • Clamp to the cap and carry on: risk the cap and keep trading. The ladder can no longer recover everything. • Stop for the rest of the day: no new trades today; tomorrow losses carried is cleared and it restarts at the base. • Stop permanently: no new trades until you reload the strategy.
EXAMPLE	Rule B with the cap at 500: 50, 100, 300, then 900 is over 500, so trading stops for the day. The worst day costs 450, 4.5% of the account.
WHY THIS VALUE	Set it to the most you accept losing on one trade, about 5% of the balance. At 100,000 there is effectively no cap.

Group 22 - Webhook message

What the strategy attaches to each order so your bridge can place it at FxPro. None of these settings change the backtest.

Attach a webhook message to every order

Default: OFF

Set: ON for live trading

WHAT IT DOES Fills in the message of every order. One TradingView alert (condition: this strategy, **Order fills**, message `{{strategy.order.alert_message}}`) then sends the right message for every entry and exit.

Message format

Default: JSON

Set: whatever your bridge reads

WHAT IT DOES Three formats. For the long trade in chapter 3:

JSON	<code>{"id":"","action":"buy","side":"long","symbol":"XAUUSD","qty":0.05,"entry":4309.000,"sl":4299.000,"tp":4341.880}</code>
PineConnector	<code>ID,buy,XAUUSD,sl=4299.000,tp=4341.880,volume=0.05</code>
Plain text	<code>buy XAUUSD side=long qty=0.05 entry=4309.000 sl=4299.000 tp=4341.880</code>

An exit sends `close` (JSON, plain) or `closeLong` / `closeShort` (PineConnector).

WHY THIS VALUE

Ask your bridge for its exact format and compare it with the JSON above before going live.

Minimum lot your broker accepts

Default: 0 (no check)

Set: 0.01

WHAT IT DOES A setup whose size comes out below this is skipped instead of sent. It is counted in the table row 'Skipped - stop distance / min lot'.

EXAMPLE 50 risk on a 300-point stop is 0.0017 lots. FxPro would reject it; with 0.01 set, the strategy never sends it.

Quantity to send

Default: Lots

Set: Lots

WHAT IT DOES TradingView sizes gold in ounces. **Lots** divides by 100 before sending, so 5 ounces is sent as 0.05. **Raw units** sends 5, which an MT5 bridge reads as 5 lots.

WHY THIS VALUE The most dangerous setting in the file: the wrong choice makes every trade 100 times too big. MT4/MT5 bridges want Lots. Check the first live trade's size in MT5.

License ID / account tag

Default: blank

Set: as your bridge needs

WHAT IT DOES PineConnector puts its licence ID first in every command; JSON copies it into the `id` field. Leave blank if your bridge does not use one.

Group 23 - Commission

Your broker's charge per trade, so the size and the target account for it. This group feeds the strategy's own sizing and counters; TradingView's report needs the Properties tab as well (chapter 10).

Commission model

Default: Auto - per lot, contract size from the ticker

Set: Auto - per lot

- WHAT IT DOES**
- **Auto - per lot:** you enter the charge per lot, one side. The lot size is read from the ticker: 100 for gold, 5,000 for silver, 100,000 for forex pairs, 1 for everything else.
 - **Per lot - I set the contract size:** the same, but you type the units per lot.
 - **Percent of trade value:** for crypto and shares.
 - **Fixed cash per order:** a flat fee per order.
 - **Off:** commission ignored.

WHY THIS VALUE The table row 'Commission model' shows what was detected, for example '28/lot x2, lot=100'. Check it on a new ticker.

Charge per LOT, ONE side

Default: 28

Set: 28

WHAT IT DOES The charge to open (the strategy doubles it for the close). 28 per lot per side on gold is 0.28 per ounce per side, 0.56 per ounce for a complete trade.

Units per lot / Percent / Fixed cash

Default: 100 / 0.05 / 3.50

Set: not used

WHAT IT DOES Only read by the matching commission model.

Push the target out to cover the commission

Default: ON

Set: ON

WHAT IT DOES Moves the target far enough that a win still nets the full R after costs. The push-out is costs per ounce $\times (R + 1)$: with your settings $0.72 \times 4 = 2.88$ points.

EXAMPLE Without it, on a 3-point stop at 1:1, a loss costs 50 but a win pays only about 34.

WHY THIS VALUE Without it the costs make every winner smaller than it should be.

Commission in both places: never counted twice

Set 28 here **and** 0.36 per contract in Properties. When Properties has a commission, the strategy uses TradingView's after-cost figures and does not subtract its own again. Properties changes only TradingView's report; the sizes, targets and messages are the same either way.

Group 24 - Safety

Every guard here is optional. Each one stops new trades; none of them stops an opposite-signal exit.

Cancel an unfilled order on ANY new signal

Default: ON

Set: ON

WHAT IT DOES When a new signal prints, a waiting order is pulled, even if the new signal does not arm a setup itself. OFF: the old order stays until something replaces it.

Cancel an unfilled order after N bars

Default: 0 (never)

Set: 0, or 30 to 60 on 1m

WHAT IT DOES A setup that has waited this many candles without filling is dropped. Counted in 'Cancelled - expired unfilled'.

Skip the setup if the stop is CLOSER than (price)

Default: 0 (off)

Set: 3.0

WHAT IT DOES Setups with a stop nearer than this are skipped and counted in 'Skipped - stop distance / min lot'.

EXAMPLE At a 3-point stop costs are 19% of the risk; at 1 point they are 42%. The 'Costs last trade' row turns red above 25%.

WHY THIS VALUE Very tight stops mean huge positions where the spread and commission take most of the risk.

Skip the setup if the stop is FURTHER than (price)

Default: 0 (off)

Set: 0 (off)

WHAT IT DOES The other end: a very wide stop makes the size tiny and the target far away. Optional.

Max trades per day

Default: 0 (no limit)

Set: 0 or 10

WHAT IT DOES After this many entries in a day (midnight to midnight in the session timezone), no new trades until tomorrow.

Stop for the day after losing this much

Default: 0 (off)

Set: 150

WHAT IT DOES Adds up the day's closed results after costs. Once the day is down by this amount, no new trades until tomorrow.

EXAMPLE 150 = three base losses. The day ends before a bad run gets expensive.

Stop PERMANENTLY after an equity drawdown of this %

Default: 0 (off)

Set: 20

WHAT IT DOES Measured from the highest equity reached. Unlike the daily stop it never resets: no new trades until you reload the strategy.

Weekend: flatten before it / cutoff day and hour / Trade 24/7

Default: ON / Fri 21 / OFF

Set: ON / Fri 21 / OFF

WHAT IT DOES From the cutoff until the market reopens, any open trade is closed and nothing new is opened; Saturday and Sunday are blocked. 'Trade 24/7' ON treats weekends like any other day: for crypto only, never for gold.

WHY THIS VALUE A weekend gap does not respect your stop: price can open far beyond it on Monday.

Groups 25 to 28 - News, spread, profit target, news dates

Blackout windows around news, the broker's spread as a cost, stopping once you have made enough, and news windows that only work on the dates you choose.

Group 25 - News / blackout windows

When a window starts

Default: Close any open trade

Set: Close any open trade

WHAT IT DOES Close any open trade: flatten at market when a window begins. Leave open trades alone: the running trade keeps its stop and target; only new trades are blocked.

WHY THIS VALUE A news spike can jump straight through a stop and fill far worse than the price you set.

Window 1, 2, 3 - block trading / time

Default: all off

Set: on for big USD news

WHAT IT DOES Up to three windows, in hours and minutes, read in the session timezone. Inside a window no setup is armed, any waiting order is cancelled, and an open trade is handled by the setting above. A window may cross midnight (2330-0030). Windows only work on intraday charts.

EXAMPLE US CPI and NFP come out at 8:30 New York time: 18:00 IST in the US summer, 19:00 IST in the US winter. A window of 17:50-18:20 covers the summer release. FOMC decisions: 23:30 IST in summer, 00:30 IST in winter.

WHY THIS VALUE Switch a window on for the days that matter and move it when US clocks change.

Group 26 - Live-trading realism

Broker spread, in price

Default: 0 (not modelled)

Set: 0.16

WHAT IT DOES Your broker's spread, in price (not ticks, not points). The strategy treats it as a cost like commission: the size shrinks so a stop-out still costs your risk, the target moves out so a win still nets full R, and the 'Paste into Properties' row includes half of it per side. Nothing sent to the broker changes.

EXAMPLE You measured 0.08 to 0.16 on FxPro gold. With 0.16, costs per ounce become $0.56 + 0.16 = 0.72$, and the Properties number becomes $0.72 \div 2 = 0.36$.

WHY THIS VALUE TradingView fills the backtest at the chart price and never charges a spread. In the simulator, setting the spread shrank the backtest-versus-live gap from -6.05 to +0.60 per trade. Use the top of the range you see so the backtest errs on the careful side.

Group 27 - Profit target: stop new trades

New in v4.2. Once the net result of your closed trades reaches the target, the strategy takes no new trades. It never closes a running trade: the count only changes when a trade closes, and this strategy holds one trade at a time, so you are already flat.

Stop taking new trades once the profit target is reached

Default: OFF

Set: optional

WHAT IT DOES Switches the feature on. The table row 'Profit target (made / target)' shows progress; it turns green with REACHED, and BLOCKED NOW reads 'profit target'.

Profit target, in account currency

Default: 500

Set: your choice

WHAT IT DOES Net profit after commission and spread, the same figure as TradingView's Cumulative P&L once Properties commission is set.

Count the profit

Default: Total since the start date

Set: Each day, if you use it daily

WHAT IT DOES

- **Total since the start date:** everything closed from the start date. Once reached it stays stopped. To trade again, raise the target or move the date, then re-create the alert.
- **Each day:** counts from zero every midnight in the session timezone. Reached means no more trades today; tomorrow it starts again.
- **Each week:** the same, from zero every Monday.

EXAMPLE Each day, target 200. Monday: +120, -40, +150 = 230, so trading stops for Monday. Tuesday starts at 0: -50, -50, +250 = 150, still under 200, so it keeps trading.

Start date (only for Total)

Default: 1 Jan 2000

Set: the day the live alert starts

WHAT IT DOES Trades that close on or after this moment are counted. Only used by 'Total'.

WHY THIS VALUE TradingView runs the whole chart history before it goes live, and with the 2000 default those backtest trades count. If the backtest already made more than the target, the live alert starts out stopped. For live trading with 'Total', set this to the day you switch the alert on. For a backtest, leave it at 2000.

Profit target and loss limit together

Each day with a 200 target and 'Stop for the day after losing' at 150 gives every day a ceiling and a floor. The profit target does not reset the Rule A / B ladder; it carries on when trading starts again.

Group 28 - News windows only on chosen dates

New in v5.0. It changes **when** the group 25 windows apply, not what they do. Off: the windows work every day, as before.

News windows work **ONLY** on the dates below

Default: OFF

Set: ON, with this month's news days

WHAT IT DOES ON: a news window only blocks trading on the dates you list. On every other date it does nothing, even though it is switched on.

The date that counts is the date the window **starts** on, in the session timezone. A 2325-0015 window for FOMC on the 17th needs only 17 in the list; it still runs past midnight.

EXAMPLE CPI on the 12th and NFP on the 3rd. Window 1: 1750-1820. Dates: 3, 12. On the 3rd and 12th no trading 17:50 to 18:20; on every other day the window does nothing.

WHY THIS VALUE Big news is on a few days a month. Blocking the same hours every day throws away good trading hours for nothing.

Dates (day of the month)

Default: empty

Set: for example 3, 12, 17

WHAT IT DOES Days separated by commas or spaces; ranges work. 3, 12, 28 or 12-14 or 3 12 17 28 or 12 - 14, 20. Days 1 to 31 only; anything else is ignored.

The table row 'News windows active on' shows what was read, e.g. '3, 12, 28 of Oct 2026'. ON with nothing valid shows NO VALID DATES in red, and the windows then block nothing.

These dates are for

Default: This month only

Set: This month only

WHAT IT DOES

- **This month only:** the dates apply to the current calendar month. Earlier months in the backtest are not blocked on them. When a new month starts, type the new dates and re-create the alert; if you forget, the windows stop working until you do.
- **Every month:** the same day numbers in every month, e.g. the 12th of each month. Useful in a backtest.

Every month: new dates, new alert

Look up the month's big USD releases in an economic calendar, type the dates (IST), then delete the alert and create it again. An alert keeps the settings it was created with.

The Properties tab

Settings (gear icon) → Properties. These fields belong to TradingView, not to the script, and they decide whether the backtest and live behave the way your Inputs say.

Field	Set to	Why
Initial capital	Your real FxPro balance, USD	The leverage cap (equity × 30) and the drawdown stop are worked out from it. The size is not; it comes from your risk amount.
Default order size	Leave (1, Quantity)	Never used: the strategy always sends its own size.
Pyramiding	0	One position at a time.
Bar detalization	Default	A lower-timeframe option (Premium plans) makes backtest fills more exact inside a candle. It does not change live trading.
Script execution	On bar close ONLY	The one that matters most. With "On realtime bar tick" ticked, live trading acts on unfinished candles, e.g. a CHOC that disappears by the close; the backtest never does. Leave "After order is filled" unticked too.
Commission	Cash per contract, 0.36	Copy the table's 'Paste into Properties cash/contract' row. On your gold chart 1 contract = 1 ounce. Percent is wrong for a per-lot charge; fixed USD per order would charge 0.01 lots the same as 1 lot.
Long / Short leverage	100x	Explained below. 30x caused your "Margin call" exits.
Slippage	0	Makes stops and market exits worse by that many ticks (OANDA gold: 200 ticks = 0.20) where the sizing cannot see it, so a stop-out loses more than your risk. Use the spread setting instead.
Limit order execution	Requested price	The entry fills when price touches your level, which is what the strategy and the alert expect.
Order execution delay	One tick	An order fills on the next tick after it is placed: the normal behaviour.

Margin calls: what they are, and why 100x

With leverage you put up only a deposit, the margin: at 30x it is 1/30 of the trade's value. If the account can no longer cover it, part of the trade is force-closed: a margin call. TradingView simulates this from the Properties leverage.

Step	Properties leverage 30x	Properties leverage 100x
Rule B trade, cut by Max leverage 30	300,000 of gold (0.75 lots at 4,000)	same
Deposit TradingView requires	$300,000 \div 30 = 10,000$: the whole account	$300,000 \div 100 = 3,000$
Price moves 1.00 against you	account 9,925, deposit about 10,000: margin call , part of the trade force-closed	nothing happens; a margin call would need a 7,000 loss

That is how one trade became a 75.8 and a 0.2 in your List of Trades. A real broker only closes positions at its stop-out level, far below the full deposit. Keep Properties leverage at least **3 times** Max leverage; the row 'Margin calls (Properties)' must read 0.

The counter table

Thirty-two rows on the chart. Each counts exactly one thing, from the first candle of the chart to the last.

Signals and trades

Row	What it shows
CHOCH signals on the chart	Every main-tier CHOCH, or 'off' if you do not trade CHOCH.
BOS signals on the chart	The same for BOS.
Setups armed	Signals that passed every rule and got a stop, target and entry level.
Trades entered	Real entries, one per trade. '(1 open)' when one is running.
- by ENTRY RULE 1 / RULE 2	Entries at the pullback level / at the broken pivot.
Setups cancelled, never filled	Orders pulled before they filled. '(+1 waiting)' when an order is resting.

Exits

Row	What it shows
Exit - target / stop	Bracket exits.
Exit - opposite signal	Closed by a reversal signal.
Exit - 02:00 flat / weekend	Closed by the force-close hour or the weekend cutoff.
Exit - news window	Closed because a blackout window started.
Margin calls (Properties)	Slices TradingView force-closed. Must be 0; red if not (chapter 10).

Filters and settings in use

Row	What it shows
Trades cut by leverage cap	Trades entered at a size the Max leverage cap cut down.
Skipped - stop distance / min lot	Setups refused by the stop filters or the minimum lot.
Cancelled - expired unfilled	Orders dropped by the N-bar expiry.
ENTRY rules in use (1 / 2)	'1 + 2 (dynamic)', '1 only', '2 only' or 'NONE' in red.
RULE 2 higher timeframe	15m, 1h, 4h... or why Rule 2 is off.
LOSS RECOVERY (A / B)	'off', 'A - recover + base' or 'B - double the losses'. Not the same thing as the entry rules.

Risk and costs

Row	What it shows
Losses carried	What the recovery ladder still owes.
Risk NEXT trade	What the next trade will risk. Orange when the ladder raised it.
Risk cap hit / HALT	Times the hard cap was reached; HALTED when it is stopping trades now.
Last trade risk	What the last trade really risked, costs included, and its size in lots.
Costs last trade	Commission plus spread on the last trade, and its share of the risk. Red above 25%.
Costs paid total (comm + spread)	All costs across the backtest.
Commission model	What is charged and the lot size detected, e.g. '28/lot x2, lot=100'.

Automation

One alert drives everything: an order fills in TradingView, the alert fires, the webhook reaches your bridge, and the bridge trades at FxPro. TradingView runs the alert on its own servers, so your computer can be off; the bridge must run all the time.

Setting up the alert

- 1 Inputs, group 22: switch on "Attach a webhook message to every order". Pick your bridge's format. Quantity to send: Lots. Minimum lot: 0.01.
- 2 Check the Properties tab (chapter 10). Click OK.
- 3 On the chart: Alerts → Create alert. Condition: **SMC Structure Strategy**, then **Order fills**.
- 4 Message box: `{{strategy.order.alert_message}}` and nothing else.
- 5 Notifications: tick Webhook URL and paste your bridge's URL. Webhooks need a paid TradingView plan.
- 6 Save. This single alert covers every buy, sell and close.

Every time you change a setting

Delete the alert and create it again. An alert keeps a copy of the settings it was created with; changing Inputs or Properties later does not reach it.

What the broker sees, and what it does not

- A **buy** or **sell** with size, stop and target, at the moment TradingView fills the entry. FxPro enters **at market**, a second or two later.
- A **close** when the strategy exits for any reason other than its own stop or target.
- **Never** the waiting order. The limit lives inside TradingView; cancelling it sends nothing because there is nothing at the broker to cancel.
- Moving the stop or target of a running trade: never happens. The bracket is fixed at entry, the same in TradingView and at FxPro.

How close live gets to the backtest

The **decisions** are the same live and in the backtest: same signals, same rule choice, same timing, same bracket, as long as Script execution is "On bar close". What can still differ is the **price**:

1. **Spread**, the biggest. Covered by group 26.
2. **Entry at market after the fill**. FxPro buys a second or two after TradingView's limit fills, usually a little worse. No setting removes this.
3. **Different feeds**. The chart is OANDA; the broker is FxPro. Levels can differ by a few cents.

With the spread set, the simulator put the backtest within about 1 per trade of simulated live, slightly on the careful side. Compare your first 30 to 50 demo trades with the List of Trades to get your own number.

Keeping it running

- Alerts can stop, for example after a "Calculation error". A stopped alert trades nothing and warns no one. Check it daily.
- Check the first live trade's size in MT5 before you leave it alone. The bridge runs all the time: a cloud bridge, or a VPS for an MT5 expert advisor.

Before you go live

Tick every line.

Check	
☐	Properties: Script execution On bar close only.
☐	Properties: Long and Short leverage 100x ; the 'Margin calls' row reads 0.
☐	Properties: Slippage 0 ; Commission Cash per contract with the table's number (0.36).
☐	Properties: Initial capital = your real FxPro balance.
☐	Group 26: Broker spread 0.16 .
☐	Group 21: Max leverage no higher than FxPro's gold leverage. Hard cap 500 , 'Stop for the rest of the day'.
☐	Group 21: Loss recovery Off, or Rule A. If Rule B, you have read chapter 5.
☐	Group 24: Stop closer than 3.0 skipped; daily loss limit set; weekend flatten ON.
☐	Group 27: if you use the profit target with 'Total', the start date is today.
☐	Group 28: if you use news dates, this month's dates are typed and the table row 'News windows active on' shows them.
☐	Group 22: webhook ON, Quantity to send Lots , minimum lot 0.01, format matches your bridge.
☐	Alert: condition Order fills, message <code>{{strategy.order.alert_message}}</code> , webhook URL pasted, created after the last settings change.
☐	The table's three sums add up. 'Costs last trade' is not red.
☐	Two weeks on a demo account. Every fill compared with the List of Trades.
☐	First live trade: size checked in MT5.

Questions and problems

The questions that have come up so far, with the short answer.

The table said 54 setups armed but 100 trades filled.

TradingView's margin-call simulation split trades into slices, and v4.0 counted each slice as a trade. Fixed in v4.1. Set Properties leverage to 100x and the 'Margin calls' row should read 0.

My trades exit on 'Margin call'.

Properties leverage 30x together with Max leverage 30 makes a capped trade use the whole account as deposit, so any loss triggers it. Set Properties leverage to 100x (chapter 10).

Under Rule B my losses do not double each time.

Rule B doubles the total carried, not the last trade. Early exits lose less than the risk, and Max leverage cuts the biggest trades. Chapter 5 shows your trades 13 to 20 step by step.

Is Cumulative P&L before or after costs?

After, once Properties commission is set to 0.36. With Properties commission at 0 it is before costs; subtract the table's 'Costs paid total'.

Changing the spread or commission changed which trades filled.

Costs change the size and push the target out. A trade that just reached its old target may miss the new one, and with Rule B one different result changes every size after it. Expected.

The daily chart shows signals but no trades.

Time-of-day filters must be Auto or Never on daily charts. The 'Time filters' row should say 'off (daily+)'.

A trade appears in TradingView but not at FxPro.

Check in order: the alert exists and is active; condition is Order fills; message is the placeholder; webhook URL is right; Quantity to send is Lots; the size is at least 0.01 lots; the bridge's log shows the message.

Live results are worse than the backtest.

Check that Script execution is 'On bar close', the spread is set, and Properties commission is set. Then compare 30 to 50 trades: a small gap is normal (entry at market after the fill).

The profit target stopped trading as soon as I went live.

With 'Total', the backtest trades count too. Set the start date to the day the alert starts, then re-create the alert.

My news window did not block on a news day.

With group 28 ON, check the row 'News windows active on': the date must be listed, and with 'This month only' it must be this month's date. After changing the dates, re-create the alert.

'Costs last trade' is red.

Costs are over 25% of the risk: the stop was very tight. Set 'Skip if the stop is CLOSER than' to 3.0.

What does 'Entry rules 1 + 2 (dynamic)' mean when I chose Rule B?

They are different settings. Entry rules decide how a trade is entered; Rule A / B decides how much it risks after losses.

Glossary

Every term used in this handbook.

BOS	Break of structure: price breaks the last pivot in the direction of the trend. A continuation signal.
CHOCH	Change of character: price breaks the last pivot against the trend. A reversal signal.
CHOCH* level	The live structure level on the other side of the trade. The stop goes beyond it.
Main tier	The top level of structure. The strategy ignores internal and inner structure.
Move (leg)	The run from the CHOCH* level to the latest extreme. Rule 1 measures its pullback % on it.
Higher timeframe (HTF)	The slower chart Rule 2 checks, e.g. 15m for a 1m chart. Read from its last closed candle.
Risk	Money lost at the stop, after commission and spread.
R multiple	The target as a multiple of the stop distance. 3R pays three times the risk.
Lot, ounce, contract, unit	Gold: 1 lot = 100 ounces. TradingView's contract and unit on OANDA gold = 1 ounce.
Tick, point	The smallest price step. OANDA gold: 1 tick = 0.001. MT5 points for 2-decimal gold: 0.01.
Spread	The gap between buy and sell price, paid on every trade.
Commission, per side / round turn	Your broker's fee: 28 per lot to open, 28 to close, 56 for the round turn.
Slippage	Getting a worse price than asked, mostly on stops and market orders.
Limit order	Buy below / sell above the market at a set price. The strategy's entries are limits inside TradingView.
Market order	Filled immediately at the current price. What the broker does when the alert arrives.
Bracket (SL / TP)	The stop-loss and take-profit attached to a trade.
Webhook, bridge	The alert's message is sent to a URL; the bridge behind it places the trade at FxPro.
Leverage, margin	Leverage lets you hold more than your balance; margin is the deposit the broker keeps for it.
Margin call	Forced closing of part of a trade when the account cannot cover the margin.
Drawdown	The fall from the highest equity reached.
Losses carried	What the recovery ladder still owes, after costs.
Rule A / Rule B	Loss recovery. A: (carried + base) ÷ R. B: 2 × carried, at least the base.
Hard cap	The most one recovery trade may risk.