

SMC Structure Strategy

Every setting explained in plain English: what it does, an example, and the value to use for automated XAUUSD trading on FxPro, and how to set up any other ticker.

SCRIPT

SMC_Structure_Strategy_v8.0.txt

BUILT FOR

XAUUSD, 1-minute chart, OANDA feed

EXAMPLE ACCOUNT

10,000 USD, 50 base risk

PLATFORM

TradingView, Pine Script v6

EXECUTED AT

FxPro MT5 via TheConnector

EXAMPLE COSTS (YOU SET THEM PER TICKER)

28 per lot per side, spread 0.16

This handbook describes what the code does, checked line by line and in a simulator. It is not financial advice, and no backtest guarantees future results. Run it on a demo account first.

CONTENTS

What is in this handbook

Read chapters 1 to 3 once. Use the rest as a reference: every setting has its own card with the default, the value to use and the reason.

1	Start here What the strategy does, in one page	3
2	Your recommended setup Every setting on one page, with the value to use	4
3	How one trade works From a CHOCH on the chart to an order at FxPro, with real numbers	6
4	Group 20 - Entries, session, targets Signals, entry rules, target, stop, time filters	8
5	Group 21 - Position size and risk Sizing, lot rounding, leverage cap, Rule A and Rule B	11
6	Groups 22 and 30 - Webhook message, TheConnector What is sent to your broker bridge, and the TheConnector settings	15
7	Group 23 - Commission How broker charges change size and target	17
8	Group 24 - Safety Daily limits, stop filters, weekend	18
9	News master switch, groups 25 to 28 One switch for all news blocks, blackout windows, spread model, profit target, news dates	19
10	Group 29 - Automatic US news, US clock, US holidays NFP, jobless claims and ISM by rule; summer and winter time; US holidays	22
11	Which signals become trades Rule 1 or Rule 2 per signal, extra trades on BOS, every reason a signal is not traded, audit labels, a new ticker	24
12	The Properties tab The ten TradingView fields and what to put in each	29
13	The counter table What every row means and the sums that must add up	31
14	Automation Alert set-up, messages, live vs backtest, running 24/7 on an MQL5 VPS	33
15	Before you go live The checklist	35
16	Questions and problems Answers to the questions that have come up so far	36
17	Glossary Every term used in this handbook - then every change after v7.1	38

Start here

The strategy watches market structure on your chart, turns main-tier CHOCH or BOS signals into limit orders with a stop and a target, and sends each fill to your broker through a webhook.

What it does, in five lines

- 1 **It finds structure.** The same engine as the SMC Market Structure indicator (v17.3) marks pivots, BOS and CHOCH. The strategy trades only the **main tier**, not internal or inner structure.
- 2 **A signal arms a setup.** A CHOCH (or BOS, if you allow it) gives a direction, a stop at the opposite structure level, an entry level and a target.
- 3 **It waits for price.** The entry is a limit order at a pullback level (Rule 1) or at the pivot that was just broken (Rule 2). No chasing at market.
- 4 **It sizes for your risk.** The size is worked out so that a stop-out loses your risk amount *including* commission and spread, rounded to 0.01 lots, capped by leverage.
- 5 **It sends the fill to your broker.** When TradingView fills the order, one alert sends buy or sell with the stop and target to your bridge, and FxPro opens the trade.

What it will not do

- Hold a long and a short at the same time, which is a TradingView limit.
- Move the stop, unless you switch on group 32 (v7.4): then only to break-even and in 1R steps, never against you.
- Add to a position, except a trade for each same-side BOS (v7.1, chapter 11).
- Invent a stop. If there is no opposite structure level, there is no trade.
- Protect you from a recovery ladder (Rule A or B) that you switch on. Only the hard cap does that.

The files

File	What it is
<code>SMC_Structure_Strategy_v8.0.txt</code>	The strategy. Paste it into the Pine Editor, save, add to chart.
<code>SMC_Structure_Strategy_v8.0_NOTES.txt</code>	The full notes: every feature, every bug ever found and fixed, how each version was tested.
<code>SMC_Structure_Strategy_v8.0_HANDBOOK.pdf</code>	This handbook: every setting, with an example and the value to use.

Three settings outside the Inputs tab decide whether live matches the backtest

- **Properties** → **Script execution:** "On bar close" only. Untick "On realtime bar tick".
- **Properties** → **Long / Short leverage:** 100x, so TradingView never simulates a margin call.
- **After any change to Inputs or Properties:** delete the alert and create it again. An alert keeps the settings it was created with.

Words you will see everywhere

Risk	The money you lose if the stop is hit, after commission and spread. Your base risk is 50.
CHOCH* level	The live structure level on the other side of the trade. The stop goes just beyond it.
Lot / ounce	1 lot of gold = 100 ounces. TradingView counts ounces (a size of 5 = 0.05 lots). Your broker counts lots.
Costs per ounce	You type commission and spread for each ticker. In the gold example: commission 28 + 28 per lot = 0.56 per ounce, plus spread 0.16 = 0.72 per ounce for a complete trade.

Your recommended setup

One page with every setting and the value to use for XAUUSD on a 1-minute OANDA chart, a 10,000 USD FxPro account, 28 per lot per side commission and a spread of 0.08 to 0.16. Each value is explained on its setting card later in the handbook.

Setting	Set to	Why, in one line
Group 0 - News windows master switch (new in v7.0, the first setting)		
News windows ON	ON	OFF = no news and no US-holiday blocks at all.
Group 20 - Entries, session, targets		
Enable trading	ON	Master switch for new trades.
RULE 1 - pullback % entry	ON	Takes the signals the higher timeframe disagrees with.
RULE 2 - broken pivot, HTF must agree	ON	Takes the signals the higher timeframe agrees with.
Take trades on	CHOCH only	Fewest, cleanest signals. With BOS on, a same-side BOS adds a trade (v7.1).
RULE 1 pullback %	25 (yours)	Lower = more fills at worse prices.
Target - R multiple	3 (yours)	A win pays 3 times the risk, after costs.
Stop buffer	1.0 (yours)	Keeps the stop beyond the level plus the spread.
Opposite signal: close and reverse	ON	An opposite CHOCH closes every open trade.
Entry order handling	Compare both	Keep the better one after costs.
Higher timeframe for RULE 2	Auto	1m chart reads 15m.
Time-of-day filters	Auto	On for intraday charts, off for daily and above.
Session timezone	Asia/Kolkata	Every hour setting is read in this zone.
Entries from / stop at / force-close	6 / 23 / 2	No trades 02:00 to 06:00 IST (thin market, rollover).
Signal audit labels	OFF (ON to check)	Shows what happened to every signal.
Group 21 - Position size and risk		
Position size	Risk-based	Every stop-out costs the same money.
BASE risk per trade	50	0.5% of a 10,000 account.
Round to lot step	0.01	FxPro takes 0.01-lot steps.
Rounding may raise risk by at most	25	Stops tiny trades rounding up into big risk.
Max leverage	30	Never above the leverage FxPro gives you on gold.
Loss-recovery sizing	Off	Safest. If you use one, Rule A is gentler at 1:3.
HARD CAP on risk per trade	500	5% of the account. Never 100,000.
When the cap is reached	Stop for the day	Draws a line under a bad run.
Group 22 - Webhook		
Attach a webhook message	ON (live only)	No effect on the backtest.
Message format	TheConnector	Your bridge's own commands.
License ID / account tag	blank	The access key goes in the webhook URL instead.
Minimum lot your broker accepts	0.01	Skips orders FxPro would reject.

Setting	Set to	Why, in one line
Quantity to send	Lots	Raw units would be 100 times too big on MT5.
Group 30 - Broker bridge, TheConnector		
Symbol to send	your MT5 gold name	Blank sends XAUUSD; check Market Watch.
TheConnector tag	smcgold	7 letters or less: each trade adds its own code (smcgold-k3f9).
Stop / target fields	sl_price / tp_price	Always read as exact prices.
Group 23 - Commission		
Commission model	Auto - per lot	Detects 100 ounces per gold lot.
Charge per LOT, ONE side	yours, e.g. 28	Starts at 0. Type it for each ticker.
Push the target out to cover commission	ON	A win still nets the full 3R.
Group 24 - Safety		
Cancel unfilled order on new signal	ON	Old levels do not linger.
Cancel an unfilled order after N bars	0	Optional; 30 to 60 on 1m if stale fills bother you.
Skip if the stop is CLOSER than	3.0	Below 3 points costs eat more than 19% of the risk.
Skip if the stop is FURTHER than	0 (off)	Optional.
Max trades per day	0 or 10	Optional brake on choppy days.
Stop for the day after losing	150	Three base losses and the day is over.
Stop PERMANENTLY after drawdown %	20	Last line of defence.
Flatten before weekend / Trade 24/7	ON, Fri 21 / OFF	No trade carries the weekend gap.
Groups 25 to 29, 31 and 32		
News windows	ON for big USD news	For example 17:50-18:20 IST on CPI and NFP days.
When a window starts	Close any open trade	A news spike can jump your stop.
Broker spread	yours, e.g. 0.16	Type it for each ticker.
Profit target	Optional	For example Each day, 150 to 200.
News windows only on chosen dates	ON, this month	Blocks only on the news days.
Automatic US news windows	ON	NFP, jobless claims, ISM worked out by rule.
NFP / claims / ISM Mfg / ISM Services	ON / ON / ON / ON	Minutes before / after: 10 / 20.
US clock	Auto	Follows US summer and winter time.
Group 25 times in New York time	ON	Type CPI as 0825-0900 New York.
Trade on US market holidays	OFF	Thin, erratic markets.
Max trades open / audit label size (31)	0 or 2 to 3 / Large	Caps stacked BOS trades / readable labels (v7.3).
Step stop / Break-even only (32)	OFF / OFF, or one ON	Optional (v7.4): move the stop as the trade gains.
Properties tab		
Initial capital	Your real balance	The leverage cap and drawdown use it.
Script execution	On bar close only	Live acts only on finished candles.
Commission	Cash/contract 0.36	From the table's 'Paste into Properties' row.
Long / Short leverage	100x	Stops simulated margin calls.
Slippage / limit fills / delay	0 / Requested / 1 tick	Spread setting covers costs.

How one trade works

One long trade from start to finish with your settings and real numbers: pullback 25%, R multiple 3, stop buffer 1.0, base risk 50, commission 28 per lot per side, spread 0.16.

1. The signal

A bullish CHOCH prints. The move runs from the CHOCH* low at **4300.00** up to **4312.00**. The higher timeframe (15m) is not bullish, so this signal goes to **Rule 1**. If it were bullish, Rule 2 would enter at the pivot the CHOCH broke instead.

2. The setup

Item	How it is worked out	Value
Entry (Rule 1, 25%)	$4312.00 - 25\% \times (4312.00 - 4300.00)$	4309.00
Stop	CHOCH* low 4300.00 – buffer 1.00	4299.00
Stop distance	$4309.00 - 4299.00$	10.00
Costs per ounce	commission 0.56 + spread 0.16	0.72
Size	$50 \div (10.00 + 0.72) = 4.66 \text{ oz} = 0.0466 \text{ lots}$, rounded to the 0.01 step	0.05 lots
Real risk	$5 \text{ oz} \times 10.72$ (7.2% over 50, inside the 25% limit)	53.60
Target	$4309.00 + 3 \times 10.00 + 0.72 \times (3 + 1)$ cost push-out	4341.88
Leverage check	$5 \text{ oz} \times 4309 = 21,545$, far under $10,000 \times 30 = 300,000$	OK

If the stop is hit: -53.60. If the target is hit: $5 \times 32.88 - 5 \times 0.72 = \mathbf{+160.80}$, exactly 3×53.60 . Costs are inside both numbers.

3. Waiting for the fill

The buy limit sits **inside TradingView** at 4309.00. Nothing is sent to FxPro yet. Two different moments matter:

- **The level is recalculated at each candle close.** In Continuous mode, if the move makes a new high, the level moves up to 25% below the new high at that close. In Send once mode it stays at 4309.00.
- **The fill happens in real time.** On the tick where price touches the level, in the middle of a candle, TradingView fills the order and the alert fires on that same tick.

4. The message and the broker

```
{"action":"buy","symbol":"XAUUSD","volume":0.05,"sl_price":4299.000,"tp_price":4341.880,"tag":"smcgold-k3f9"}
```

That is the TheConnector format (chapter 6). Your bridge receives this and FxPro opens **0.05 lots at market** with SL 4299.00 and TP 4341.88, usually within a second or two. From now on FxPro holds the stop and target itself.

5. The exit

How it ends	What happens at FxPro
Stop or target is hit	FxPro closes it with its own SL / TP. TradingView also sends a close message, which finds nothing to close.
Opposite signal	TradingView closes at the next candle open and sends <code>closeLong</code> / <code>closeShort</code> for every open trade, each with its own tag. The bridge closes each one.

How it ends	What happens at FxPro
02:00 force-close, weekend cutoff, news window	Same: a <code>close</code> message at that moment.

Continuous or Send once? The same trade both ways

At 10:01 price makes a new high at 4316.00. At 10:04 it dips to 4311.80 and turns up.

	Continuous	Send once
10:01 close	Moves to 4312.00, 0.04 lots, target 4353.88	Stays at 4309.00, 0.05 lots
10:04 dip to 4311.80	Fills at 4312.00	No fill (2.80 above the order)
Price runs away without coming back	Wins at its target	Never fills: 0
Price falls straight to 4299	Stopped out	Fills at 4309, then stopped out
Price dips to 4308.50, then rallies to 4342	Still open, target not reached	Fills and wins at 4341.88

Both risk about 50 and both win 3R when they win. Continuous gets **more fills** and catches strong moves. Send once gets **fewer fills at better prices**. For how closely live copies the backtest they are almost the same once the spread is set: in the simulator the gap was +0.43 per trade for Continuous and +1.18 for Send once. Keep the one with the better backtest after costs.

Group 20 - Entries, session, targets

Which signals are traded, how the entry is placed, where the stop and target go, and at what hours.

Enable trading

Default: ON

Set: ON

WHAT IT DOES The master switch for new trades. OFF: no new setups and no new orders. The table keeps counting signals, and the 02:00 force-close still flattens an open trade.

WHY THIS VALUE Turn it OFF to pause without removing the strategy. Remember an alert keeps the settings it was made with, so re-create the alert after switching it back on.

RULE 1 - pullback % entry

Default: ON

Set: ON

WHAT IT DOES Entry at a pullback of the move, measured from the CHOCH* level to the move's extreme. Used for signals where the higher timeframe does **not** agree.

- **Rule 1 alone** (Rule 2 off): every signal is entered this way. The higher timeframe is not even loaded, so the script is faster.
- **Both on**: the strategy chooses per signal.

RULE 2 - entry at the broken pivot, higher timeframe must AGREE

Default: ON

Set: ON

WHAT IT DOES Entry at the pivot the signal just broke, as a retest, used only when the higher-timeframe trend points the same way as the signal. Since v7.0 a rule 2 setup keeps the stop it was armed with until it fills or is cancelled (chapter 11).

- **Rule 2 alone** (Rule 1 off): a signal is traded **only** when the higher timeframe agrees. Everything else is skipped.
- **Both off**: no trades at all. The table says NONE in red.

EXAMPLE Bullish CHOCH breaks a pivot at 4312.00 and the 15m trend is up: Rule 2 places a buy limit at 4312.00. If the 15m trend were down, Rule 1 would place it at the 25% pullback instead.

WHY THIS VALUE With both on, you trade every signal but choose the entry type by the higher timeframe. The table's rows 'by ENTRY RULE 1' and 'by ENTRY RULE 2' show how many trades each rule took.

Take trades on

Default: CHOCH only

Set: CHOCH only

- WHAT IT DOES**
- **CHOCH only**: change of character, the reversal signal. Fewest trades.
 - **BOS only**: break of structure, the continuation signal.
 - **CHOCH and BOS**: both, several times more signals.

Signals you switch off do not arm a setup, do not reverse a trade and do not cancel a waiting order.

Since v7.1: with BOS on, a BOS the same way as your open trades gets a trade of its own and the open trades stay; an **opposite CHOCH** closes every open trade, in all three modes (chapter 11).

WHY THIS VALUE Start with CHOCH only and compare against CHOCH and BOS in a backtest with the costs set. More signals are not better if each one pays costs.

RULE 1 pullback %

Default: 50

Set: 25 (your current)

WHAT IT DOES How deep the pullback must be before a Rule 1 entry fills. The level is $\text{extreme} - \% \times (\text{extreme} - \text{CHOCH* Level})$ for a long.

In Continuous mode it **ratchets**: every new extreme moves the level up at the next candle close. A candle against the move leaves it alone.

EXAMPLE Move 4300 to 4312: at 25% the level is 4309.00; at 50% it is 4306.00. A pullback that stops at 4307 fills the 25% order but not the 50% order.

WHY THIS VALUE **Smaller %**: fills more often, but closer to the top, so the stop is further away and the size smaller. **Larger %**: fewer fills at better prices. 25 is your choice; test 25 against 50 with costs on.

Target - R multiple

Default: 1.0

Set: 3.0 (your current)

WHAT IT DOES The target distance as a multiple of the entry-to-stop distance. With 'Push the target out' ON, a target hit nets exactly $R \times$ the real risk after costs.

EXAMPLE Stop 10 points away, R 3: target 30 points away, plus 2.88 for costs. Win +160.80 on a 53.60 risk.

WHY THIS VALUE At 3R you win less often but each win pays three losses. It also makes Rule A much gentler (chapter 5).

Stop buffer beyond the CHOCH* level

Default: 0.0

Set: 1.0 (your current)

WHAT IT DOES Extra distance, in price, between the structure level and your stop. For a long the stop is the CHOCH* low minus the buffer.

WHY THIS VALUE Keep it at least your spread (0.16) so a stop is not taken by the spread alone. 1.0 on gold is fine. A bigger buffer means a wider stop and a smaller size.

Opposite signal while in a trade: close and reverse

Default: ON

Set: ON

WHAT IT DOES ON: an opposite signal closes **every** running trade at the next candle open and arms the new direction. An opposite CHOCH does this in all three 'Take trades on' modes, BOS only included (v7.1). OFF: the new signal is ignored until the trades end.

The **close** works even when trading is halted (daily limit, risk cap, news, weekend). The **reversal** waits until the halt lifts.

WHY THIS VALUE A CHOCH against you means the structure has turned. Staying in rarely helps.

Entry order handling

Default: Continuous - follow the level

Set: Compare both

WHAT IT DOES

- **Continuous**: while a setup waits, the entry, stop and size are recalculated at every candle close and the order follows the level.
- **Send once**: the entry, stop, target and size are fixed when the order is first placed.

Neither changes how many messages your broker gets: an alert is sent only when an order **fills**.

EXAMPLE See 'Continuous or Send once?' at the end of chapter 3.

WHY THIS VALUE Run the backtest both ways with Properties commission set and keep the better net profit. If they are close, Send once is easier to check against the chart.

Higher timeframe for RULE 2

Default: Auto - paired with the chart

Set: Auto

WHAT IT DOES Which timeframe must agree for Rule 2. Auto pairs it with the chart: 1m → 15m, 5m → 1h, 15m → 4h, 1h → 1D, 4h → 1W, 1D → 1M. The trend comes from the last **closed** higher-timeframe candle, so the backtest and live see the same value.

WHY THIS VALUE If you pick a timeframe that is not above the chart's, it is ignored and every signal goes to Rule 1.

Time-of-day filters

Default: Auto - off on daily charts and above

Set: Auto

WHAT IT DOES Switches the session window, the force-close hour and the weekend cutoff together. **Auto**: on for intraday charts, off on 1D and above. **Always apply**: on everywhere. **Never apply**: no time rules at all.

WHY THIS VALUE A daily candle carries a single time of day, so an hour filter on a daily chart would block every trade. Auto prevents that.

Session timezone

Default: Asia/Kolkata

Set: Asia/Kolkata

WHAT IT DOES The timezone every hour setting is read in: session hours, force-close, weekend cutoff, news windows, and the start of each day and week for the daily limits and the profit target.

Take entries from / Stop taking entries at (hour)

Default: 6 / 23

Set: 6 / 23

WHAT IT DOES New trades only between these hours. An order still waiting when the window closes is cancelled; an open trade is not closed by this setting.

EXAMPLE 6 and 23 in IST: entries from 06:00 to 23:00. A window may cross midnight, for example 22 to 4.

Force-close any open trade at (hour)

Default: 2

Set: 2

WHAT IT DOES At this hour any open trade is closed at market and any waiting order is cancelled. From this hour until 'Take entries from' the strategy stays flat.

WHY THIS VALUE 02:00 to 06:00 IST covers the daily rollover, when gold spreads widen and liquidity is thin.

Signal audit labels - what happened to every signal

Default: OFF

Set: ON while checking

WHAT IT DOES A small label on every signal you trade on: the signal and the higher-timeframe trend, then R1 / R2 ARMED and FILLED or CANCELLED with the reason, or SKIP with the reason. Changes no trade. Details and examples in chapter 11.

Draw levels / Show the counter table / table position

Default: ON / ON / Bottom right

Set: ON / ON / any

WHAT IT DOES Draws the pending entry (orange), the stop (red) and the target (teal), and shows the counter table (chapter 13). Display only; trading is not affected.

Group 21 - Position size and risk

How big each trade is, and what happens to the size after losses.

The sizing formula

size in ounces = risk ÷ (stop distance + costs per ounce)
 costs per ounce = commission for a complete trade + spread = 0.56 + 0.16 = 0.72
 then: round to 0.01 lots → check the rounding limit → cut by Max leverage

Stop distance	Ounces (50 risk)	Lots sent	Real risk	Costs share of risk
2 points	18.4	0.18	48.96	26%
3 points	13.4	0.13	48.36	19%
5 points	8.7	0.09	51.48	13%
10 points	4.7	0.05	53.60	7%
25 points	1.9	0.02	51.44	3%

Tighter stops mean bigger positions and a larger share lost to costs. That is why chapter 8 recommends skipping stops closer than 3 points.

Position size

Default: Risk-based off the stop

Set: Risk-based off the stop

- WHAT IT DOES**
- **Risk-based:** the formula above. Every stop-out costs the same money on any instrument.
 - **Fixed quantity:** always the same number of units (ounces on gold).
 - **Fixed cash per trade:** always the same position value.

WHY THIS VALUE Only risk-based makes the loss recovery rules, the table's risk rows and the hard cap mean anything.

BASE risk per trade

Default: 50

Set: 50

WHAT IT DOES The money lost when the stop is hit, after commission and spread. Loss recovery (Rule A / B) works in multiples of this number.

WHY THIS VALUE 0.25% to 1% of the account is normal. 50 is 0.5% of 10,000. The 'Last trade risk' row shows what each trade really risked.

Fixed quantity / Fixed cash per trade

Default: 1 / 1000

Set: not used

WHAT IT DOES Only read in those two sizing modes. Ignored with risk-based sizing.

Round the size to the broker's lot step

Default: 0.01

Set: 0.01

WHAT IT DOES Rounds the size to what your broker accepts, so the backtest trades the sizes you really get. Normal rounding: 0.0828 → 0.08; 0.0850 and 0.0899 → 0.09. If rounding reaches zero the setup is skipped, not sent empty. 0 = off.

WHY THIS VALUE Your real risk is then a little above or below 50. That was always true at the broker; now the backtest shows it.

Never let rounding raise the risk by more than (%)

Default: 25

Set: 25

WHAT IT DOES If rounding **up** would push the real risk more than this % over your risk amount, the size is rounded **down** instead.

EXAMPLE 0.0066 lots would round up to 0.01, which is 52% more risk. Above the 25% limit, so it rounds down to 0 and the setup is skipped.

Max leverage (position value / equity)

Default: 30

Set: 30

WHAT IT DOES Caps the position at equity × this number. Since v7.1 it covers **all open trades together**: a stacked BOS trade only gets the room left, and is skipped when there is none. When it cuts a trade, the size is rounded down to the lot step and the table row 'Trades cut by leverage cap' counts it.

EXAMPLE Equity 10,000 × 30 = 300,000 of gold, about 0.69 lots at 4,340. Rule B asked for 1.5 lots on one of your trades; this cap cut it to 0.70.

WHY THIS VALUE Keep it at or **below** the leverage FxPro really gives you on gold, or FxPro may reject trades the backtest takes. Keep the Properties leverage (chapter 12) at least 3 times higher.

Loss recovery: how Rule A and Rule B work

Both rules share one number, **losses carried**. After every closed trade:

losses carried = losses carried - the trade's result (after commission and spread)
a loss adds to it, a profit takes off from it, it never goes below 0

Rule	Next trade risks	With your settings (base 50, R 3)
Off	always the base	50
Rule A	(losses carried + base) ÷ R multiple	(carried + 50) ÷ 3
Rule B	2 × losses carried, never less than the base	2 × carried, at least 50

When losses carried is 0, both go back to 50. A win that only pays off part of the carried losses keeps the ladder going from what is left.

Rule A: three stops, then a target

Risk	Result	Carried
50.00	stop -50.00	50.00
33.33	stop -33.33	83.33
44.44	stop -44.44	127.78
59.26	target +177.78	0

Run ends +50: every loss back plus one base. At 1:3 the risk after the first loss is **lower** than 50, because a win pays three times.

Rule B: three stops, then a target

Risk	Result	Carried
50	stop -50	50
100	stop -100	150
300	stop -300	450
900	target +2,700	0

Run ends +2,250, but needs 900 of risk. With the hard cap at 500 the 900 trade is blocked: the day stops and you restart at 50 tomorrow, 450 down.

Rule A: a partial win in the middle

Risk	Result	Carried
50.00	stop -50.00	50.00
33.33	stop -33.33	83.33
44.44	opposite signal +30.00	53.33
34.44	target +103.33	0

Rule B: early exits, like your trades 13 to 16

Risk	Result	Carried
50	opposite signal -20	20
50	opposite signal -15	35
70	stop -70	105
210	opposite signal +100	5
50	target +150	0

Why Rule B does not look like "doubling" in your List of Trades

It doubles the **total carried**, not the last trade. Opposite-signal exits lose less than the full risk, so the carried amount grows slowly. And once Rule B asks for more than Max leverage allows, the size is cut: on your trade 19 it asked for 1,607 of risk and the cap allowed 736.

Your trades 13 to 20, rebuilt from your List of Trades

#	Carried before	Rule B asked	Lots	How it closed	Result	Carried after
13	0	50	0.04	opposite signal	-22.27	22.27
14	22.27	50 (base)	0.03	opposite signal	-12.57	34.84
15	34.84	69.68	0.04	stop	-66.88	101.72
16	101.72	203.44	0.17	stop	-202.72	304.44
17	304.44	608.88	0.23	opposite signal	-307.19	611.63
18	611.63	1,223.26	0.64	opposite signal	-192.13	803.76
19	803.76	1,607.52	0.70 (cap)	stop	-736.75	1,540.51
20	1,540.51	3,081.02	0.64 (cap)	opposite signal	+795.14	745.37

Stops lost almost exactly what was asked (trades 15 and 16; the gap is 0.01-lot rounding). Early exits lost less. Trades 19 and 20 were cut by Max leverage 30. With the hard cap at 500, trading would have stopped for the day before trade 17.

Loss-recovery sizing

Default: Off

Set: Off (recommended)

WHAT IT DOES Off, Rule A or Rule B, as explained above.

WHY THIS VALUE Both rules grow the position after losses, the fastest known way to empty an account. Rule B from a 50 base: 50, 100, 300, 900, 2,700, 8,100. After five full losses in a row the next trade would risk 81% of a 10,000 account, and at 1:3 you only need to win one trade in four to break even, so long losing streaks are normal. If you use a rule, Rule A is far gentler at 1:3.

HARD CAP on risk per trade / when the cap is reached

Default: 500 / Stop for the day

Set: 500 / Stop for the day

WHAT IT DOES	The most the recovery ladder may ask for on one trade. If the next risk would be higher: • Clamp to the cap and carry on: risk the cap and keep trading. The ladder can no longer recover everything. • Stop for the rest of the day: no new trades today; tomorrow losses carried is cleared and it restarts at the base, from the first candle of the day (fixed in v7.5). • Stop permanently: no new trades until you reload the strategy.
EXAMPLE	Rule B with the cap at 500: 50, 100, 300, then 900 is over 500, so trading stops for the day. The worst day costs 450, 4.5% of the account.
WHY THIS VALUE	Set it to the most you accept losing on one trade, about 5% of the balance. At 100,000 there is effectively no cap.

Groups 22 and 30 - Webhook message, TheConnector

What the strategy attaches to each order so your bridge can place it at FxPro, and the settings for TheConnector. None of these settings change the backtest.

Attach a webhook message to every order

Default: OFF

Set: ON for live trading

WHAT IT DOES Fills in the message of every order. One TradingView alert (condition: this strategy, **Order fills**, message `{{strategy.order.alert_message}}`) then sends the right message for every entry and exit.

Message format

Default: JSON

Set: TheConnector

WHAT IT DOES Four formats. For the long trade in chapter 3:

TheConnector	<code>{"action":"buy","symbol":"XAUUSD","volume":0.05,"sl_price":4299.000,"tp_price":4341.880,"tag":"smcgold-k3f9"}</code>
JSON	<code>{"id":"","action":"buy","side":"long","symbol":"XAUUSD","qty":0.05,"entry":4309.000,"sl":4299.000,"tp":4341.880,"trade":"Lk3f9"}</code>
PineConnector	<code>ID,buy,XAUUSD,sl=4299.000,tp=4341.880,volume=0.05</code>
Plain text	<code>buy XAUUSD side=long qty=0.05 entry=4309.000 sl=4299.000 tp=4341.880 trade=Lk3f9</code>

An exit sends `closeLong` / `closeShort` (TheConnector, PineConnector) or `close` (JSON, plain). PineConnector's close hits every long / short on the symbol, so with stacked trades use TheConnector.

WHY THIS VALUE TheConnector is your bridge. Its format sends the exact lot (`volume`), the stop and target as exact prices and a tag, and never `closeAll`, which would close everything on every symbol.

Minimum lot your broker accepts

Default: 0 (no check)

Set: 0.01

WHAT IT DOES A setup whose size comes out below this is skipped instead of sent. It is counted in the table row 'Skipped - stop / min lot / costs'.

EXAMPLE 50 risk on a 300-point stop is 0.0017 lots. FxPro would reject it; with 0.01 set, the strategy never sends it.

Quantity to send

Default: Lots

Set: Lots

WHAT IT DOES TradingView sizes gold in ounces. **Lots** divides by 100 before sending, so 5 ounces is sent as 0.05. **Raw units** sends 5, which an MT5 bridge reads as 5 lots.

WHY THIS VALUE The most dangerous setting in the file: the wrong choice makes every trade 100 times too big. MT4/MT5 bridges want Lots. Check the first live trade's size in MT5.

License ID / account tag

Default: blank

Set: blank (TheConnector)

WHAT IT DOES TheConnector: leave it blank and put your access key at the end of the webhook URL, as TheConnector recommends. If you type it here instead, every message carries it in `accessKey`. PineConnector puts its licence ID first in every command; JSON copies it into `id`.

Symbol to send (group 30)

Default: blank = the chart's XAUUSD

Set: your MT5 gold symbol

WHAT IT DOES The symbol name at your broker, if it differs from the chart. Check FxPro's MT5 Market Watch and type it exactly. Used by every message format.

TheConnector tag (group 30)

Default: smcgold

Set: smcgold

WHAT IT DOES Sent in every entry and exit. TheConnector stamps it into the position's comment and then closes only positions carrying it, so manual trades and other strategies on the account are never touched. Letters, digits, `-` and `_` only. Needs robot 0.0.21 or later.

Every trade has its own tag: your text, a dash and the trade's 4-character code, made from the signal candle's time (v7.2), e.g. `smcgold-k3f9`, `smcgold-k3g1`. The same candle always gives the same code, even after TradingView restarts the alert. A close only ever closes its own trade.

EXAMPLE A long from a CHOCH carries `smcgold-k3f9`, a long from the next BOS `smcgold-k3g1`. An opposite CHOCH sends two closes, one per tag.

WHY THIS VALUE Keep it to **7 characters or less**: with the dash and the 4-character code it must fit TheConnector's 12 (a longer text is cut). Never leave it blank when trades can stack. Switch versions while flat: a trade opened by v7.0 or v7.1 carries another tag and v7.2 would not close it.

TheConnector stop / target fields (group 30)

Default: sl_price / tp_price

Set: sl_price / tp_price

WHAT IT DOES **sl_price / tp_price**: always read as exact prices, whatever the robot's Price mode is. **sl / tp**: the plain fields, whose unit follows the robot's Price mode, which must then be set to prices.

WHY THIS VALUE TheConnector needs one price unit per alert; mixing units sends the order with no stop and no target. This option can't mix them.

Never paste the sample message from TheConnector's dashboard

It is one fixed text - buy, risk 1, sl 20, tp 45. With this strategy's one alert, every fill - sells and exits too - would open another buy. The alert message must be only `{{strategy.order.alert_message}}`.

Group 23 - Commission

Your broker's charge per trade, so the size and the target account for it. This group feeds the strategy's own sizing and counters; TradingView's report needs the Properties tab as well (chapter 12).

Commission model

Default: Auto - per lot, contract size from the ticker

Set: Auto - per lot

- WHAT IT DOES**
- **Auto - per lot:** you enter the charge per lot, one side. The lot size is read from the ticker: 100 for gold, 5,000 for silver, 100,000 for forex pairs, 1 for crypto and indices (1 coin, 1 index unit), exactly as at FxPro.
 - **Per lot - I set the contract size:** the same, but you type the units per lot.
 - **Percent of trade value:** for crypto and shares.
 - **Fixed cash per order:** a flat fee per order.
 - **Off:** commission ignored.

WHY THIS VALUE The table row 'Commission model' shows what was detected, for example '28/lot x2, lot=100'. Check it on a new ticker.

Charge per LOT, ONE side

Default: 0

Set: yours for this ticker (28 on gold)

WHAT IT DOES The charge to open (the strategy doubles it for the close). It starts at 0, so nothing is charged until you type the figure for the ticker on the chart. Commission differs by market and account: open and close 0.01 lot and read the statement (0.28 there means 28 per lot). 28 per lot per side on gold is 0.28 per ounce per side, 0.56 per ounce for a complete trade.

WHY THIS VALUE The table row 'Commission model' is orange and reads '0 - type yours in group 23' until you do.

Units per lot / Percent / Fixed cash

Default: 100 / 0.05 / 3.50

Set: not used

WHAT IT DOES Only read by the matching commission model.

Push the target out to cover the commission

Default: ON

Set: ON

WHAT IT DOES Moves the target far enough that a win still nets the full R after costs. The push-out is costs per ounce $\times (R + 1)$: with your settings $0.72 \times 4 = 2.88$ points.

EXAMPLE Without it, on a 3-point stop at 1:1, a loss costs 50 but a win pays only about 34.

WHY THIS VALUE Without it the costs make every winner smaller than it should be.

Commission in both places: never counted twice

Set your commission here (28 on gold) **and** the table's Properties number in Properties (0.36 on gold). When Properties has a commission, the strategy uses TradingView's after-cost figures and does not subtract its own again. Properties changes only TradingView's report; the sizes, targets and messages are the same either way.

Group 24 - Safety

Every guard here is optional. Each one stops new trades; none of them stops an opposite-signal exit.

Cancel an unfilled order on ANY new signal

Default: ON

Set: ON

WHAT IT DOES When a new signal prints, a waiting order is pulled, even if the new signal does not arm a setup itself. OFF: the old order stays until something replaces it.

Cancel an unfilled order after N bars

Default: 0 (never)

Set: 0, or 30 to 60 on 1m

WHAT IT DOES A setup that has waited this many candles without filling is dropped. Counted in 'Cancelled - expired unfilled'.

Skip the setup if the stop is CLOSER than (price)

Default: 0 (off)

Set: 3.0

WHAT IT DOES Setups with a stop nearer than this are skipped and counted in 'Skipped - stop distance / min lot'. It is a gold number in price; on another ticker type that market's own value.

EXAMPLE At a 3-point stop costs are 19% of the risk; at 1 point they are 42%. The 'Costs last trade' row turns red above 25%.

WHY THIS VALUE Very tight stops mean huge positions where the spread and commission take most of the risk.

Skip the setup if the stop is FURTHER than (price)

Default: 0 (off)

Set: 0 (off)

WHAT IT DOES The other end: a very wide stop makes the size tiny and the target far away. Optional.

Max trades per day

Default: 0 (no limit)

Set: 0 or 10

WHAT IT DOES After this many entries in a day (midnight to midnight in the session timezone), no new trades until tomorrow.

Stop for the day after losing this much

Default: 0 (off)

Set: 150

WHAT IT DOES Adds up the day's closed results after costs. Once the day is down by this amount, no new trades until tomorrow.

EXAMPLE 150 = three base losses. The day ends before a bad run gets expensive.

Stop PERMANENTLY after an equity drawdown of this %

Default: 0 (off)

Set: 20

WHAT IT DOES Measured from the highest equity reached. Unlike the daily stop it never resets: no new trades until you reload the strategy.

Weekend: flatten before it / cutoff day and hour / Trade 24/7

Default: ON / Fri 21 / OFF

Set: ON / Fri 21 / OFF

WHAT IT DOES From the cutoff until the market reopens, any open trade is closed and nothing new is opened; Saturday and Sunday are blocked. 'Trade 24/7' ON treats weekends like any other day, on every ticker. For crypto, switch it on only on the crypto chart.

WHY THIS VALUE A weekend gap does not respect your stop: price can open far beyond it on Monday.

News master switch, groups 25 to 28

One switch that turns every news block on or off, then blackout windows around news, the broker's spread as a cost, stopping once you have made enough, and news windows that only work on the dates you choose.

Group 0 - News windows master switch (new in v7.0)

News windows ON (OFF = no news and no US-holiday blocks at all)

Default: ON

Set: ON, or OFF for no news blocks

WHAT IT DOES The very first setting in the panel. **ON**: group 25 windows, group 28 dates, and group 29 automatic US news and US holidays all work exactly as you set them. **OFF**: none of them blocks anything, whatever those groups say - trades are taken freely inside your session hours (06:00 to 23:00). The session hours, force-close, weekend cutoff and daily limits still apply.

WHY THIS VALUE Your news settings are kept while it is OFF, so ON restores them. The table row News windows active on reads MASTER SWITCH OFF. Re-create the alert after switching it.

Group 25 - News / blackout windows

When a window starts

Default: Close any open trade

Set: Close any open trade

WHAT IT DOES **Close any open trade**: flatten at market when a window begins. **Leave open trades alone**: the running trade keeps its stop and target; only new trades are blocked.

WHY THIS VALUE A news spike can jump straight through a stop and fill far worse than the price you set.

Window 1, 2, 3 - block trading / time

Default: all off

Set: on for big USD news

WHAT IT DOES Up to three windows, in hours and minutes, read in the session timezone. Inside a window no setup is armed, any waiting order is cancelled, and an open trade is handled by the setting above. A window may cross midnight (2330-0030). Windows only work on intraday charts.

EXAMPLE US CPI and NFP come out at 8:30 New York time: 18:00 IST in the US summer, 19:00 IST in the US winter. A window of 17:50-18:20 covers the summer release. FOMC decisions: 23:30 IST in summer, 00:30 IST in winter.

WHY THIS VALUE Switch a window on for the days that matter. Tick 'Read the group 25 window times in New York time' (group 29) and type 0825-0900 instead: it then follows US summer and winter time by itself.

Group 26 - Live-trading realism

Broker spread, in price

Default: 0 (not modelled)

Set: yours for this ticker (0.16 on gold)

WHAT IT DOES	Your broker's spread, in price (not ticks, not points). The strategy treats it as a cost like commission: the size shrinks so a stop-out still costs your risk, the target moves out so a win still nets full R, and the 'Paste into Properties' row includes half of it per side. Nothing sent to the broker changes.
EXAMPLE	Spreads differ by market and through the day, so type the one for the ticker on each chart. You measured 0.08 to 0.16 on FxPro gold. With 0.16, costs per ounce become $0.56 + 0.16 = 0.72$, and the Properties number becomes $0.72 \div 2 = 0.36$.
WHY THIS VALUE	TradingView fills the backtest at the chart price and never charges a spread. In the simulator, setting the spread shrank the backtest-versus-live gap from -6.05 to $+0.60$ per trade. Use the top of the range you see so the backtest errs on the careful side.

Group 27 - Profit target: stop new trades

New in v4.2. Once the net result of your **closed** trades reaches the target, the strategy takes no new trades. It never closes a running trade: the count only changes when a trade closes, and this strategy holds one trade at a time, so you are already flat.

Stop taking new trades once the profit target is reached

Default: OFF

Set: optional

WHAT IT DOES	Switches the feature on. The table row 'Profit target (made / target)' shows progress; it turns green with REACHED, and BLOCKED NOW reads 'profit target'.
--------------	--

Profit target, in account currency

Default: 500

Set: your choice

WHAT IT DOES	Net profit after commission and spread, the same figure as TradingView's Cumulative P&L once Properties commission is set.
--------------	--

Count the profit

Default: Total since the start date

Set: Each day, if you use it daily

WHAT IT DOES	• Total since the start date: everything closed from the start date. Once reached it stays stopped. To trade again, raise the target or move the date, then re-create the alert. • Each day: counts from zero every midnight in the session timezone. Reached means no more trades today; tomorrow it starts again. • Each week: the same, from zero every Monday.
EXAMPLE	Each day, target 200. Monday: $+120, -40, +150 = 230$, so trading stops for Monday. Tuesday starts at 0: $-50, -50, +250 = 150$, still under 200, so it keeps trading.

Start date (only for Total)

Default: 1 Jan 2000

Set: the day the live alert starts

WHAT IT DOES	Trades that close on or after this moment are counted. Only used by 'Total'.
WHY THIS VALUE	TradingView runs the whole chart history before it goes live, and with the 2000 default those backtest trades count. If the backtest already made more than the target, the live alert starts out stopped. For live trading with 'Total', set this to the day you switch the alert on. For a backtest, leave it at 2000.

Profit target and loss limit together

Each day with a 200 target and 'Stop for the day after losing' at 150 gives every day a ceiling and a floor. The profit target does not reset the Rule A / B ladder; it carries on when trading starts again.

Group 28 - News windows only on chosen dates

New in v5.0. It changes **when** the group 25 windows apply, not what they do. Off: the windows work every day, as before.

News windows work **ONLY** on the dates below

Default: OFF

Set: ON, with this month's news days

WHAT IT DOES ON: a news window only blocks trading on the dates you list. On every other date it does nothing, even though it is switched on.

The date that counts is the date the window **starts** on, in the session timezone. A 2325-0015 window for FOMC on the 17th needs only 17 in the list; it still runs past midnight.

EXAMPLE CPI on the 12th and NFP on the 3rd. Window 1: 1750-1820. Dates: 3, 12. On the 3rd and 12th no trading 17:50 to 18:20; on every other day the window does nothing.

WHY THIS VALUE Big news is on a few days a month. Blocking the same hours every day throws away good trading hours for nothing.

Dates (day of the month)

Default: empty

Set: for example 3, 12, 17

WHAT IT DOES Days separated by commas or spaces; ranges work. 3, 12, 28 or 12-14 or 3 12 17 28 or 12 - 14, 20. Days 1 to 31 only; anything else is ignored.

The table row 'News windows active on' shows what was read, e.g. '3, 12, 28 of Oct 2026'. ON with nothing valid shows NO VALID DATES in red, and the windows then block nothing.

These dates are for

Default: This month only

Set: This month only

- WHAT IT DOES**
- **This month only:** the dates apply to the current calendar month. Earlier months in the backtest are not blocked on them. When a new month starts, type the new dates and re-create the alert; if you forget, the windows stop working until you do.
 - **Every month:** the same day numbers in every month, e.g. the 12th of each month. Useful in a backtest.

Every month: new dates, new alert

Look up the month's big USD releases in an economic calendar, type the dates (IST), then delete the alert and create it again. An alert keeps the settings it was created with.

Group 29 - Automatic US news, US clock, US holidays

The strategy cannot read an economic calendar, but it can work out from the date alone every US release that follows a fixed rule, on the New York clock, with US summer and winter time handled for you.

Automatic US news windows (dates worked out by rule)

Default: OFF

Set: ON

WHAT IT DOES Switches on the four releases below. Around each one the strategy behaves exactly as in a group 25 news window: no new trades, any waiting order cancelled, an open trade closed or left alone as 'When a window starts' says.

The table row 'US news (auto) - next' shows the next release it worked out, in your session time.

WHY THIS VALUE The big regular US releases move gold hard in seconds. These four never need typing again.

NFP jobs report - 08:30 New York

Default: ON

Set: ON

WHAT IT DOES The Bureau of Labor Statistics' own rule: the third Friday after the week that contains the 12th of the previous month. Usually the first Friday, not always. A January date on the 1st to 3rd moves a week later; a date on a US holiday moves to the day before.

EXAMPLE Worked out: Fri 2 Oct 2026 18:00 IST, Fri 6 Nov 19:00 IST (US winter time from 1 Nov), Fri 4 Dec 19:00, Fri 8 Jan 2027 19:00 (not the 1st: January rule). Checked against 30 real release dates: all correct.

Weekly jobless claims - every Thursday 08:30 New York

Default: ON

Set: ON

WHAT IT DOES Every Thursday. When Thursday is a US holiday, it comes out on the Wednesday before, and so does the window.

EXAMPLE Thanksgiving week 2026: Wednesday 25 November.

WHY THIS VALUE Smaller than NFP, but it hits every week. Switch it off if you would rather trade Thursday evenings.

ISM Manufacturing PMI (1st working day) / ISM Services PMI (3rd working day) - 10:00 New York

Default: ON / ON

Set: ON / ON

WHAT IT DOES Working days skip weekends and US holidays. In January ISM publishes one working day later, and the rule follows that.

EXAMPLE October 2026: Manufacturing Thu 1 Oct, Services Mon 5 Oct, both 19:30 IST. January 2027: Tue 5 and Thu 7 Jan.

Block from minutes BEFORE / until minutes AFTER the release

Default: 10 / 20

Set: 10 / 20

WHAT IT DOES The window around each release. With 10 / 20 an 08:30 New York release blocks 08:20 to 08:50 New York time, which is 17:50 to 18:20 in India in US summer.

US clock (summer / winter time)

Default: Auto

Set: Auto

WHAT IT DOES The clock every New York time is read on. **Auto** follows US daylight saving: clocks go forward on the second Sunday of March and back on the first Sunday of November (in 2026: 8 March and 1 November). **Always summer / Always winter** pin it, only as an override.

New York	US summer (EDT)	US winter (EST)
08:30	18:00 IST	19:00 IST
10:00	19:30 IST	20:30 IST
14:00 (FOMC)	23:30 IST	00:30 IST

WHY THIS VALUE India never changes its clocks, the US does twice a year. Auto means you never move a window by hand again. The table row 'US clock' shows the one in use and what 08:30 New York is today.

Read the group 25 window times in New York time

Default: OFF

Set: ON

WHAT IT DOES ON: your own group 25 windows are read on the US clock too, so you type them the way the US calendar gives them and they follow summer and winter time. The group 28 dates are still read on your own calendar.

EXAMPLE CPI: window 0825-0900, dates in group 28. FOMC: 1355-1430 on the decision day.

WHY THIS VALUE Do not start a window inside gold's daily break (about 17:00 to 18:00 New York): the strategy only acts at candle closes, so it would see that window one candle after the reopen.

Trade on US market holidays

Default: ON

Set: OFF

WHAT IT DOES OFF: no trading from 00:00 to 24:00 New York time on the ten US market holidays, each worked out by rule every year: New Year, Martin Luther King Day, Presidents' Day, Good Friday, Memorial Day, Juneteenth, Independence Day, Labor Day, Thanksgiving, Christmas. A holiday on a Saturday moves to the Friday, on a Sunday to the Monday.

EXAMPLE 2026: 1 Jan, 19 Jan, 16 Feb, 3 Apr, 25 May, 19 Jun, 3 Jul, 7 Sep, 26 Nov, 25 Dec. Thanksgiving is blocked 10:30 IST Thu to 10:30 IST Fri (US winter time).

WHY THIS VALUE Gold still trades on most of these days, but thinly, with wide spreads and an early close.

What it cannot know

CPI, PPI, retail sales and FOMC have no fixed rule. Put them in group 25 (times) and group 28 (dates) each month. A US government shutdown delays even the regular releases; if that happens, put the real dates in group 28.

Which signals become trades

How each CHOCH / BOS is turned into a rule 1 or rule 2 setup, the extra trade for every same-side BOS (v7.1), every reason a signal is not traded, the v7.0 rule 2 fix, and the signal audit labels that show all of it on your chart.

The rule choice, per signal

Rules ticked	Higher timeframe agrees	Disagrees or undecided
Rule 1 only	Rule 1 (pullback %)	Rule 1 (pullback %) - the higher timeframe is not asked at all
Rule 2 only	Rule 2 (broken pivot)	Skipped
Rule 1 + 2	Rule 2 (broken pivot)	Rule 1 (pullback %)

"Take trades on" decides which signals count: CHOCH only, BOS only, or both. "Agrees" is read from the last **closed** higher-timeframe candle (15m on a 1m chart), so it never repaints. A 15m candle that is still forming can look different on the 15m chart; the strategy only uses it once it has closed.

Fixed in v7.0: rule 2 keeps the bracket it was armed with

Rule 2's entry is fixed at the broken pivot, but up to v6.1 its stop kept following the live CHOCH* level in Continuous mode. Example, CHOCH only, long: rule 2 arms a buy at 4310 with the stop under the swing low at 4302. Price runs up and makes a BOS at 4325 (not traded in CHOCH only), and the live level moves up to 4314. The stop followed it, **above** the 4310 entry, and the setup was cancelled without a word. When price came back to 4310, no trade. In the simulator this killed between about 1 in 12 and 1 in 4 rule-2 setups. Now rule 2 keeps the stop it was armed with. Rule 1 is unchanged.

Extra trades on BOS (new in v7.1)

Take trades on	What a BOS the same way as your open trades does
CHOCH only	Nothing, as before: a BOS is not a signal here. One trade at a time, exactly the trades of v7.0.
CHOCH and BOS	The CHOCH trade stays open and the BOS gets a trade of its own: rule 1 or rule 2 by the higher timeframe, its own entry, stop and target, the full risk. Every further BOS the same way adds one more.
BOS only	The same: every new BOS the same way adds another trade.

- **Each trade ends at its own stop or target.** One trade stopping out does not touch the others.
- **An opposite CHOCH closes every open trade** at the next candle open, in all three modes, BOS only included ("close and reverse" ON, the default). If you trade that CHOCH, the reverse setup is armed on the same candle, placed once the old trades are closed, and fills when price comes back to its entry: in the simulator 91% armed and 61% of those filled. In BOS only it opens nothing; the next BOS the other way does.
- The 02:00 force-close, the weekend cutoff and a news window set to close trades also close every trade.
- Only one order waits at a time, and while trades are open it is always the same way as them.

Example, CHOCH and BOS, long, R 3

CHOCH up: rule 1 buys 4310, stop 4302, target 4334. Filled. BOS up at 4325 and the 15m agrees: rule 2 buys the broken pivot 4325, stop 4316, target 4352. Filled, two trades open. Price reaches 4334: trade 1 takes its target, trade 2 stays. CHOCH down at 4331: trade 2 is closed at the next open and a short setup is armed.

Every stacked trade risks your full base risk

Four trades open at 50 each is 200 at risk at the same moment, and one sharp reversal can stop them all. On your gold settings the simulator had up to 7 open at once. What protects you: Max leverage now covers all open trades together, Max trades per day counts every trade, and the daily loss limit counts the total. Loss recovery (Rule A / B) raises every new trade after losses, which grows very fast with several trades: keep it Off or the hard cap low. Compare CHOCH only with CHOCH and BOS in your own backtest before going live.

A signal makes no setup when (label: SKIP)

- Trading is blocked: news window, US holiday, weekend, daily loss or trade limit, risk cap, profit target, drawdown stop.
- It is outside the session hours. It is not kept for later.
- You are already in a trade the same way and the signal is a CHOCH (a same-side BOS adds a trade, below), or you are in the opposite trade with "close and reverse" off.
- Rule 2 only, and the higher timeframe does not agree.
- There is no structure level on the other side for the stop.

An armed setup ends without a trade when (label: CANCELLED)

- Price does not come back to the entry before the next signal replaces it, the trend flips against it, the session ends, a news window starts or the weekend cutoff comes.
- Its stop is closer or further than your group 24 limits. With your 3.0 minimum on gold this is the biggest single reason: in the simulator it removed about 1 in 3 armed CHOCH setups.
- The size is below your broker's minimum lot, or zero.

Signal audit labels (group 20)

Default: OFF

Set: ON while checking, OFF for live

WHAT IT DOES Every signal you trade on gets a label. First line: the signal and the higher-timeframe trend the rule choice used (up / dn / - ; 'off' when rule 2 is off). Then what happened. Since v7.3 the labels are solid and dark with white text: dark blue = armed, dark green = filled, dark orange = cancelled, dark grey = skipped. Their size is 'Audit label size' in group 31 (Small, Normal, Large or Huge; default Large).

CHOCH up HTF up
R2 ARMED
FILLED

The higher timeframe agreed, rule 2 armed at the broken pivot, and the order filled.

BOS up HTF up
R2 ARMED
FILLED

In a long already: this BOS got its own trade (v7.1). The long stays open.

CHOCH dn HTF up
R1 ARMED
CANCELLED - stop too close / too far

Rule 1 armed (higher timeframe against), then refused by your group 24 stop limits.

WHY THIS VALUE

It changes no trade. TradingView keeps at most 500 labels, shared with the structure labels, so on a long history the oldest disappear. If a label ever fails to explain a missing trade, screenshot it with the date and time.

Checked in simulation: every combination

Four two-week markets, your gold settings (pullback 25, R 3, buffer 1.0, minimum stop 3.0, spread 0.16), news switch ON with a window, the automatic US news and US holidays. Every signal was decided again by a separate checker written from the rule table above: **0 differences** in all 18 runs, with the news switch on and off.

Take trades on	Rules	Signals	R1 armed	R2 armed	Filled v7.0	Filled v6.1
CHOCH only	1 only	810	523	0	271	271
CHOCH only	2 only	810	0	230	138	125
CHOCH only	1 + 2	810	293	230	282	263
BOS only	1 only	1,948	823	0	238	238
BOS only	2 only	1,948	0	447	144	137
BOS only	1 + 2	1,948	313	445	240	233
CHOCH and BOS	1 only	2,758	1,274	0	463	463
CHOCH and BOS	2 only	2,758	0	648	266	249
CHOCH and BOS	1 + 2	2,758	572	654	490	466

Rule 1 alone is unchanged. Wherever rule 2 is used, v7.0 fills more: those are the setups v6.1 was silently cancelling. Signals minus armed are the skips listed above (mostly outside hours and already in a trade); armed minus filled are the cancels (mostly the 3.0 minimum stop and a new signal arriving first).

v7.1: the same markets with stacked BOS trades

A second broker copy that holds several trades checked every bar: an opposite CHOCH always leaves no trade open, the trades are always one way, every message carries its own trade's tag, and the leverage cap covers them all. **0 faults** in all 18 runs, and in 300 random combinations of every setting (7,396 trades, up to 12 open at once). CHOCH only is identical to v7.0 in 83 of 83.

Take trades on	Rules	Trades v7.0	Trades v7.1	Stacked	Most open
CHOCH only	1 only	271	271	0	1
CHOCH only	2 only	138	138	0	1
CHOCH only	1 + 2	282	282	0	1
BOS only	1 only	238	406	157	6
BOS only	2 only	144	290	133	7
BOS only	1 + 2	240	452	195	7
CHOCH and BOS	1 only	463	679	221	7
CHOCH and BOS	2 only	266	427	177	7
CHOCH and BOS	1 + 2	490	742	267	7

Stacked = trades filled while another was already open. The simulated markets are random, so their profit says nothing about real gold: judge stacking on your own backtest.

Fixed in v7.2: each stop or target closes its own trade

v7.1 left TradingView on its default "first in, first out" rule: whichever stacked trade hit its stop or target, the **oldest** trade was closed. With BOS on that was about 1 exit in 7 to 1 in 9 in the simulator, and it cut trades in two in the List of Trades. Live, FxPro closes the right trade by its tag, so the backtest did not match. v7.2 closes the trade each exit belongs to. CHOCH only was never affected.

Your FxPro contract sizes

The strategy reads these from the ticker, and all of them match what you checked at FxPro. Lot step and minimum lot (0.01) are in lots, so they fit every market as they are. Commission and spread are **yours to type** for each ticker. The strategy turns a charge of C per lot per side into a cost per unit with the lot size:

Market	1 lot	0.01 lot	Commission per unit, round trip	At C = 28
XAUUSD gold	100 oz	1 oz	$2 \times C \div 100$	0.56
XAGUSD silver	5,000 oz	50 oz	$2 \times C \div 5,000$	0.0112
EURUSD, GBPUSD, AUDUSD ...	100,000	1,000 units	$2 \times C \div 100,000$	0.00056 = 5.6 pips
BTCUSD, ETHUSD	1 coin	0.01 coin	$2 \times C$	56
US30, US500	1 unit	0.01 unit	$2 \times C$	56 points

Plus the spread you type in group 26. The table row 'Paste into Properties cash/contract' gives the exact Properties number. Pairs quoted in another currency (USDJPY) are converted for you.

Setting up a new ticker

An alert keeps the settings it was created with, so each ticker gets **its own chart and its own alert**.

- 1 Open the ticker on its own 1-minute chart and add the strategy. Check the table row **Ticker - type / 1 lot / symbol sent**.
- 2 Distances: type price values for this market into group 20 (stop buffer) and group 24 (closer / further limits). A gold 3.0 minimum stop is 30,000 pips on EURUSD.
- 3 Type this ticker's commission per lot (group 23) and spread (group 26). Group 21: Max leverage no higher than FxPro gives on this market, because crypto and indices often get far less than gold.
- 4 Crypto: switch on 'Trade 24/7' (group 24) on the crypto chart if you want Saturdays and Sundays. Symbol: the broker's name in group 30 if it differs.
- 5 Properties → Commission → Cash per contract: paste this ticker's number from the table.
- 6 Run the backtest. Check 'Costs last trade' (red above 25%) and 'Skipped'. If most setups are skipped, 1-minute stops are too small for this market's costs.
- 7 Create the alert on this chart: Order fills only, message only `{{strategy.order.alert_message}}`, webhook URL ending in your access key. Check the first live trade's lots in MT5.

Finding your commission and spread for a ticker

- **Commission:** open 0.01 lot and close it, then read the statement. The charge per lot per side is $100 \times$ one side of that trade: 0.28 on the statement means 28 per lot.
- **Spread:** the spread column in MT5's Market Watch at the hours you trade. Use the top of the range you see.

Group 31 - Stacked BOS trades + audit labels (new in v7.3)

Max trades open at the same time

Default: 0 = no limit

Set: 0, or 2 to 3 to cap the risk

WHAT IT DOES Caps how many trades can be open at once; the CHOCH trade counts too. At the limit a further BOS the same way adds nothing (label: SKIP - max trades open); when a trade ends, the next BOS can add again. 1 = never stack. It never stops a close or a reversal.

EXAMPLE Limit 3: the CHOCH trade and 2 BOS trades are open, so the next BOS is skipped. One takes its target, and the BOS after that adds a trade again.

Audit label size

Default: Large

Set: Large, or Normal if they overlap

WHAT IT DOES Text size of the signal audit labels (Small, Normal, Large, Huge); the dark box grows with it. Switch the labels on in group 20.

Group 32 - Stop management (new in v7.4)

Both switches are OFF by default: the stop then stays where it was placed, as before. 1R is the distance from your entry to your first stop. **Break-even** is your entry plus commission and spread, so a trade stopped there nets zero (on gold: entry + 0.72).

Buy 4310, stop 4302 (1R = 8), R 3	Step stop	Break-even only
Price reaches 4318 (1R)	Stop to break-even, 4310.72	Only if a candle CLOSES above 4318: stop to 4310.72
Price reaches 4326 (2R)	Stop to 1R, 4318	Stays at 4310.72
Price reaches 4334 (3R)	Target, the trade closes	Target, the trade closes

Step stop - at every 1R, move the stop up one step

Default: OFF

Set: OFF, or ON to lock profit in steps

WHAT IT DOES When a trade REACHES 1R (the candle high for a buy, low for a sell; on the entry candle only its close), the stop moves to break-even at that candle close. At 2R to 1R, at 3R to 2R, always one step behind, until the target closes the trade. With R 5 the steps go on to 4R; with R 1 or less nothing changes. If both switches are ON, this one is used.

Break-even only - once a candle CLOSES beyond 1R

Default: OFF

Set: OFF, or ON for one safe move

WHAT IT DOES When a candle CLOSES beyond 1R, the stop moves to break-even and never moves again. A wick through 1R that closes back does nothing. Ignored while Step stop is ON.

Real time, CHOC, and FxPro

- The stop **moves** at a candle close; it is **hit** in real time like any stop, and that trade's close goes to FxPro at once. FxPro keeps the original stop as a safety net and closes at market, so a fast market can close a little worse than the stop.
- An **opposite CHOC** still closes the trade at the next candle open, wherever its stop is. Example: 2R reached, stop at 1R, then a CHOC the other way: the trade closes on the CHOC.
- Each stacked trade has its own steps. The table row "Exit - moved stop (BE / step)" counts the exits and the moves.

The Properties tab

Settings (gear icon) → Properties. These fields belong to TradingView, not to the script, and they decide whether the backtest and live behave the way your Inputs say.

Field	Set to	Why
Initial capital	Your real FxPro balance, USD	The leverage cap (equity × 30) and the drawdown stop are worked out from it. The size is not; it comes from your risk amount.
Default order size	Leave (1, Quantity)	Never used: the strategy always sends its own size.
Pyramiding	100	The most trades open at once (v7.1). At 0 or 1 TradingView refuses every extra BOS trade without a word. For your own limit use Max trades open (group 31) instead.
Bar detalization	Default	A lower-timeframe option (Premium plans) makes backtest fills more exact inside a candle. It does not change live trading.
Script execution	On bar close ONLY	The one that matters most. With "On realtime bar tick" ticked, live trading acts on unfinished candles, e.g. a CHOC that disappears by the close; the backtest never does. Leave "After order is filled" unticked too.
Commission	Cash per contract, 0.36	Copy the table's 'Paste into Properties cash/contract' row. On your gold chart 1 contract = 1 ounce. Percent is wrong for a per-lot charge; fixed USD per order would charge 0.01 lots the same as 1 lot.
Long / Short leverage	100x	Explained below. 30x caused your "Margin call" exits; 1x makes TradingView refuse almost every order.
Slippage	0	Makes stops and market exits worse by that many ticks (OANDA gold: 200 ticks = 0.20) where the sizing cannot see it, so a stop-out loses more than your risk. Use the spread setting instead.
Limit order execution	Requested price	The entry fills when price touches your level, which is what the strategy and the alert expect.
Order execution delay	One tick	An order fills on the next tick after it is placed: the normal behaviour.

Margin calls: what they are, and why 100x

With leverage you put up only a deposit, the margin: at 30x it is 1/30 of the trade's value. If the account can no longer cover it, part of the trade is force-closed: a margin call. TradingView simulates this from the Properties leverage.

Step	Properties leverage 30x	Properties leverage 100x
Rule B trade, cut by Max leverage 30	300,000 of gold (0.75 lots at 4,000)	same
Deposit TradingView requires	$300,000 \div 30 = 10,000$: the whole account	$300,000 \div 100 = 3,000$
Price moves 1.00 against you	account 9,925, deposit about 10,000: margin call , part of the trade force-closed	nothing happens; a margin call would need a 7,000 loss

That is how one trade became a 75.8 and a 0.2 in your List of Trades. A real broker only closes positions at its stop-out level, far below the full deposit. Keep Properties leverage at least **3 times** Max leverage; the row 'Margin calls (Properties)' must read 0.

Too little leverage: orders thrown away without a word

At **1x** a 50 risk on a 3-point stop asks for about 16 oz: 64,000 of gold on a 10,000 account. TradingView cannot hold it and throws the order away. No error, no arrow, nothing in the List of Trades, and **no alert**, so FxPro gets nothing either.

The signal and its ARMED label stay on the chart. Same market and settings, trades entered, on a backtester that copies TradingView's order rules:

Properties leverage	CHOCH only	CHOCH and BOS
None (the file's own), 100x, 30x or 10x	67	198
5x	66	187
2x	0	40
1x	0	8

Margin in % works the other way round

If your Properties show "Margin for long / short positions" in %, type 1 (= 100x), never 100 (= 1x). Properties belong to each copy of the strategy on the chart, not to the code: a copy added fresh has its own. Since v7.6 the table row '- REFUSED by TradingView' turns red when orders are thrown away.

The counter table

Thirty-eight rows on the chart. Each counts exactly one thing, from the first candle of the chart to the last.

Signals and trades

Row	What it shows
CHOCH signals on the chart	Every main-tier CHOCH, or 'off' if you do not trade CHOCH.
BOS signals on the chart	The same for BOS.
Setups armed	Signals that passed every rule and got a stop, target and entry level.
Trades entered	Real entries, one per trade, ended or not. '312 (3 still open)': 312 in total, 309 ended, 3 running now.
- TradingView List of Trades	TradingView's own count, e.g. '309 closed + 3 open' (v7.2). Adds up to Trades entered; orange when not (margin calls).
- REFUSED by TradingView	Setups whose order TradingView did not fill although the price went through it (v7.6): Properties leverage too low or Pyramiding too small. Must be 0; red if not (chapter 12).
- by ENTRY RULE 1 / RULE 2	Entries at the pullback level / at the broken pivot.
Setups cancelled, never filled	Orders pulled before they filled. '(+1 waiting)' when an order is resting.

Exits

Row	What it shows
Exit - target / stop	Bracket exits.
Exit - moved stop (BE / step)	Ended at a stop group 32 had moved, then the number of stop moves and the switch in use. 'off' while both switches are OFF (v7.4).
Exit - opposite signal	Closed by a reversal signal.
Exit - 02:00 flat / weekend	Closed by the force-close hour or the weekend cutoff.
Exit - news window / holiday	Closed because a blackout window, an automatic US release window or a US holiday started.
Margin calls (Properties)	Slices TradingView force-closed. Must be 0; red if not (chapter 12).

Filters and settings in use

Row	What it shows
Trades cut by leverage cap	Trades entered at a size the Max leverage cap cut down.
Skipped - stop distance / min lot	Setups refused by the stop filters or the minimum lot.
Cancelled - expired unfilled	Orders dropped by the N-bar expiry.
ENTRY rules in use (1 / 2)	'1 + 2 (dynamic)', '1 only', '2 only' or 'NONE' in red.
RULE 2 higher timeframe	15m, 1h, 4h... or why Rule 2 is off.
LOSS RECOVERY (A / B)	'off', 'A - recover + base' or 'B - double the losses'. Not the same thing as the entry rules.

Risk and costs

Row	What it shows
Losses carried	What the recovery ladder still owes.
Risk NEXT trade	What the next trade will risk. Orange when the ladder raised it.
Risk cap hit / HALT	Times the hard cap was reached; HALTED when it is stopping trades now.
Last trade risk	What the last trade really risked, costs included, and its size in lots.
Costs last trade	Commission plus spread on the last trade, and its share of the risk. Red above 25%.
Costs paid total (comm + spread)	All costs across the backtest.
Commission model	What is charged and the lot size detected, e.g. '28/lot x2, lot=100'. Orange '0 - type yours in group 23' until you type a charge.
Paste into Properties cash/contract	The number for Properties → Commission → Cash per contract (0.36 for you).

Status

Row	What it shows
Time filters	'on', or 'off (daily+)' when Auto has turned them off.
Profit target (made / target)	e.g. '312.5 / 500 total'. Green with REACHED once hit; 'off' when unused.
News windows active on	'every day', or the dates read from group 28, e.g. '3, 12, 28 of Oct 2026'. NO VALID DATES in red if nothing could be read.
US news (auto) - next	The next release group 29 worked out, e.g. 'NFP Fri 02 Oct 18:00' in your session time.
US clock	Summer or winter time, auto or forced, and what 08:30 New York is today, e.g. 'summer EDT (auto) 08:30 NY = 18:00'.
US holidays	'trading normally' or 'NO trading', and the next US holiday, or TODAY.
Ticker - type / 1 lot / symbol sent	e.g. 'Gold 1 lot = 100 sends XAUUSD': the market type, units in one lot, and the symbol the webhook sends.
BLOCKED NOW	What is stopping new trades now: drawdown, US holiday, news window, weekend, daily limit, risk cap, profit target, disabled, or '-'.

Three sums that must always add up

- Setups armed = Trades entered + Setups cancelled + (1 if an order is waiting)
- Trades entered = by RULE 1 + by RULE 2
- Closed trades in the List of Trades = the six Exit rows + Margin calls

If one of these does not add up on your chart, something is wrong: tell me which.

Comparing with the Strategy Tester

- **Total trades** in the Overview counts only trades that have ended. A trade still open at the right edge is not in it.
- The **List of Trades** shows each trade on two lines, entry and exit, under one number (#). The chart marks each trade twice too.
- **CHOCH / BOS signals** are signals, not trades: many never become one. The audit labels show why.

Automation

One alert drives everything: an order fills in TradingView, the alert fires, the webhook reaches your bridge, and the bridge trades at FxPro. TradingView runs the alert on its own servers, so your computer can be off; the bridge must run all the time.

Setting up the alert

- 1 Inputs, group 22: switch on "Attach a webhook message to every order". Message format: TheConnector. Quantity to send: Lots. Minimum lot: 0.01. Group 30: your MT5 gold symbol, tag smcgold, sl_price / tp_price.
- 2 Check the Properties tab (chapter 12). Click OK.
- 3 On the chart: Alerts → Create alert. Condition: **SMC Structure Strategy**, then **Order fills**.
- 4 Message box: `{{strategy.order.alert_message}}` and nothing else.
- 5 Notifications: tick Webhook URL. For TheConnector: `https://webhook.theconnector.fr/YOUR_ACCESS_KEY`. Webhooks need a paid TradingView plan.
- 6 Save. This single alert covers every buy, sell and close.

Every time you change a setting

Delete the alert and create it again. An alert keeps a copy of the settings it was created with; changing Inputs or Properties later does not reach it.

What the broker sees, and what it does not

- A **buy** or **sell** with size, stop and target, at the moment TradingView fills the entry. FxPro enters **at market**, a second or two later.
- A **close** when the strategy exits for any reason other than its own stop or target.
- **Never** the waiting order. The limit lives inside TradingView; cancelling it sends nothing because there is nothing at the broker to cancel.
- Moving the stop or target of a running trade: never happens. The bracket is fixed at entry, the same in TradingView and at FxPro.

How close live gets to the backtest

The **decisions** are the same live and in the backtest: same signals, same rule choice, same timing, same bracket, as long as Script execution is "On bar close". What can still differ is the **price**:

1. **Spread**, the biggest. Covered by group 26.
2. **Entry at market after the fill**. FxPro buys a second or two after TradingView's limit fills, usually a little worse. No setting removes this.
3. **Different feeds**. The chart is OANDA; the broker is FxPro. Levels can differ by a few cents.

With the spread set, the simulator put the backtest within about 1 per trade of simulated live, slightly on the careful side. Compare your first 30 to 50 demo trades with the List of Trades to get your own number.

Keeping it running

- Alerts can stop, for example after a "Calculation error". A stopped alert trades nothing and warns no one. Check it daily.
- Check the first live trade's size in MT5 before you leave it alone.
- On the MQL5 VPS: glance at its Journal and at TheConnector's dashboard once a day, and keep Algo Trading off on the laptop.

Running 24/7 without your laptop: TheConnector on an MQL5 VPS

The strategy and its alert already run on TradingView's servers, and TheConnector's webhook receiver runs in its cloud. The one piece on your laptop is **MT5 with TheConnector's EA**, which picks up each command and places it at FxPro. An MQL5 VPS is MetaQuotes' own server running a copy of your MT5 around the clock, next to FxPro's London servers. **Cost:** \$15 a month, \$14 for three months, \$12.80 a month for a year, per trading account. It runs Expert Advisors only (no DLLs), and you see its logs, not its screen.

A. Prepare MT5 on the laptop

- 1 Log in to the FxPro account with the **main** (trading) password and tick "Save password". Tools → Options → Community: log in with your mql5.com account.
- 2 Tools → Options → Expert Advisors: tick "Allow algorithmic trading" and "Allow WebRequest for listed URL", then add TheConnector's address exactly as its MT5 guide gives it. Leave DLL imports off.
- 3 Close every chart but one (e.g. XAUUSD M1). Keep only your symbols in Market Watch. Put TheConnector's EA on that chart with your ACCOUNT_CODE and ROUTING_TOKEN, and "Allow Algo Trading" ticked. Check the Experts tab and TheConnector's dashboard show it connected.

B. Rent and migrate

- 1 Navigator → Accounts → right-click the account → **Register a Virtual Server**. MT5 picks the server closest to FxPro (London).
- 2 Take the free trial if offered, otherwise one month. Pay, choose migration type **Experts**, click **Migrate**. Your login, chart, EA inputs, symbols and WebRequest list move across. On the VPS, algo trading is always on.

Then switch the laptop's Algo Trading button OFF

Otherwise the EA runs in two places and every command could be placed twice. With it off you can keep MT5 open to watch, or close it.

C. Check and test, on a demo account

- 1 Navigator → right-click the virtual server → **Journal**: the migration finished and the EA loaded with no errors. Error 4014 on a web request = TheConnector's address is missing from the WebRequest list: add it on the laptop and migrate again.
- 2 **Shut the laptop down**. Create one temporary TradingView alert that fires soon, with your webhook URL and the fixed message `{"action":"buy","symbol":"XAUUSD","volume":0.01,"tag":"smcgo1d"}`. A 0.01-lot buy must appear on the demo account in MT5 on your phone. Close it, then **delete the test alert**.
- 3 Passed? Only now take a longer plan, and later set up the strategy's own alert on the live account.

Later

- **Changed something in MT5** (EA inputs, a new robot version, a different chart): do it on the laptop, then right-click the virtual server and migrate again. The laptop's setup replaces the VPS copy. Keep Algo Trading off on the laptop afterwards.
- **Changed the strategy in TradingView**: the VPS is not involved. Re-create the strategy's alert, as always.
- **Renewal**: mql5.com profile → Hosting. When the subscription ends, the trades stop without warning. Check the TradingView alert's expiry date too.
- **If the MQL5 VPS will not run the EA**: use an ordinary Windows VPS in London (Azure free 12 months, Contabo about \$10, FxPro VPS \$30), install MT5 as on the laptop, and add MT5 to the Windows Startup folder.

Before you go live

Tick every line.

Check
☐ Properties: Script execution On bar close only.
☐ Properties: Long and Short leverage 100x ; the 'Margin calls' row reads 0.
☐ Properties: Slippage 0 ; Commission Cash per contract with the table's number (0.36).
☐ Properties: Initial capital = your real FxPro balance.
☐ Groups 23 and 26: your commission per lot and spread for this ticker (28 and 0.16 on gold).
☐ Group 21: Max leverage no higher than FxPro's gold leverage. Hard cap 500 , 'Stop for the rest of the day'.
☐ Group 21: Loss recovery Off, or Rule A. If Rule B, you have read chapter 5.
☐ Group 24: Stop closer than 3.0 skipped; daily loss limit set; weekend flatten ON.
☐ Group 27: if you use the profit target with 'Total', the start date is today.
☐ Group 28: if you use news dates, this month's dates are typed and the table row 'News windows active on' shows them.
☐ Group 29: automatic US news ON, US clock Auto, the table rows 'US news (auto) - next' and 'US clock' look right.
☐ v8.0: from v7.0 to v7.6 the code replaced while flat (settings stay); from v6.1 or older added FRESH and every setting typed again. Properties Pyramiding shows 100 , leverage 100x ; the row '- REFUSED by TradingView' reads 0.
☐ Group 0: the news master switch as you want it. Group 20: audit labels OFF for live (or ON while you check). Group 31: Max trades open as you want it (0 = no limit). Group 32: stop switches OFF, or the one you chose. The 'Ticker' row shows Gold, 1 lot = 100 and your MT5 name.
☐ Every other ticker: its own chart, its own commission and spread, its own settings (chapter 11), its own Properties commission and its own alert.
☐ Group 22: webhook ON, format TheConnector , Quantity to send Lots , minimum lot 0.01. Group 30: MT5 gold symbol, tag, sl_price / tp_price.
☐ TheConnector: robot 0.0.21 or later; webhook URL ends with your access key; tag 7 characters or less.
☐ MQL5 VPS: migrated with type Experts; Journal shows the EA loaded; the laptop's Algo Trading is OFF; a test trade arrived with the laptop shut down.
☐ Alert: condition Order fills, message <code>{{strategy.order.alert_message}}</code> , webhook URL pasted, created after the last settings change.
☐ The table's three sums add up. 'Costs last trade' is not red.
☐ Two weeks on a demo account. Every fill compared with the List of Trades.
☐ First live trade: size checked in MT5.

Questions and problems

The questions that have come up so far, with the short answer.

My trades exit on 'Margin call'.

Properties leverage 30x together with Max leverage 30 makes a capped trade use the whole account as deposit, so any loss triggers it. Set Properties leverage to 100x (chapter 12).

Under Rule B my losses do not double each time.

Rule B doubles the total carried, not the last trade. Early exits lose less than the risk, and Max leverage cuts the biggest trades. Chapter 5 shows your trades 13 to 20 step by step.

Is Cumulative P&L before or after costs?

After, once Properties commission is set to 0.36. With Properties commission at 0 it is before costs; subtract the table's 'Costs paid total'.

Changing the spread or commission changed which trades filled.

Costs change the size and push the target out. A trade that just reached its old target may miss the new one, and with Rule B one different result changes every size after it. Expected.

The daily chart shows signals but no trades.

Time-of-day filters must be Auto or Never on daily charts. The 'Time filters' row should say 'off (daily+)'.

Trades stop when my laptop is off.

MT5 with TheConnector's EA runs on the laptop. Move it to an MQL5 VPS (chapter 14): rent it from MT5's Navigator, migrate with type Experts, then switch the laptop's Algo Trading off.

A trade appears in TradingView but not at FxPro.

Check in order: the alert exists and is active; condition is Order fills; message is the placeholder; webhook URL is right; Quantity to send is Lots; the size is at least 0.01 lots; the bridge's log shows the message.

Live results are worse than the backtest.

Check that Script execution is 'On bar close', the spread is set, and Properties commission is set. Then compare 30 to 50 trades: a small gap is normal (entry at market after the fill).

The profit target stopped trading as soon as I went live.

With 'Total', the backtest trades count too. Set the start date to the day the alert starts, then re-create the alert.

Can I paste TheConnector's sample message into the alert?

No. It is one fixed buy; every fill would open another buy. The message must be only `{{strategy.order.alert_message}}` and the format TheConnector (group 22).

TheConnector opened a trade without a stop.

Check the robot is 0.0.21 or later and that group 30 uses `sl_price` / `tp_price`. Mixing price units in one alert makes TheConnector drop both stop and target.

Why did the NFP block move from 19:00 to 18:00?

US summer time started. With US clock on Auto the strategy moves by itself; 08:30 New York is 18:00 IST in summer and 19:00 IST in winter.

Does it know CPI and FOMC by itself?

No. They have no fixed rule. Put them in group 25 (times, ideally in New York time) and group 28 (dates) each month.

My news window did not block on a news day.

With group 28 ON, check the row 'News windows active on': the date must be listed, and with 'This month only' it must be this month's date. After changing the dates, re-create the alert.

A BOS opened a second trade while I was already in one.

With BOS on, every same-side BOS gets its own trade, stop, target and tag; an opposite CHOCH closes them all.

The Strategy Tester shows far fewer trades than v7.1, or than the table.

Not the code: v7.1 and v7.2 take the same trades. In the table: '- REFUSED by TradingView' red = Properties leverage too low or Pyramiding under 100 (chapter 12). Table far above the Strategy Tester = its date range covers only part of the chart. A few apart is normal: Total trades counts only ended trades.

My trade reached 2R, then a CHOCH came before the stop at 1R. Does it close?

Yes: an opposite CHOCH closes every trade at the next open, wherever its stop is. If none comes, the stop at 1R closes it, in real time.

A BOS did not add a trade.

Properties → Pyramiding must be 100, not 0 or 1. Otherwise the audit label says why, e.g. SKIP - max trades open (group 31).

'Costs last trade' is red.

Costs are over 25% of the risk: the stop was very tight. Set 'Skip if the stop is CLOSER than' to 3.0.

Some CHOCH / BOS signals are not traded.

Switch on the signal audit labels (group 20): every signal shows what happened to it. Chapter 11 lists every reason. A label that does not explain a missing trade: send me a screenshot.

Rule 1 was used although the 15m chart shows the trend agreeing.

The strategy reads the last CLOSED 15m candle, so it never repaints. A 15m candle still forming can already show the new trend on the 15m chart. The audit label shows the trend the strategy used ('HTF up / dn / -').

The 'Commission model' row is orange.

No charge per lot is typed yet (it starts at 0). Type your commission for this ticker in group 23.

EURUSD, GBPUSD and AUDUSD take zero trades.

Your stop settings are gold prices: a 3.0 minimum stop is 30,000 pips on EURUSD. Type forex values into groups 20 and 24 on the forex chart, and your forex commission and spread into groups 23 and 26.

Do I have to set the lot size for each ticker?

No. It is read from the ticker: forex 100,000, gold 100, silver 5,000, crypto 1, indices 1, which matches FxPro. Check the table's 'Ticker' row.

On forex almost every setup is 'Skipped'.

Gold numbers in group 24 do not fit forex. And at 28 per lot a round trip is 5.6 pips: more than a few-pip stop risks in the market.

What does 'Entry rules 1 + 2 (dynamic)' mean when I chose Rule B?

Different settings: entry rules decide how a trade is entered; Rule A / B how much it risks after losses.

Glossary

Every term used in this handbook.

BOS	Break of structure: price breaks the last pivot in the direction of the trend. A continuation signal.
CHOCH	Change of character: price breaks the last pivot against the trend. A reversal signal.
CHOCH* level	The live structure level on the other side of the trade. The stop goes beyond it.
Main tier	The top level of structure. The strategy ignores internal and inner structure.
Move (leg)	The run from the CHOCH* level to the latest extreme. Rule 1 measures its pullback % on it.
Higher timeframe (HTF)	The slower chart Rule 2 checks, e.g. 15m for a 1m chart. Read from its last closed candle.
Risk	Money lost at the stop, after commission and spread.
R multiple	The target as a multiple of the stop distance. 3R pays three times the risk.
Lot, ounce, contract, unit	1 lot: gold 100 oz, silver 5,000, forex 100,000, crypto and indices 1. OANDA gold contract = 1 oz.
Tick, point	The smallest price step. OANDA gold: 1 tick = 0.001. MT5 points for 2-decimal gold: 0.01.
Spread	The gap between buy and sell price, paid on every trade.
Commission, per side / round turn	Your broker's fee: 28 per lot to open, 28 to close, 56 for the round turn.
Slippage	Getting a worse price than asked, mostly on stops and market orders.
Limit order	Buy below / sell above the market at a set price. The strategy's entries are limits inside TradingView.
Market order	Filled immediately at the current price. What the broker does when the alert arrives.
Bracket (SL / TP)	The stop-loss and take-profit attached to a trade.
Webhook, bridge	The alert's message is sent to a URL; the bridge behind it places the trade at FxPro.
Leverage, margin	Leverage lets you hold more than your balance; margin is the deposit the broker keeps for it.
Margin call	Forced closing of part of a trade when the account cannot cover the margin.
Drawdown	The fall from the highest equity reached.
Losses carried	What the recovery ladder still owes, after costs.
Rule A / Rule B	Loss recovery. A: (carried + base) ÷ R. B: 2 × carried, at least the base.
Hard cap	The most one recovery trade may risk.
Tag (TheConnector)	Your tag plus the trade's code (smcgold-k3f9); the robot closes only that position.
Stacked trades	Several trades open the same way at once (v7.1), one per same-side BOS.
Break-even, step stop	Entry plus costs, so a stop there nets zero; the step stop moves it up 1R at a time (v7.4).
Master news switch	The first setting (v7.0). ON: all news settings work as set. OFF: no news and no US-holiday blocks.
Signal audit labels	Optional labels (group 20) showing what happened to every signal, and why.
Market type	Forex, gold, silver, crypto or index / other, read from the ticker. It decides the lot size.
NFP	Non-farm payrolls, the US monthly jobs report.
ISM PMI	US business surveys: Manufacturing on the 1st working day, Services on the 3rd.
Jobless claims	Weekly count of new US unemployment claims, every Thursday.
EDT / EST	US summer time (UTC-4) and winter time (UTC-5).

Every change after v7.1

v8.0 is your v7.1 with every change of v7.2 to v7.6 added, built again from your file and checked against each version on the way.

From	Change
v7.2	Each stop or target closes only its own trade (close_entries_rule 'ANY'). v7.1 closed the oldest stacked trade first and could cut a trade in two.
v7.2	The trade code comes from the signal candle's time (tag smcgold-k3f9), not a running number that could change when TradingView recalculated.
v7.2	A new entry is recognised by its order code.
v7.2	Table: 'Trades entered 312 (3 still open)' and the row '- TradingView List of Trades'.
v7.3	New setting, group 31: Max trades open at the same time (0 = no limit).
v7.3	New setting, group 31: Audit label size (Large). Labels are solid dark colours with white text.
v7.4	New setting, group 32: Step stop (OFF): 1R to break-even, 2R to 1R, and so on.
v7.4	New setting, group 32: Break-even only (OFF): a close beyond 1R moves the stop to break-even, once.
v7.4	Break-even = entry + commission + spread. A stop only moves below the price reached. New row 'Exit - moved stop (BE / step)'.
v7.5	The compiler warning 'Shadowing variable _tk' is gone.
v7.5	Bug fix: loss recovery 'Stop for the rest of the day' - the new day starts before the first candle's order is sized (bug since v2.2).
v7.5	Faster: market type and news-window times read once. 'Exit - moved stop' counts only real moves.
v7.6	New row '- REFUSED by TradingView' and the label line 'REFUSED BY TRADINGVIEW': orders TradingView did not fill although the price went through them.
v8.0	Only the version text on line 2. The code is v7.6's.

Settings

84 settings in v7.1, 88 in v8.0. The 4 new ones (groups 31 and 32) come after all the others, so every v7.1 setting keeps its place and its default.

Same trades as v7.1

v8.0 chooses which signals become trades exactly as v7.1 does. If a chart shows far fewer trades, look at the table: a red row "- REFUSED by TradingView" means Properties leverage or Pyramiding (chapter 12).