Type-Level Property Based Testing

Thomas Ekström Hansen & Edwin Brady

TyDe '24 — 9th September 2024

• Many systems exhibit Finite-State-Machine-like behaviour

- Many systems exhibit Finite-State-Machine-like behaviour
- These can be modelled using dependent types

- Many systems exhibit Finite-State-Machine-like behaviour
- These can be modelled using dependent types
 - Dependent types are difficult to get right

- Many systems exhibit Finite-State-Machine-like behaviour
- These can be modelled using dependent types
 - Dependent types are difficult to get right
- How do we increase confidence in our dependent types?

Disclaimer: "increase confidence"

This is not a proof technique

But hopefully, it helps us catch errors faster and provides guarantees that our model behaves as intended

• Stateful systems are ubiquitous


- Stateful systems are ubiquitous
- Embedded controllers for automatic doors, ATMs, network protocols, etc...


- Stateful systems are ubiquitous
- Embedded controllers for automatic doors, ATMs, network protocols, etc...
- These are all stateful


- Stateful systems are ubiquitous
- Embedded controllers for automatic doors, ATMs, network protocols, etc...
- These are all stateful.
- And we would very much like them to be correct











 Dependently typed languages like Agda and Idris

- Dependently typed languages like Agda and Idris
- Can construct advanced types and embedded DSLs

- Dependently typed languages like Agda and Idris
- Can construct advanced types and embedded DSLs
- Have the types and type checker guide the implementation and verify its behaviour (correct-by-construction)

- Dependently typed languages like Agda and Idris
- Can construct advanced types and embedded DSLs
- Have the types and type checker guide the implementation and verify its behaviour (correct-by-construction)

```
head :: [a] -> a
-- crashes on
-- `head []`
```

- Dependently typed languages like Agda and Idris
- Can construct advanced types and embedded DSLs
- Have the types and type checker guide the implementation and verify its behaviour (correct-by-construction)

```
head :: [a] -> a
-- crashes on
-- `head []`
head : Vect (S k) a
     -> a
-- always safe because
-- the length must be
```

-- at least 1


- Dependently typed languages like Agda and Idris
- Can construct advanced types and embedded DSLs
- Have the types and type checker guide the implementation and verify its behaviour (correct-by-construction)

-- the length must be

-- at least 1

Fits somewhere in the middle


The ATM state machine




Datatype for the ATM states

data ATMState


- = Ready
- CardInserted
- Session



Datatype for ATM operation results




Datatype for ATM operation results



Everything which does not have a result returns Unit — ()

State Transition Function



Dependent State Transition

Dependent State Transition

ATM Indexed State Monad

```
data ATM : (t : Type) -> ATMState -> (t -> ATMState) ->
CheckPIN : (pin : Int)
           -> ATM PINok CardInserted ChkPINfn
  Insert : ATM () Ready (const CardInserted)
  Dispense : (amt : Nat) -> ATM () Session (const Session)
  Eject : ATM () st (const Ready)
  Pure : (x : t) -> ATM t (stFn x) stFn
  (>>=) : ATM a s1 s2f -> ((x : a) -> ATM b (s2f x) s3f)
  \rightarrow -> ATM b s1 s3f
```

Why Is This Neat?

• We declare our intended start and end state in the type

```
prog : ATM () Ready (const Ready)
```

Why Is This Neat?

We declare our intended start and end state in the type

```
prog : ATM () Ready (const Ready)
```

 And the type-checker verifies that we don't use operations incorrectly

```
      prog = do
      -- We start in Ready

      Insert
      -- Ready to CardInserted

      Correct <- CheckPIN 1234</td>
      --- CI to Session

      | Incorrect => <...> ---- (or stay in CI)

      Dispense 42
      ---- Stay in Session

      Eject
      ----- Return to Ready
```

Dependent Types Only Get Some Things Right

Rejected by the type-checker:

```
badProg : ATM ()
            Ready (const Ready)
badProg = do
 Insert.
 let pin = 1234
 Correct <- CheckPIN pin
    Incorrect => InsertCard
 Dispense 42
  -- We never Eject, so we
  -- never come back to
  -- Ready'
```

Dependent Types Only Get Some Things Right

Rejected by the type-checker:

```
badProg : ATM ()
            Ready (const Ready)
badProg = do
 Insert.
 let pin = 1234
 Correct <- CheckPIN pin
    Incorrect => InsertCard
 Dispense 42
  -- We never Eject, so we
  -- never come back to
  -- `Readu'
```

Accepted by the type-checker:

```
loopProg : ATM ()
              Ready (const Ready)
loopProg = do
    Insert.Card
    let pin = 4321
    loopIncorrect pin
  where
    loopIncorrect : Nat -> ATM ()
                       CardInserted
                       (const Ready)
    loopIncorrect p = do
      Incorrect <- CheckPIN p</pre>
        | Correct => -- <...>
```

loopIncorrect p

Property Based Testing

Generate instances of types from random numbers
 data Gen a : (Int -> a) -> Type

Property Based Testing

Generate instances of types from random numbers
 data Gen a : (Int -> a) -> Type

• interface Arbitrary a where arbitrary : Gen a

Property Based Testing

• Generate instances of types from random numbers data Gen a : (Int -> a) -> Type

- interface Arbitrary a where arbitrary: Gen a
- We express boolean properties, which are then tested over random inputs (typically 100)

```
reverse (reverse xs) == xs
```

What About Dependent Types?

QuickCheck works very well for regular types, what about dependent types?

```
Arbitrary t => Arbitrary (Vect n t) where
```

```
Arbitrary t => Arbitrary (Vect n t) where
arbitrary = do
  length_ <- arbitrary</pre>
```

```
Arbitrary t => Arbitrary (Vect n t) where
arbitrary = do
   length_ <- arbitrary
arbVect <- nArbitrary length_</pre>
```

```
Arbitrary t => Arbitrary (Vect n t) where
arbitrary = do
   length_ <- arbitrary
arbVect <- nArbitrary length_
pure arbVect</pre>
```

```
Arbitrary t => Arbitrary (Vect n t) where
arbitrary = do
  length_ <- arbitrary
arbVect <- nArbitrary length_
pure arbVect
-- Error: cannot unify length_ with n</pre>
```

Consider generating arbitrary vectors:

```
Arbitrary t => Arbitrary (Vect n t) where
arbitrary = do
  length_ <- arbitrary
arbVect <- nArbitrary length_
pure arbVect
-- Error: cannot unify length_ with n</pre>
```

How do we solve this?

Arbitrary Dependent Types

• The solution is more dependent types!

Arbitrary Dependent Types

- The solution is more dependent types!
- Specifically: dependent pairs

```
record DPair a (p : a -> Type) where
  constructor MkDPair
  fst : a
  snd : p fst
```

Arbitrary Dependent Types

- The solution is more dependent types!
- Specifically: dependent pairs

```
record DPair a (p : a -> Type) where
  constructor MkDPair
  fst : a
  snd : p fst
```

As long as we know how to generate an `Arbitrary a`,
we can generate an `Arbitrary (x : a ** p x)`

When we know the length, we will know the type of the vector

Arbitrary (n : Nat ** Vect n a) where

```
Arbitrary (n : Nat ** Vect n a) where
arbitrary = do
   length_ <- arbitrary</pre>
```

```
Arbitrary (n : Nat ** Vect n a) where
arbitrary = do
  length_ <- arbitrary
arbVect <- nArbitrary length_</pre>
```

```
Arbitrary (n : Nat ** Vect n a) where
arbitrary = do
  length_ <- arbitrary
  arbVect <- nArbitrary length_
  pure (length_ ** arbVect)</pre>
```

```
Arbitrary (n : Nat ** Vect n a) where
arbitrary = do
  length_ <- arbitrary
  arbVect <- nArbitrary length_
  pure (_ ** arbVect)</pre>
```

Arbitrary ATMs?

Can we do a similar thing for the ATM?

Arbitrary ATMs?

Can we do a similar thing for the ATM?

With a bit of work, yes!

A Bit of Work

 Store the operation and its result instance — for example whether PINok was successful

```
(<resT> ** <stFn> ** MkOpRes <op> <res : resT> ...)
```

A Bit of Work

 Store the operation and its result instance — for example whether PINok was successful

```
(<resT> ** <stFn> ** MkOpRes <op> <res : resT> ...)
```

 Store an operation-result pair, and the state this moved us to

A Bit of Work

 Store the operation and its result instance — for example whether PINok was successful

```
(<resT> ** <stFn> ** MkOpRes <op> <res : resT> ...)
```

 Store an operation-result pair, and the state this moved us to

```
TraceStep (OpRes <stT> ...) <resSt : stT>
```

• A chain of these make up a *trace*

ATM: from CardInserted

This is still QuickCheck, we can control the frequency of generated instances:

```
options CardInserted = do
   -- we need a PIN, even though we control the result
let arbPIN = 0
let op1 = (_ ** _ ** MkOpRes (CheckPIN arbPIN) Correct)
let op2 = (_ ** _ ** MkOpRes (CheckPIN arbPIN) Incorrect)
let op3 = (_ ** _ ** MkOpRes Eject ())
frequency $ [(1, pure op1), (4, pure op2), (1, pure op3)]
```

Type-Level Property Based Testing

• In Idris2, the So type is inhabited iff its argument evaluates to True

Type-Level Property Based Testing

- In Idris2, the So type is inhabited iff its argument evaluates to True
- In other words, we can run property based testing as part of the type checking process!

```
So (quickCheck <property>)
```

Type-Level Property Based Testing

- In Idris2, the So type is inhabited iff its argument evaluates to True
- In other words, we can run property based testing as part of the type checking process!

```
So (quickCheck <property>)
```

 Idris2 is built on Quantitative Type Theory, which has erasure, meaning the tests can be removed from the compiled program

QuickCheck Spots the Error!

```
0 PROP_eventuallyReady : Fn (ATMTrace Ready 10) Bool
PROP_eventuallyReady = MkFn
  (\case (MkATMTrace _ trace) => elem Ready (map (.resSt) trace))
```

QuickCheck Spots the Error!

```
0 PROP_eventuallyReady : Fn (ATMTrace Ready 10) Bool
PROP_eventuallyReady = MkFn
  (\case (MkATMTrace _ trace) => elem Ready (map (.resSt) trace))
```

With a property to eventually return to Ready, the file no longer type checks

QuickCheck Spots the Error!

```
O PROP_eventuallyReady : Fn (ATMTrace Ready 10) Bool
PROP_eventuallyReady = MkFn
  (\case (MkATMTrace _ trace) => elem Ready (map (.resSt) trace))
With a property to eventually return to Ready, the file no
longer type checks
-- Error: While processing right hand side of
           EventuallyReady_OK. When unifying:
    So True
-- and:
    So (quickCheck PROP_eventuallyReady)
-- Mismatch between: True and False.
```

QuickCheck Gives a Trace

Investigating by running QuickCheck at the REPL, the error is exactly the fault in the model

QuickCheck Gives a Trace

Investigating by running QuickCheck at the REPL, the error is exactly the fault in the model

```
MkQCRes (Just False) <log> """
Falsifiable, after 4 tests:
Starting @ Ready:
[ (<ATM 'Insert ~ ()'>, CardInserted)
, (<ATM 'CheckPIN 0 ~ Incorrect'>, CardInserted)
<...>
]\n"""
```

Fixing Things

• Now that we know there's an error, we can fix things!

Fixing Things

Now that we know there's an error, we can fix things!

Fixing Things

• Now that we know there's an error, we can fix things!

 Carrying this through to the generators, our property passes: the file reloads successfully and the REPL reports

```
> quickCheck PROP_eventuallyReady
MkQCRes (Just True) <log> "OK, passed 100 tests"
```

- With most verification tools, we have to translate between representations
 - Spec, model, and implementation are independent

- With most verification tools, we have to translate between representations
 - Spec, model, and implementation are independent
- This results in the risk of translation mistakes

- With most verification tools, we have to translate between representations
 - Spec, model, and implementation are independent
- This results in the risk of translation mistakes
 - The verification tool might not support the same types as the implementation language

- With most verification tools, we have to translate between representations
 - · Spec, model, and implementation are independent
- This results in the risk of translation mistakes
 - The verification tool might not support the same types as the implementation language
 - Might think we're verifying the same thing, when in actual fact the semantics have changed between representations

All in one

In our case, the specification is the model; everywhere

All in one

In our case, the specification is the model; everywhere

All in one

In our case, the specification is the model; everywhere

And this works for anything expressed in terms of states and operations with results — ISMs generalise

We Are Testing Types!

 We have tested the dependent types which help guide us when writing the implementation, not the implementation itself since it is being kept in check by the types

We Are Testing Types!

- We have tested the dependent types which help guide us when writing the implementation, not the implementation itself since it is being kept in check by the types
- Testing gives us confidence that our dependent types are not misleading

We Are Testing Types!

- We have tested the dependent types which help guide us when writing the implementation, not the implementation itself since it is being kept in check by the types
- Testing gives us confidence that our dependent types are not misleading
- Dependent types are type-level programs, let's test them!

Thank You

Email: teh6@st-andrews.ac.uk

Paper



doi:10.1145/3678000.3678206

Further Work

- Running tests at the type level puts a lot of strain on the compiler, so there may be interesting optimisations to explore there
- Can we do more? ARQ with Sliding Window? Protocols with crash-stop failures?
- What kinds of properties can we test? There are parallels to Model Checking, so how does this compare to LTL or TLA+?

Generic ISM Datatype

```
op : forall st . (t' : Type) \rightarrow st \rightarrow (t' \rightarrow st) \rightarrow Type
data Prog : {0 stT : _} -> (opT : (t' : _) -> stT -> (t'
\rightarrow -> stT) -> Type) -> (t : Type) -> (from : stT) -> (to
\rightarrow : t -> stT) -> Type where
  Pure : (x : t) -> Prog opT t (stFn x) stFn
  Op : {0 opT : (t' : _) -> stT -> (t' -> stT) -> Type} ->

→ opT t st stFn → Prog opT t st stFn

  (>>=) : Prog opT resT1 st1 stFn1 -> ((x : resT1) -> Prog
  → opT resT2 (stFn1 x) stFn2) -> Prog opT resT2 st1
  \hookrightarrow stFn2
```

Operation-Result Pairs

TraceStep

```
record TraceStep (opT : (t' : _) -> stT -> (t' -> stT) ->
constructor MkTS
 {0 stepRT : _}
 {0 stepSt : stT}
 {0 stepFn : stepRT -> stT}
 opRes : OpRes opT stepRT stepSt stepFn
 resSt : stT
 {auto showStT : Show stT}
```

Trace

```
data Trace : (opT : (t' : _) -> stT -> (t' -> stT) -> \rightarrow Type) -> stT -> Nat -> Type where

MkTrace : Show stT => (initSt : stT) -> {bound : Nat}

-> (trace : Vect bound (TraceStep opT))

-> Trace opT initSt bound
```