NAME

ovsdb-tool - Open vSwitch database management utility

SYNOPSIS

```
ovsdb-tool [options] create [db [schema]]
ovsdb-tool [options] compact [db [target]]
ovsdb-tool [options] convert [db [schema [target]]]
ovsdb-tool [options] needs-conversion [db [schema]]
ovsdb-tool [options] db-version [db]
ovsdb-tool [options] schema-version [schema]
ovsdb-tool [options] db-cksum [db]
ovsdb-tool [options] schema-cksum [schema]
ovsdb-tool [options] query [db] transaction
ovsdb-tool [options] transact [db] transaction
ovsdb-tool [options] [-m | --more]... show-log [db]
ovsdb-tool help
Logging options:
        [-v[module[:facility[:level]]]]...
        [--verbose[=module[:facility[:level]]]]...
        [--log-file[=file]]
Common options:
        [-h \mid --help] [-V \mid --version]
```

DESCRIPTION

The **ovsdb-tool** program is a command-line tool for managing Open vSwitch database (OVSDB) files. It does not interact directly with running Open vSwitch database servers (instead, use **ovsdb-client**).

Basic Commands

create db schema

Reads an OVSDB schema from the file named *schema* and creates a new OVSDB database file named db using that schema. The new database is initially empty. This command will not overwrite an existing db.

schema must contain an OVSDB schema in JSON format. Refer to the OVSDB specification for details.

compact *db* [*target*]

Reads *db* and writes a compacted version. If *target* is specified, the compacted version is written as a new file named *target*, which must not already exist. If *target* is omitted, then the compacted version of the database replaces *db* in-place.

convert *db schema* [*target*]

Reads *db*, translating it into to the schema specified in *schema*, and writes out the new interpretation. If *target* is specified, the translated version is written as a new file named *target*, which must not already exist. If *target* is omitted, then the translated version of the database replaces *db* inplace.

This command can do simple "upgrades" and "downgrades" on a database's schema. The data in *db* must be valid when interpreted under *schema*, with only one exception: data in *db* for tables and columns that do not exist in *schema* are ignored. Columns that exist in *schema* but not in *db* are set to their default values. All of *schema*'s constraints apply in full.

needs-conversion db schema

Reads the schema embedded in *db* and the standalone schema in *schema* and compares them. If the schemas are the same, prints **no** on stdout; if they differ, print **yes**.

db-version db

schema-version schema

Prints the version number in the schema embedded within the database db or in the standalone schema schema on stdout. A schema version number has the form x.y.z. See **ovs-vswitchd.conf.db**(5) for details.

Schema version numbers and Open vSwitch version numbers are independent.

If *schema* or *db* was created before schema versioning was introduced, then it will not have a version number and this command will print a blank line.

db-cksum db

schema-cksum schema

Prints the checksum in the schema embedded within the database *db* or of the standalone schema *schema* on stdout.

If *schema* or *db* was created before schema checksums were introduced, then it will not have a checksum and this command will print a blank line.

query db transaction

Opens db, executes transaction on it, and prints the results. The transaction must be a JSON array in the format of the **params** array for the JSON-RPC **transact** method, as described in the OVSDB specification.

The *db* is opened for read-only access, so this command may safely run concurrently with other database activity, including **ovsdb-server** and other database writers. The *transaction* may specify database modifications, but these will have no effect on *db*.

transact db transaction

Opens db, executes transaction on it, prints the results, and commits any changes to db. The transaction must be a JSON array in the format of the **params** array for the JSON-RPC **transact** method, as described in the OVSDB specification.

The *db* is opened and locked for read/write access, so this command will fail if the database is opened for writing by any other process, including **ovsdb-server**(1). Use **ovsdb-client**(1), instead, to write to a database that is served by **ovsdb-server**(1).

show-log db

Prints a summary of the records in db's log, including the time and date at which each database change occurred and any associated comment. This may be useful for debugging.

To increase the verbosity of output, add $-\mathbf{m}$ (or $--\mathbf{more}$) one or more times to the command line. With one $-\mathbf{m}$, \mathbf{show} - \mathbf{log} prints a summary of the records added, deleted, or modified by each transaction. With two $-\mathbf{m}s$, \mathbf{show} - \mathbf{log} also prints the values of the columns modified by each change to a record.

OPTIONS

Logging Options

 $-\mathbf{v}[spec]$

--verbose=[spec]

Sets logging levels. Without any *spec*, sets the log level for every module and facility to **dbg**. Otherwise, *spec* is a list of words separated by spaces or commas or colons, up to one from each category below:

- A valid module name, as displayed by the **vlog/list** command on **ovs-appctl**(8), limits the log level change to the specified module.
- **syslog**, **console**, or **file**, to limit the log level change to only to the system log, to the console, or to a file, respectively.

On Windows platform, **syslog** is accepted as a word and is only useful along with the **—syslog–target** option (the word has no effect otherwise).

• **off**, **emer**, **err**, **warn**, **info**, or **dbg**, to control the log level. Messages of the given severity or higher will be logged, and messages of lower severity will be filtered out. **off** filters out all messages. See **ovs-appctl**(8) for a definition of each log level.

Case is not significant within spec.

Regardless of the log levels set for **file**, logging to a file will not take place unless **—-log-file** is also specified (see below).

For compatibility with older versions of OVS, any is accepted as a word but has no effect.

-v --verbose

Sets the maximum logging verbosity level, equivalent to --verbose=dbg.

- vPATTERN: facility: pattern

--verbose=PATTERN:facility:pattern

Sets the log pattern for *facility* to *pattern*. Refer to **ovs-appctl**(8) for a description of the valid syntax for *pattern*.

--log-file[=file]

Enables logging to a file. If *file* is specified, then it is used as the exact name for the log file. The default log file name used if *file* is omitted is /var/log/openvswitch/ovsdb-tool.log.

--syslog-target=host:port

Send syslog messages to UDP *port* on *host*, in addition to the system syslog. The *host* must be a numerical IP address, not a hostname.

Other Options

- -h
- **--help** Prints a brief help message to the console.
- $-\mathbf{V}$
- --version

Prints version information to the console.

FILES

The default *db* is /usr/etc/openvswitch/conf.db. The default *schema* is /usr/share/openvswitch/vswitch.ovsschema. The help command also displays these defaults.

SEE ALSO

ovsdb-server(1), **ovsdb-client**(1), and the OVSDB specification.