Assembly: load/store operations; arithmetic operations; translating assembly code to low-level C code

COSC 208, Introduction to Computer Systems, 2022-03-22

Announcements

• Project 2 due Thursday, Mar 31

Outline

- Warm-up
- · Assembly (recap)
- · Load/store operations
- Arithmetic and bitwise operations
- Translating assembly code to low-level C code

Operands

- Registers
 - General purpose: w0 through w30 (32-bit) and x0 through x30 (64-bit)
 - Stack pointer (top of current stack frame): sp
- Constant -- e.g., #0x20 vs #12 (hexa vs decimal)
- Memory
 - Dereference --- e.g., [x1]
 - Add to (offset from) memory address, then dereference --- e.g., [sp,#16]

Load/store operations

```
value at [address] found in Rb
is loaded into register Ra

LDR Ra, [Rb]

STR Ra, [Rb]

value found in register Ra
is stored to [address] found in Rb
```

Warm-up: load/store operations

Q1: Write the C c	ode equivalent for each line of assembly, treating registers as if they were variable names.
• ldr x0,	[sp]
• str w0,	[sp]
• ldr x1,	[sp, #12]
• str x2,	[x3, #0x10]
A rithmatia a	nalla sigal an anationa
Anumeuc a	nd logical operations
	nd logical operations ode equivalent for each line of assembly, treating registers as if they were variable names.
	ode equivalent for each line of assembly, treating registers as if they were variable names.
Q2: Write the C c	ode equivalent for each line of assembly, treating registers as if they were variable names.
Q2: Write the C c	ode equivalent for each line of assembly, treating registers as if they were variable names.
Q2: Write the C c	rode equivalent for each line of assembly, treating registers as if they were variable names. w1, w2
Q2: Write the C c	rode equivalent for each line of assembly, treating registers as if they were variable names. w1, w2
Q2: Write the C c	rode equivalent for each line of assembly, treating registers as if they were variable names. w1, w2
Q2: Write the C c	rode equivalent for each line of assembly, treating registers as if they were variable names. w1, w2
Q2: Write the C c • lsl w0, • and w3,	rode equivalent for each line of assembly, treating registers as if they were variable names. w1, w2
Q2: Write the C c • lsl w0, • and w3,	w1, w2 w4, #20
Q2: Write the C c • lsl w0, • and w3,	w1, w2 w4, #20
• Isl w0, • and w3, • mul w5,	w4, #20 w6, #0x11
Q2: Write the C c • lsl w0, • and w3,	w4, #20 w6, #0x11

Mapping assembly code to C code

Q3: The following C code was compiled into assembly.

```
1
   #include <stdio.h>
int years_to_double(int rate) {
3
       int ruleof72 = 72;
4
       int years = ruleof72 / rate;
5
       return years;
  }
6
7
  int main() {
8
       int r = 10;
9
       int y = years_to_double(r);
       printf("With an interest rate of %d% it will take ~%d
10
           years to double your money\n", r, y);
11 }
```

For each line of assembly, indicate which original line of C code (above) the assembly instruction was derived from.

Translating assembly code to low-level C code

The following C program (operands.c) has been compiled into assembly:

```
int operandsA(int a) {
    return a;
long operandsB(long b) {
    return b:
int operandsC(int *c) {
    return *c;
long operandsD(long *d) {
    return *d;
}
int main() {
    operandsA(5);
    operandsB(5);
    int x = 5;
    operandsC(&x);
    long y = 5;
    operandsD(&y);
}
```

Q4: Write the C code equivalent for each line of assembly, treating registers as if they were variable names. The assembly code for the operandsA function has already been translated into low-level C code.

```
00000000000007ec <operandsA>:
   7ec: d10043ff sub sp, sp, \#0x10 // sp = sp - 0x10
   7f0:
           b9000fe0
                    str w0, [sp, #12] //*(sp + 12) = w0
   7f4:
         b9400fe0 ldr w0, [sp, #12] // w0 = *(sp + 12)
   7f8:
                      add sp, sp, \#0x10 // sp = sp + 0x10
           910043ff
   7fc:
           d65f03c0
                                          // return
                      ret
00000000000000800 <operandsB>:
   800: d10043ff sub sp, sp, #0x10
                                          //
   804:
        f90007e0 str x0, [sp, #8]
f94007e0 ldr x0, [sp, #8]
                                          //
   808:
                                          //
        910043ff add sp, sp, #0x10
   80c:
                                          //
   810:
          d65f03c0
                    ret
                                          //
0000000000000814 <operandsC>:
   814:
          d10043ff sub sp, sp, \#0x10
                                          //
   818:
                    str x0, [sp, #8]
           f90007e0
                                          //
   81c:
           f94007e0 ldr x0, [sp, #8]
                                          //
                    ldr w0, [x0]
   820:
           b9400000
                                          //
   824:
           910043ff
                      add sp, sp, #0x10
                                          //
           d65f03c0
   828:
                      ret
                                          //
0000000000000082c <operandsD>:
   82c: d10043ff sub sp, sp, #0x10
                                          //
   830:
          f90007e0 str x0, [sp, #8]
                                          //
   834:
          f94007e0 ldr x0, [sp, #8]
                                          //
          f9400000 ldr x0, [x0]
   838:
                                          //
                                          //
   83c:
           910043ff
                       add sp, sp, #0x10
   840:
           d65f03c0
                       ret
                                          //
```

Q5: How does the assembly code for operandsA and operandsB differ? Why?	
Q6: How does the assembly code for operandsB and operandsD differ? Why?	
Q7: How does the assembly code for operandsC and operandsD differ? Why?	