MIND IT! QUIZMASTER CHEAT SHEET

A · ESSENTIAL QUIZMASTER CONTROLS

Button	What it does	Button	What it does
Correct [C] ✓	+ value (+ bonus) · shows ⚡ while it applies.	+30 Sec ✓	+30 s per press; not after Time's Up.
Wrong Answer [W] ✓	− value; same question → next team (fresh 45 s).	Adjust Score ✓	More Controls → ± amount + reason (on TV).
Wrong, no penalty [X]	0; question moves on.	Next Question [N]	Back to the board (auto 3½ s after a correct).
Pass [S] ✓	0; next team: 30 s + time left (max 45).	Undo [U] ✓	Reverses the last score (and gives back its chip).
Timer [T] ✓	Start / stop the clock (it auto-starts).	End Round Early [E] ✓	Open question closed unscored → round summary.
Pause Timer ✓	Pause / resume. End Timer = time's up now.	Final Round	Close Wagers · Reveal Answer · mark · Reveal [V].
Reveal Answer [R] ✓	Answer on TV, no scoring.	🏁 END GAME (tablet)	After standings: saved once → menus.
Back to Board [B] ✓	Leave unscored; question stays open.	Show Standings [P]	Flash the standings on the TV.

B · SCORING CHEAT SHEET

Situation	Rule	Example
Correct	+ value (+ pass-on bonus) (+ speed bonus)	400 question → **+400**
Wrong	− value; question → next team (fresh clock). Never earns a bonus.	400 → **−400**; next team right → +400
Pass	0; question → next team	—
Pass-on bonus	+25% of value **per explicit pass** before the right answer (or fixed 100/pass)	600 passed twice → 600 + 300 = **+900**
Speed bonus	+50% of the round's **lowest** value · picking team only · right within 10 s · not after pass/wrong, not DD, not Triple Gamble	Rd 1 (200–1,000): 200 in 4 s → **+300**. Rd 2: bonus 200
Daily Double	Bet min = value, max = higher of score, 1,000, value · ± wager · no pass/bonus	Score 0, tile 400 → bet 400–1,000
Triple Gamble	± 3× value; on a DD a fixed ± 6× value · no pass	400 → **±1,200**; DD 1,000 → **±6,000**
Phoenix	+ max(value, min(2×value + 20% of gap, gap)) · wrong = 0	1,200 tile, 3,000 behind → **+3,000** (level)
Bottoms Up	Wrong → ✓ Finished = 0 · ✕ Not finished = − value	800 wrong, drink finished → **0**
Negative score	Allowed. Below 0 = sits out the Final.	−600 can still play rounds
Final Round	Eligible ≥ 0 · bet 0 to score · right + bet · wrong − bet · wrong-no-penalty 0	2,400 bets 1,000 → **3,400** / 1,400

Values (auto): 1–3 rounds start 200 / 400 / 600; 4 rounds 250 / 500 / 750 / 1,000. Row k = start × k. Speed bonus = half the start value.

C · SPECIAL ABILITIES

Ability	When	Who activates	Limit	Effect	Key restriction
💰 **Daily Double**	Found by picking its tile (1·2·2·3 per round)	Picking team (bet on phone) / QM	—	± wager	Only that team answers; can't pass. Lock the wager first.
🎲 **Triple Gamble**	Own turn, **before** picking	Team phone (confirm) / QM "Use for…"	1 per game	± 3× (DD 6×)	No pass, no bonuses; wrong ends the question.
🔥 **Phoenix**	Rounds 2–4, own turn, before picking	Last team > 2,000 behind / QM	1 per game	double + 20% gap, capped at leader	Wrong = 0. Expires at round end. Not on a DD.
🍺 **Bottoms Up**	Round 1 only, own turn, before picking	Team phone (designated player) / QM	1 per game	Wrong = 0 if drink finished	QM decides Finished / Not finished. Not on a DD.

One chip per question · chips need Standard Mode + laptop app · none in Buzzer Mode or the Final · QM can **Switch off** before the pick (team keeps it) · Undo gives the chip back.

D · TIMERS

Question	Final Round	After a pass	After a wrong	+30 Sec	Speed window
45 s, auto-starts	60 s + thinking music	30 s + time left, max 45 s	fresh 45 s	+30 s per press, not after Time's Up	first 10 s

Time's up on a normal question → card ⏰ **Time's up for…**: WRONG ANSWER / PASS / Dismiss (nothing automatic). DD & Triple Gamble: no card. Final: typed answers close 2 s after time's up. Heartbeat in the last 10 s.

MIND IT! QUIZMASTER CHEAT SHEET

A · BEFORE THE GAME

- ☐ **Laptop** plugged in, sleep off, Mind It! open on Setup.
- ☐ **Questions checked**: 4 · Rounds & Questions → "Template Check: No problems found"; Final question set.
- ☐ **Teams registered**: 2–8 teams, each ≥ 1 player (1 player = their name & picture); Quizmaster chosen. ✓ *Ready to Start*.
- ☐ **Audience View** open on the TV, full screen.
- ☐ **Tablet connected**: Connect ▾ → Connect Tablet; tablet shows *Connected*.
- ☐ **Phones connected**: scan the QR on the TV (or 📶 Devices → Phone Join QR); codes in 🔐 Team Codes. 📶 Teams 4/4.
- ☐ **Connection check**: 📶 Check Connections → TEST ALL → "All set".
- ☐ **Audio checked**: Test Sound; TV/HDMI sound output.
- ☐ **Game saved**: ⋯ ▾ → Backups & Restore → Back Up Now.
- ☐ Optional: 2-minute 🎭 Rehearsal (nothing counts).

The TV shows the phone join QR until Round 1 starts (switch: 5 · Audio & Presentation). Never show the **Phone Remote** code — that one is for the Quizmaster.

B · DURING THE GAME

- **Questions:** trust *Now Playing*. Next question = team **after the one who picked**. Wrong pick? **Back to Board (B)**.
- **Scoring:** read the answer first; check the amount on the button; **Undo (U)** at once if wrong; disputes → **Adjust Score** with a reason.
- **Special abilities:** chips are used **before** picking. Team phone flat? 🎟 **Team Chips** → **Use for…**. Bottoms Up wrong → ✓ Finished / ✕ Not finished.
- **Daily Double:** wait for "locked in" (or type it + **Lock Wager & Show Question**).
- **Team connections:** 📶 Teams x/y. Asleep = phone locked. Wrong team → phone *Change Team Code*.
- **Audience View:** never minimise it; the host window may sit on top. Breaks: ⋯ ▾ → ☕ Intermission.
- **Timer issues:** Pause/Resume, +30 Sec — same for every team.
- **Back up** at every round summary (Save Backup File).

C · EMERGENCY TROUBLESHOOTING — fastest safe fix

Problem	Fastest safe recovery
Host app closes unexpectedly	Reopen **Mind It!.exe** → **Resume saved game** (NOT Start fresh) → reopen Audience View → tablet & phones reconnect by themselves → restart/extend the timer if a question was live → check scores. No resume? ⋯ → Backups & Restore → Choose Backup File… → Return to game.
Tablet disconnects	Keep playing on the laptop. Tablet retries by itself; else Main Menu → **Connect To Laptop** (or Connect Tablet → PIN). Same Wi-Fi?
Audience View "Reconnecting to Host…"	Make sure the laptop's host window is open and the laptop awake; it clears itself. Still stuck: Audience View ▾ → Open Audience Window again.
Phone disconnects	Unlock the phone, bring the browser to the front, pull to refresh; code is remembered. Wager in doubt? You type it (✏️ Change a Wager).
Score is incorrect	**Undo (U)** if it was the last action; otherwise **Adjust Score** + reason (shown on TV).
Timer freezes	Press Pause/Resume or **T**; check for a ⏰ Time's-up card; the laptop's clock is the real one.
Question doesn't load / blank tile	**Back to Board (B)** and pick again. Empty slot → Setup (pauses) → 4 · Rounds & Questions → fill or 🔄 Replace → Return to game.
Nothing can connect	Same Wi-Fi? Guest Wi-Fi → laptop **mobile hotspot**. VPN off. Firewall: allow Mind It! on Private. Restart Mind It! → Resume.

D · ENDING THE GAME

- ☐ **Finish the Final Round**: all wagers in (or Close Wagers → missing = 0), question, answers typed (the question is locked).
- ☐ **Confirm scores**: mark every team (Accept / Reject / Wrong, No Penalty / ✎ Edit Answer), then Reveal lowest first.
- ☐ **Check standings** on the TV; level on points → most correct answers wins.
- ☐ **Results saved** automatically when the standings appear ("✓ Game saved to history").
- ☐ 🏅 **Achievements & Fun Stats** (Space) · Save Picture.
- ☐ Press 🏁 **END GAME** on the tablet (or Back to Setup on the laptop).
- ☐ **Return to main menu**: tablet → Main Menu, laptop → Setup. Then Back Up Now.

KEYS & LIMITS

Main action	Space
Open / close wagers	O / L
Teams	2–8 · ≥ 1 player each
Board	6 categories × 5 · up to 4 rounds + Final
DD cap (low scores)	1,000
Phoenix needs	last place, > 2,000 behind
Phone page	http://<laptop>:8765/play
Never on the TV	answers, bets, team codes, chips*

*Except the public Phoenix holder.

Help: Complete Idiot's Guide Ch. 22 (HELP! My game closed) & Ch. 23