SINvACC
SINGAPORE VIRTUAL AREA CONTROL CENTRE

VATSIM Singapore Virtual Area Control Centre

Singapore Changi (WSSS) Arrival Brief

Version 1.5
Updated 22 October 2026

Table of Contents

Introduction 2
Revision Logs 2
Airport Information and Charts 2
Airport Scenery 2
Airport Layout 3
Overview 3
Terminal 1 4
Terminal 2 5
Terminal 3 6
Terminal 4 7
Taxiway NOTAM 8
Flight Plan 9
Standard Terminal Arrival Route (STAR) 9
ASUNA 9
ARAMA 9
TEBUN 9
LELIB 9
NUFFA 9
LEBAR 10
KARTO 10
UGEBO 11
REPOV 11
PUBLISHED HOLD FIX 12
Frequencies 13
Procedures 14
Pre-Arrival 14
Singapore Radar (WSJC_CTR) 15
Singapore Approach (WSSS_APP) 18
Singapore Arrival (WSSS_F_APP) 20
Singapore Tower (WSSS_TWR) 22
Singapore Ground (WSSS_GND) 24

Introduction

This document is to assist VATSIM pilots when arriving at Singapore Changi Airport (WSSS). Ensure that you read and familiarise yourself with this document to maximise your experience in the Singapore FIR. If you have any queries, kindly contact us on the Singapore vACC Discord.

https://community.vatsim.net/

Revision Logs

Revision	Revision Date	Change	Change by
1.0	26 March 2021	Initial Version	Isaac Tan – SGP3
1.1	16 July 2021	Updated Airport Information (Terminal 2) Updated Taxiway NOTAM Updated Procedures	Isaac Tan – SGP3
1.2	12 February 2023	Updated Airport Information and Charts Updated Airport Information (Terminal 2)	Isaac Tan – SGP3
1.4	11 August 2025	Updated Introduction Updated Procedures Updated Airport Layout Updated Airport Scenery	Ryan Thum – SGP6
1.5	22 October 2026	Added new note to Vacating Added diagram of Taxiway Restrictions Revised Pre Arrival Section b	Edric Ong – SGP6

Airport Information and Charts

For the latest charts and airport procedures, pilots can refer to the latest Navigraph charts or the links below.

SINvACC Linktree
pushback.sinvacc.org (WSSS)

Airport Scenery

There are multiple sceneries available for use. You may view them at the following links below.

Scenery Developer	**Links**
imaginesim	FSX P3Dv4/v5 MSFS 2020
Cloudsurf Asia Simulations	MSFS 2020 & 2024 X-Plane 11/12 GSX Pushback Profile (MSFS 2020 & 2024)
TAIMODELS	MSFS 2020 & 2024 (via iniBuilds Store) X-Plane 12 (via SimMarket) GSX Pushback Profile (MSFS 2020 & 2024)


Airport Layout

Singapore Changi Airport is the primary international airport of Singapore.

IMPORTANT

1. Changi Airport has Multiple Aircraft Receiving Stands (MARS). However as not all sceneries model these bays, departures may choose to connect at these bays. Whereas arrivals will not be assigned with a Left or Right bay option.


Overview



Terminal 1

Bays in Terminal 1 can be distinguished by their C and D prefixes.

Code F Bays: C23, C25, C26, D46, D49



Terminal 2


Bays in Terminal 2 can be distinguished by their E and F prefixes.

Code F Bays: E5, E8, E11, F31, F42, F60

IMPORTANT

Bays F31, F32, F33, F34, E2, E3, E4 are closed until further notice. Bays E1 and F30 are **permanently closed**.


Pilots may choose to connect at these bays with no restrictions on your departure. However, these bays will not be assigned on arrival into Singapore Changi Airport. Closures of TXL R1, R2 and R3 will not be simulated.



Terminal 3

Bays in Terminal 3 can be distinguished by their A and B prefixes.

Code F Bays: A2, A4, A5, A10, B2, B4, B5, B7




Terminal 4

Bays in Terminal 4 can be distinguished by their G prefixes.

Code F Bays: G18, G19, G20, G21

IMPORTANT

Bays G1-G17 can accommodate only Code C aircraft or smaller only.



Taxiway NOTAM

a. Aircraft with wingspan of 65m or more (Boeing 747-8/Airbus A380 and larger) are not permitted to taxi on certain taxiways for obstacle clearance purposes. Please refer to the Code F taxiway charts provided.

b. Taxiway Restrictions

   a. Code E or smaller


      - Taxiway Q (between TWY V and TWY P7)
      - Taxilane Q1 (south of TWY P)
      - Taxilane Q3 (south of TWY P)
      - Taxilane Q2
      - Taxilane P7 (behind aircraft stands E20 to E22)
      - Taxilane R7 (behind aircraft stands F50 to F54)
      - Taxiway U8
      - Taxiway U9
      - Taxiway U4

   b. Restricted Code E:

      - Taxilane V11 (behind aircraft stands A18 to A21) can only be used by aircraft with maximum wingspan 61m.

   c. Code C or smaller

      - Taxilane U2
      - Taxilane S6
      - Taxilane S7
      - Taxilane S8
      - Taxilane S9



c. Pilots are advised to apply speed limit of 20 knots when taxiing along TWY R and S between V10 and R7.

Flight Plan

Note that flights incoming from the North, North-East and East into the South China Sea are allocated specific Flight Levels. Please read up on your expected STAR.

Standard Terminal Arrival Route (STAR)

There are nine arrival fixes in Singapore. STARs with A Suffix will expect runway 02C/02L/02R (e.g. KARTO2A) and STARs with B Suffix will expect runway 20C/20R/20L (e.g. KARTO2B).

ASUNA

a. ASUNA arrival fix is used for flights inbound from the west from the R469 or L762 airway.
b. STARs available:
   Runway 02 – ASUNA2A
   Runway 20 – ASUNA2B

ARAMA

a. ARAMA arrival fix is no longer in use for arrivals. Refer to TEBUN/LELIB.

TEBUN

a. TEBUN arrival fix is used for flights inbound from the north-west from the A464 airway.
b. STARs available:
   Runway 02 – TEBUN1A
   Runway 20 – TEBUN1B
c. During flight planning, ensure to route via "TOPOR A464 ARAMA DCT TEBUN" to join the TEBUN arrival. Do not proceed direct to TEBUN after being cleared by ATC for the TEBUN arrival.

LELIB

a. LELIB arrival fix is used for flights inbound from the north-west from the A464 airway.
b. The LELIB arrival is designed for track shortening, and hence will only be cleared when the traffic situation permits. Pilots should expect the TEBUN1B arrival, especially during high traffic.
c. STARs available:
   Runway 02 – N.A.
   Runway 20 – LELIB3B

NUFFA

a. NUFFA arrival fix is used for flights inbound from the north-west of Singapore from Y514 airway.
b. Pilots can expect to be cleared to Singapore Changi via **VECTORS**. There is no STAR on this route.
c. Expect to cross NUFFA at **FL310**.
d. Pilots are to flight plan via NUFFA PIBAP PASPU NYLON.

LEBAR

a. LEBAR STAR is used when pilots are required to fly to the west of the aerodrome.
b. Note that this STAR is only used at ATC's discretion, hence do not flight plan this STAR until instructed to expect the LEBAR STAR
c. **DO NOT** plan for this STAR. It will only be assigned by ATC subject to traffic deposition.
d. STARs available:
    a. Runway 02 – LEBAR2A
    b. Runway 20 – LEBAR3B

ELALO

a. ELALO arrival fix is used for flights inbound from the north.
b. Possible FLAS Airways:
    M753 IPRIX Q802 ELALO – FL270, FL330
    L642 ESPOB Q801 ESBUM Q802 ELALO – FL310, FL320, FL350, FL360, FL390, FL400
c. STARs available:
    a. Runway 02 – ELALO1A
    b. Runway 20 – ELALO1B

MABAL

a. MABAL arrival fix is used for flights inbound from the north from the N892 airway.
b. Possible FLAS Airways:
    N892 – FL310, FL320, FL350, FL360, FL390, FL400
c. STARs available:
    Runway 02 – MABAL2A
    Runway 20 – MABAL2B

NOTE
Aircraft inbound via the B469 airway from Kuala Lumpur Control can expect the MABAL Arrival or vectors. Click here for more information.

KARTO

a. KARTO arrival fix is used for flights inbound from the east from the M767, M646 and G580 airways. Pilots are to flight plan to transit onto the KARTO STAR from TOMAN.
b. Possible FLAS Airways:
    M767 – FL310, FL320, FL350, FL360, FL390, FL400
    M646 – FL280, FL340, FL380
    G580 – FL280, FL300, FL340, FL380
c. STARs available:
    Runway 02 – KARTO2A
    Runway 20 – KARTO2B

UGEBO

a. UGEBO arrival fix is used for flights inbound from the South-east from the M635/M774/L504 airway.
b. STARs available:
    Runway 02 – UGEBO1A
    Runway 20 – UGEBO1B
c. Possible Routings
        SURGA T23 UGEBO
        KADAR M774 OBDOS T22 UGEBO
        BAVUS L504 OBDOS T22 UGEBO

REPOV

a. REPOV arrival fix is used for flights inbound from the south from the G579 airway.
b. STARs available:
    a. Runway 02 – REPOV2A
    b. Runway 20 – REPOV2B

PUBLISHED HOLD FIX

During periods where the arrival rate is high, pilots can expect to enter the hold for sequencing. Controllers, when able, will provide an estimate on when pilots can exit the hold or the amount of delay (either in minutes or the number of holds). Note that the time provided is an estimate for planning, hence the time of delay can increase or decrease subject to current traffic conditions. Estimates should not be understood as clearance to exit the hold, ensure that the controller has instructed you to "exit the hold" before exiting.

LIST OF PUBLISHED HOLDS FOR ARRIVALS

NAME	STAR	ALTITUDE(FT)	SPEED(IAS)	Radial (°) *	LEGS (MIN)
NYLON	-	A030-FL140	220	203-023	1
SAMKO	-	A040-FL140	220	348-168	1
VAMPO	TEBUN ASUNA	A060-FL180	220	149-329	1
REMES	REPOV	A060-FL140	220	348-168	1
KEXAS	KARTO UGEBO	A110-FL160	220	268-088	1
PASPU	ELALO MABAL	A060-FL160	220	180-360	1
REPOV	REPOV	FL150-FL250	250	348-168	1.5
KILOT	MABAL ELALO	FL220-FL270	250	227-047	1.5
KARTO	KARTO	FL170-FL310	280	089-269	1.5
ELALO	ELALO	FL280-FL350	300	174-354	1.5
MABAL	MABAL	FL280-FL350	300	231-051	1.5

Frequencies

Facility Callsign	Facility Name	Voice Callsign	Frequency	Remarks
WSSS_D_ATIS	Departure ATIS		128.600	
WSSS_A_ATIS	Arrival ATIS		128.025	
WSSS_DEL	**Delivery**	**Singapore Delivery**	**121.650**	
WSSS_2_DEL	Delivery 2	Singapore Delivery	119.600	
WSSS_3_GND	**Ground Movement Controller 3**	**Singapore Ground**	**124.300**	**Main Ground Sector**
WSSS_2_GND	Ground Movement Controller 2	Singapore Ground	121.725	
WSSS_1_GND	Ground Movement Controller 1	Singapore Ground	121.850	
WSSS_4_GND	Ground Movement Controller 4 (East)	Singapore Ground	122.550	
WSSS_5_GND	Ground Movement Controller 5	Singapore Ground	127.275	
WSSS_6_GND	Ground Movement Controller 4 (West)	Singapore Ground	125.650	
WSSS_1_TWR	**Runway Controller (02L/20R)**	**Singapore Tower**	**118.600**	**Main Runway Sector**
WSSS_2_TWR	Runway Controller (02C/20C)	Singapore Tower	118.250	
WSSS_3_TWR	Runway Controller (02R/20L)	Singapore Tower	131.400	
WSSS_DEP	Departure	Singapore Departure	120.300	
WSSS_APP/WSSS_S_APP	**South Approach**	**Singapore Approach**	**124.600**	**Main Approach Sector**
WSSS_N_APP	North Approach	Singapore Approach	124.050	
WSSS_F_APP	Arrival	Singapore Arrival	119.300	Not Required for Departure
WSJC_1_CTR	Radar Sector 1	Singapore Radar	134.400	
WSJC_2_CTR	Radar Sector 2	Singapore Radar	133.250	
WSJC_3_CTR	Radar Sector 3	Singapore Radar	133.800	
WSJC_4_CTR	Radar Sector 4	Singapore Radar	134.200	
WSJC_5_CTR	Radar Sector 5	Singapore Control	133.600	CPDLC: WSJE
WSJC_6_CTR	Radar Sector 6	Singapore Radar	134.700	
WSJC_CTR/WSJC_7_CTR	**Radar Sector 7**	**Singapore Radar**	**123.700**	**CPDLC: WSJC**
WSJC_8_CTR	Radar Sector 8	Singapore Radar	134.350	CPDLC: WSJN

Procedures

To facilitate your arrival into Singapore Changi Airport (WSSS), below is an exemplar situation of an arriving aircraft and the clearances to expect. Note that this is an example, and pilots should be familiarised with their aircraft prior to their arrival.

The example used will be SIA913 (Singapore 913) from Manila (RPLL) to Singapore. The arrival bay used is F59, and the aircraft will be landing on runway 20R.

Pre-Arrival

a. Read, understand, and have all necessary charts ready to anticipate any instructions provided (e.g. hold instructions, final speed control).
b. Plan and calculate all necessary flight information prior to commencing your approach into Singapore Changi Airport, including FMC, Track Miles, Autobrake Setting, Vacating Taxiway etc.
c. For flight planning purposes, pilots should utilise the following information to plan their own autobrake settings.

2.4.3 To enhance planning, pilots can make reference to the Landing Exit Distance (LED), information below which is measured from threshold to tangent point where the exit taxiway centerline starts to curve away from the runway centerline:

RWY	TWY Exits	LED
20R	❶❷W6, ❶❷W7, W8	5423' 1655m, 6965' 2123m, 10,043' 3061m
20C	❶❷T7, ❶❷T8, ❶❷D8 ❶❷D9, ❷D10	6312' 1924m, 7792' 2375m, 5741' 1750m 7300' 2225m, 8858' 2700m
20L	❶❷A7, ❶❷A8, ❷A9	5741' 1750m, 7300' 2225m, 8858' 2700m
02R	❶❷A6, ❶❷A5, ❷A4	6234' 1900m, 7792' 2375m, 9350' 2850m
02L	❶❷W5, ❶❷W4, ❷W3	6450' 1966m, 8173' 2491m, 9436' 2876m
02C	❶❷T6, ❶❷T5, ❷T4 ❶❷D7, ❶❷D6, ❷D5	6693' 2040m, 8350' 2545m, 10,646' 3245m 6234' 1900m, 7792' 2375m, 9350' 2850m


❶ Recommended exit taxiways. ❷ Rapid Exit Taxiway (RET) and maximum design ground speed for the exit taxiway is 50 KT.

d. Singapore vACC recommends that you set the following autobrake setting, if pilots are unsure of calculating their RET, assuming normal runway surface conditions:
    a. RWY 20R – Autobrake 3 (Boeing), Autobrake Medium (Airbus)
    b. RWY 20C – Autobrake 3 (Boeing), Autobrake Low (Airbus)
    c. RWY 20L – Autobrake 3 (Boeing), Autobrake Low (Airbus)

Singapore Radar (WSJC_CTR)

a. Singapore Radar manages aircraft in the Singapore FIR, and delegated sectors in Jakarta and Kuala Lumpur FIR.

b. Pilots should note that from SFC-FL370, the provision of Air Traffic Services in the defined area is delegated to Singapore.



c. Pilots should note that in the absence of Jakarta Radar, Singapore FIR covers the following areas from FL245-FL600.




Figure 3 – Airspace within Jakarta FIR covered Singapore ACC if Jakarta ACC is offline

d. Singapore Radar will initially provide arrival clearance into Singapore before passing you to another FIR due to the complex airspace design if required. However, a change of runway can be initiated by either Singapore Approach or Singapore Arrival if required/requested.

Phraseology

Entering from uncontrolled airspace

From	To	Frequency	Transmission
SIA913	WSJC5	133.600	Singapore Radar, Singapore 913, position 5nm TEGID, FL360.
WSJC5	SIA913	133.600	Singapore 913, Singapore Radar. Squawk 2201.
SIA913	WSJC5	133.600	Squawk 2201, Singapore 913.
Set transponder code to 2201.			
WSJC5	SIA913	133.600	Singapore 913, identified. Maintain FL360.
SIA913	WSJC5	133.600	Maintain FL360, Singapore 913.

Entering from controlled airspace

From	To	Frequency	Transmission
SIA913	WSJC5	133.600	Singapore Radar, Singapore 913, position 5nm TEGID, FL360, squawk 6501.
WSJC5	SIA913	133.600	Singapore 913, Singapore Radar. Maintain FL360.
SIA913	WSJC5	133.600	Maintain FL360, Singapore 913.

Procedural Control

From	To	Frequency	Transmission
WSJC5	SIA913	133.600	Singapore 913, request your time estimate over TODAM.
SIA913	WSJC5	133.600	Over TODAM at time 1037z, Singapore 913.
WSJC5	SIA913	133.600	Singapore 913, roger time 1037z, report overhead TODAM.
SIA913	WSJC5	133.600	Report overhead TODAM, Singapore 913.

Arrival Clearance

From	To	Frequency	Transmission
WSJC5	SIA913	133.600	Singapore 913, arrival clearance.
SIA913	WSJC5	133.600	Pass your message, Singapore 913. OR Ready to copy, Singapore 913.
WSJC5	SIA913	133.600	Singapore 913, cleared to Singapore KARTO2B arrival, expect ILS approach runway 20R.
SIA913	WSJC5	133.600	Cleared to Singapore KARTO2B arrival, expect ILS approach runway 20R, Singapore 913.

Handoff to Jakarta Radar (WIIF_NA_CTR)

From	To	Frequency	Transmission
WSJC5	SIA913	133.600	Singapore 913, contact Jakarta Radar 134.02(5).
SIA913	WSJC5	133.600	Contact Jakarta Radar 134.02(5), Singapore 913.

Initial Descent Clearance

From	To	Frequency	Transmission
WIIFTG	SIA913	133.325	Singapore 913, when ready, descend FL320 to be level by NIXEB.
SIA913	WIIFTG	133.325	When ready, descend FL320 level by NIXEB, Singapore 913.
WIIFTG	SIA913	133.325	Singapore 913, contact Singapore Radar 134.2
SIA913	WIIFTG	133.325	Contact Singapore Radar 134.2, Singapore 913.

Contacting Singapore Radar

From	To	Frequency	Transmission
SIA913	WSJC4	134.200	Singapore Radar, Singapore 913, descending FL320.
WSJC4	SIA913	134.200	Singapore 913, Singapore Radar. Descend FL160.
SIA913	WSJC4	134.200	Descend FL160, Singapore 913.

Exemplar Situations of Restrictions

From	To	Frequency	Transmission
WSJC4	SIA913	134.200	Singapore 913, on conversion, speed 280 knots. OR Singapore 913, for separation/sequence, turn left heading 250. OR Singapore 913, hold KARTO as published, FL250, 1.5 minute legs.
SIA913	WSJC4	134.200	On conversion speed 280 knots, Singapore 913. OR Turn left heading 250, Singapore 913. OR Hold KARTO as published FL250, 1.5 minute legs, Singapore 913.

Singapore Approach (WSSS_APP)

a. Singapore Approach manages initially all airborne traffic inbound for mainland Singapore, selected flights into Johor (WMKJ), and flights into Tanjung Pinang TMA (WIDD/WIDN).
b. The Transition Level is **FL130.**
    I. Note that altitude is regarded as feet (ft) under the Transition Altitude and Flight Level (FL) above the Transition Level.
    II. No altitude clearances will be given in the Transition Layer. The Transition Layer is the altitude block between the Transition Altitude and Transition Level.
c. Listen carefully to all ATC instructions. ATC will employ the following phraseology listed below:
    I. Proceed direct…
    II. Reduce Speed…
    III. Turn left/right heading…
    IV. Hold…
    V. Maintain present heading (after <waypoint>)
d. If you are unable to follow any of the above instruction from ATC, inform the controller immediately.

Phraseology

Transferring to Singapore Approach (WSSS_N_APP)

From	To	Frequency	Transmission
WSJC4	SIA913	134.200	Singapore 913, contact Singapore Approach 124.05.
SIA913	WSJC4	134.200	Contact Singapore Approach 124.05, Singapore 913.

Contacting Singapore Approach

From	To	Frequency	Transmission
SIA913	NAPP	124.050	Singapore Approach, Singapore 913, descending F160.
NAPP	SIA913	124.050	Singapore 913, Singapore Approach, descend 11000ft, QNH 1011.
SIA913	NAPP	124.050	Descend 11,000ft, QNH 1011, Singapore 913.

Exemplar Situations of Restrictions

From	To	Frequency	Transmission
NAPP	SIA913	124.050	Singapore 913, (reduce) speed 220 knots. OR Singapore 913, for separation/sequence, fly present heading. OR Singapore 913, for separation/sequence, turn right heading 330.
SIA913	NAPP	124.050	Reduce speed 220 knots, Singapore 913. OR Fly present heading, Singapore 913. OR Turn right heading 330, Singapore 913.

Joining Inner Hold Instructions

From	To	Frequency	Transmission
NAPP	SIA913	124.050	Singapore 913, hold KEXAS as published, 11,000ft, 1 minute legs.
SIA913	NAPP	124.050	Hold KEXAS as published, 11,000ft, 1 minute legs, Singapore 913.

Exiting Inner Hold Instructions

From	To	Frequency	Transmission
NAPP	SIA913	124.050	Singapore 913, exit the hold, continue on the STAR. OR Singapore 913, exit the hold, turn left heading 110.
SIA913	NAPP	124.050	Exit the hold, continue on the STAR, Singapore 913. OR Exit the hold, turn left heading 110, Singapore 913.

Singapore Arrival (WSSS_F_APP)

a. Singapore Approach will handle all aircraft airborne arriving to Singapore Changi Airport.
b. Please listen to instructions carefully. Phrases listed below may be used:
    I. Reduce Speed…
    II. Maintain 180knts till 8nm *(maintain 180 knots till 8 miles)*
    III. Maintain 150knts till 4nm *(maintain 150 knots till 4 miles)*
    IV. Maintain present heading (after <waypoint>)
c. If you are unable to meet any speed restrictions, inform the controller immediately.
d. Radar vectors and speed control will be used. Please follow all instructions and listen carefully for your callsign.
e. Do note if you are on the STAR, **DO NOT CLEAR ROUTE DISCONTINUITY** after these waypoints, **Expect Radar Vectors from**:
    I. Runway 02
        i. SAMKO
        ii. SANAT
    II. Runway 20
        i. BIDUS
        ii. NYLON
        iii. BIPOP
f. If no heading was assigned to you before you reach the waypoints stated above, FLY YOUR LAST HEADING.

Phraselogy

Transferring to Singapore Arrival (WSSS_F_APP)

From	To	Frequency	Transmission
NAPP	SIA913	124.050	Singapore 913, contact Singapore Arrivals 119.3
SIA913	NAPP	124.050	Contact Singapore Arrivals 119.3, Singapore 913.

Simultaneous Independent Parallel Approach

From	To	Frequency	Transmission
ARR	SIA913	119.300	Singapore 913, descend 2500ft, turn left heading 170 degrees, report established on the localiser runway 20R.*
SIA913	ARR	119.300	Descend 2500ft, turn left heading 170 degrees, report established on the localiser runway 20R, Singapore 913.
SIA913	ARR	119.300	Singapore 913 established localiser runway 20R.
ARR	SIA913	119.300	Singapore 913, cleared ILS approach runway 20R.
SIA913	ARR	119.300	Cleared ILS approach runway 20R, Singapore 913.

*When instructed to report established on the localiser, this means you are cleared to intercept the localiser for the runway but NOT cleared to descend on the glide. Pilots should maintain their last assigned altitude until cleared to descend on the glide.

Simultaneous Dependent Parallel Approach

From	To	Frequency	Transmission
ARR	SIA913	119.300	Singapore 913, descend 2500ft, turn left heading 170 degrees, cleared ILS approach runway 20R.
SIA913	ARR	119.300	Descend 2500ft, turn left heading 170 degrees, cleared ILS approach runway 20R, Singapore 913.

Final Approach Speed Control

From	To	Frequency	Transmission
ARR	SIA913	119.300	Singapore 913, reduce speed 180 knots till 8 mile final. OR Singapore 913, reduce speed 150 knots till 4 mile final. OR Singapore 913, reduce speed 180 knots till 8 mile final, thereafter speed 150 knots till 4 mile final.
SIA913	ARR	119.300	Reduce speed 180 knots till 8 mile final, Singapore 913. OR Reduce speed 150 knots till 4 mile final, Singapore 913. OR Reduce speed 180 knots till 8 mile final, thereafter speed 150 knots till 4 mile final, Singapore 913.

Singapore Tower (WSSS_TWR)

a. Singapore Tower will handle all aircraft movements for the runway.
b. Phrases listed below may be used.
    I. Reduce to minimum approach speed.
    II. Continue Approach runway….
    III. Turn right/left on [taxiway]
    IV. Vacate W6 taxi V7/Vacate W7 taxi V8. (For RWY 20R only)
c. To maximize runway occupancy, please exit the runway as soon as possible, do ensure that your tail is clear of the stop bar.

LDA (Landing Distance Available)

RWY	02L	02C	02R	20R	20C	20L
LDA	4000m	4000m	4000m	3260m	4000m	4000m

Phraseology

Transferring to Singapore Tower (WSSS_1_TWR)

From	To	Frequency	Transmission
ARR	SIA913	119.300	Singapore 913, contact Singapore Tower 118.6
SIA913	ARR	119.300	Contact Singapore Tower 118.6, Singapore 913.

Contacting Singapore Tower

From	To	Frequency	Transmission
SIA913	TWR1	118.600	Singapore Tower, Singapore 913, ILS approach runway 20R.
TWR1	SIA913	118.600	Singapore 913, Singapore Tower, continue approach runway 20R. OR Singapore 913, Singapore Tower, surface wind 210 degrees 10 knots, runway 20R, cleared to land. OR Singapore 913, Singapore Tower, reduce minimum approach speed, continue approach runway 20R.
SIA913	TWR1	118.600	Continue approach runway 20R, Singapore 913. OR Runway 20R, cleared to land, Singapore 913. OR Reduce minimum approach speed, continue approach runway 20R, Singapore 913.

Vacate Instructions

From	To	Frequency	Transmission
TWR1	SIA913	118.600	Singapore 913, vacate W6 turn right W. OR Singapore 913, vacate W6 turn right W. OR Singapore 913, vacate W6 taxi V7.
SIA913	TWR1	118.600	Vacate W6 turn right W, Singapore 913. OR Vacate W6 turn left W, Singapore 913. OR Vacate W6 taxi V7, Singapore 913.

*If you are unable to vacate at the specific taxiway, inform the controller immediately.

*Note: The runway is the most critical part of any aerodrome. It is the pilot's responsibility to ensure that the aircraft Is **FULLY CLEAR** of the Runway Stopbar including the tail.*

*Please utilise the charts provided and **brief yourself** on where taxiways are located and where to taxi initially. This is to ensure you know where to taxi and avoid stopping on the Rapid Exit Taxiway.*

Listen carefully where the Tower Controller instructs you to turn as you exit the runway. Refer to ANNEX A for more information.

Go Around

From	To	Frequency	Transmission
TWR1	SIA913	118.600	Singapore 913, due runway occupied, go around, I say again go around, climb 3000ft continue runway heading.
SIA913	TWR1	118.600	Going around, climb 3000ft continue runway heading, Singapore 913.
TWR1	SIA913	119.300	Singapore 913, contact Singapore Departure 120.3.
SIA913	TWR1	118.600	Contact Singapore Departure 120.3, Singapore 913.


Transferring to Singapore Ground (WSSS_3_GND)

From	To	Frequency	Transmission
TWR1	SIA913	118.600	Singapore 913, contact Singapore Ground 124.3
SIA913	TWR1	118.600	Contact Singapore Ground 124.3, Singapore 913.

Singapore Ground (WSSS_GND)

a. Singapore Ground will handle all aircraft movements on the ground excluding the runway.
b. When requesting pushback and start-up, please indicate your bay/gate.
c. When requesting taxi to runway, please indicate the runway.
d. Please listen carefully to the controller. Different phrases may be used such as
    I. Hold Short
    II. Holding Point
    III. Hold Position
    IV. Continue Taxi
    V. Traffic is a [Airline/Aircraft] taxiing from Right to Left, once traffic is clear…
    VI. Behind the [Airline/Aircraft] at your [Direction], taxi…

Ground Area of Responsibility



Phraseology

Taxi to runway

i. To ease an overload of information, SINvACC Controllers will only issue you a maximum of 3 instructions and 1 holding point/hold short instruction.
ii. Listen carefully if the instruction is to hold short or taxi to the holding point.

From	To	Frequency	Transmission
SIA913	GND3	124.300	Singapore Ground, Singapore 913, turning right W.
GND3	SIA913	124.300	Singapore 913, Singapore Ground, taxi W, R hold short R7.
SIA913	GND3	124.300	Taxi W, R, hold short R7, Singapore 913.

Transfer of Controller to Singapore Ground (WSSS_2_GND) on taxiway R

From	To	Frequency	Transmission
GND3	SIA913	124.300	Singapore 913, contact Singapore Ground 121.72(5).
SIA913	GND3	124.300	Contact Singapore Ground 121.72(5), Singapore 913.
Switch COM1 to 124.300.			
SIA913	GND2	121.725	Singapore Ground, Singapore 913, R short of R7.
GND2	SIA913	121.725	Singapore 913, Singapore Ground, taxi R R7. OR Singapore 913, Singapore Ground, traffic is a Singapore Airlines Boeing 787 taxiing from your left to right. Once traffic is clear, taxi R R7. OR Singapore 913, Singapore Ground, traffic is a Singapore Airlines Boeing 787 taxiing at your two o'clock onto R. Once traffic is clear, taxi R R7.
SIA913	GND2	121.725	Taxi R R7, Singapore 913. OR After the Singapore Airlines Boeing 787 is clear, taxi R R7.

*Do take note that phraseology could differ for each situation. Ensure that you identify the traffic and follow ATC instructions to give way accordingly. If you are unable to identify the traffic, inform the controller immediately.

-END OF DOCUMENT-