# Operating Systems (02340123) Summary - Spring 2025

#### Razi & Yara

Based on the course lectures by Dr. Leonid Raskin, the slides of Prof. Dan Tsafrir, and the tutorial slides.

This is not official course material, but a summary of the course by students.

All copyrights belong to the original authors.

July 23, 2025

# Contents

I Lectures & Tutorials	3
Topic 1: Introduction	4
Topic 2: Processes & Signals	6
Topic 3: IPC - Inter-Process Communication	13
Topic 4: Boot & Modules	18
Topic 5: Scheduling	23
Topic 6: Context Switch	33
Topic 7: Synchoronization (& Deadlocks)	36
Topic 8: Networking	46
Topic 9: Virtual Memory	55
Topic 10: Interrupts	66
Topic 11: Page Cache	70
Topic 12: Storage	75
II Overall Summary	85
III Highlights and Notes	91

# Part I Lectures & Tutorials

### Topic 1: Introduction

Operating System (OS) An Operating System's job is:

- Coordinate the execution of all SW, mainly user apps.
- Provide various common services needed by users & apps.
- An OS of a physical server controls its physical devices, e.g. CPU, memory, disks, etc.
- An OS of a virtual server only *believes* it does. There's another OS underneath, called **hypervisor** which fakes it.

Using an OS allows us to take advantage of "virtualization":

- Server Consolidation: Run multiple servers on one physical server. This is allows for better resource utilization, smaller spaces, and less power consumption.
- Disentangling SW from HW: allows for backing up/restoring, live migration, and HW upgrade. This give us the advantage of easier provisioning of new (virtual) servers = "virtual machines", and easier OS-level development and testing.

Most importantly, an OS is **reactive**, "event-driven" system, which means it waits for events to happen and then reacts to them. This is in contrast to typical programs which run from start to end without waiting for external events to occur to invoke them.

	Typical Programs	OS
What does it	Get some input, do some	Waits & reacts to "events"
typically do?	processing, produce output,	
	terminate	
Structure	Has a main function, which is	No main; multiple entry
	(more or less) the entry point	points, one per event
Termination	End of main	Power shutdown
Typical goal	$\sim$ Finish as soon as possible	Handle events as quickly as
		possible $\Rightarrow$ more time for
		apps to run

**Event Synchronousation** OS events can be classified into two:

- Asynchronous interrupts: keyboard, mouse, network, disk, etc. These are events that can happen at any time and the OS must be ready to handle them.
- Synchronous: system calls, divide by zero, page faults, etc. These are events that happen as a result of the program's execution and the OS must handle them immediately.

**Multiplexing** Multiplexing is the ability of an OS to share a single resource (e.g. CPU, memory, disk) among multiple processes or threads. This allows for better utilization of resources and enables multiple applications to run concurrently. \*Multiprogramming means multiplexing the CPU recourse.

Notable services provided by an OS:

- 1. **Isolation:** Allow multiple processes to coexist using the same resources without stepping on each other's toes. Usually achieved by multiplexing the CPU, memory, and other resource done by the OS. However, some physical resources know how to multiplex themselves, e.g. network cards, sometimes called "self-virtualizing devices".
- 2. **Abstraction:** Provides convenience & portability by:
  - offering more meaningful, higher-level interfaces
  - hiding HW details, making interaction with HW easier.

**CPL** (Current Privilege Level) The CPU defines two levels: (1) User mode, CPL=3, (2) Kernel mode, CPL=0. Privileged instructions require kernel mode to execute them, such as disk access. Syscalls (system calls) our only gateway as users to execute commands in kernel mode, where a syscall raises the CPL to 0 and executes a specific request.

# Topic 2: Processes & Signals

#### **Processes**

Each process is an instance of a program in execution, which includes:


- **Program code:** The actual code of the program.
- **Process state:** The current state of the process, including the program counter, registers, and memory management information.
- Process control block (PCB): A data structure used by the OS to manage the process, containing information such as process ID, process state, CPU registers, memory management information, and I/O status information.

A process doesn't have direct access to its PCB, it is managed by the OS (kernel space), which is task\_struct current.

Each PCB contains: real\_parent, parent, children, siblings,...

Each process has a task\_struct current pointer to its PCB.

 Process ID (PID): A unique 32-bit identifier assigned to each process by the OS. Typically only the 15 LSB bits are used. The OS keeps a hash table of PID → PCB.



**Process States** A process can be in one of the following states:

- Running: The process is currently being executed by the CPU.
- **Ready:** The process is ready to be executed but is waiting for the CPU to become available.




Figure 1: Process States

- Waiting: The process is waiting for an event to occur, such as I/O completion or a signal.
- **Zombie:** The process has terminated but its PCB is still in the system, waiting for the parent process to read its exit status. In this state, the process has released almost all of its resources, but the PCB is still in the system.

state Field in PCB Each PCB keeps a 32bit state variable where each bit indicates one of the following states:

- 1. TASK\_RUNNING: The task is either running or ready to run
- 2. TASK\_ZOMBIE: The task has terminated but is still in the system
- 3. TASK\_INTERRUPTIBLE: The task is waiting for an event to occur, but it can be interrupted by signals and come back to TASK\_RUNNING state.
- 4. TASK\_UNINTERRUPTIBLE: The task is waiting for an event to occur, but it cannot be interrupted by signals. e.g. page fault, you can't run anything (or handle any other signals) until the page fault is handled to an end.
- 5. TASK\_STOPPED: The task has been stopped in a controlled manner by a different task, e.g. by a debugger or by the user pressing Ctrl+Z in the terminal.

As we saw in "ATAM", each process can only access a certain set of utilities and functions, those who require privilege level 3 (user mode). So to access the OS services, a process must use **system calls** which are functions provided by the OS that allow processes to request services from the OS. System calls are typically implemented in the OS kernel and provide a controlled interface for processes to interact with the OS.

Each syscall, in case of an error, will change the errno variable to indicate the error type. The errno variable is a global variable that is set by system calls and some library functions in the event of an error to indicate what went wrong. It is defined in the header file errno.h. Note: errno is not reset to 0 after a successful syscall, so it must be checked immediately after the syscall, and be reset before usage if need be (if there is not any other way to make sure there is an error indeed).

i.e. errno = <Number of Last Syscall Error>;

As noted above, each process must be wait()ed for by its parent process to be able to release its PCB and resources. This is done by the wait() syscall, which suspends the calling process until one of its children terminates. In case the parent process terminates before the child, the child process becomes an orphan process and is adopted by the init process (PID 1), which will then wait for it to terminate and release its resources.

**Process Management** The OS offers various system calls to manage processes, including: (More details in the functions reference)

- fork(): Creates a new process by duplicating the calling process. The new process is called the child process, and the calling process is called the parent process. For the child, the return value is 0, and for the parent its the pid of the child, (on failure -1 for parent).
- exec(): Replaces the current process image with a new process image, effectively running a different program in the same process.
- wait(): Suspends the calling process until one of its children terminates.
- exit(): Terminates the calling process and releases its resources.
- getpid(): Returns the process ID of the calling process.
- getppid(): Returns the process ID of the parent process.
- kill(): Sends a signal to a process, which can be used to terminate or suspend the process.

Parent Vs. Real Parent Process The real parent process is the one that created the current process using fork(), or the one that adopted it in case the real parent terminated before the child.

The parent process is the one *tracing* the current process, e.g. using ptrace(). The parent process is the one that will receive signals from the current process, e.g. SIGCHLD when the current process terminates.

In most cases, the parent process is the real parent process, but it can be different in some cases, e.g. when a process is being traced by a debugger.

**Daemon Processes** A daemon process is a background process not controlled by the user. To run a process as a daemon use nohup <command> &.

Daemon names usually end with the letter "d", e.g. sshd (SSH daemon), httpd (HTTP daemon), etc.

Idle & Init The idle process is the first one that the system loads, with pid=0, and it utilized hlt when no process is ready to run. The next one is init which is created by idle, with pid=1, and it created all other processes. Every orphan process becomes the child of init.

**Process List** The OS maintains a cyclic double linked list of all processes, allowing for efficient process management and scheduling. The list starts with idle then init, where idle is the head of the list pointed to by init\_task.

#### Signals

**Signals** Signals are "notifications" sent to a process to asynchronously notify it that some event has occurred.

- \* Receiving a signal only occurs when returning from kernel mode, which in turn invokes the corresponding signal handler, i.e. signal handling is in user mode.
  - \*\* Default signal handling actions: Either die or ignore
- \*\*\* In case of several signals from different types, they will be handled by the order of their definition in the signals register.

Each signal has a name, a number (1-31), and a default action. All but 3 signals can be blocked, i.e. ignored until the process is ready to handle them. The 3 signals that cannot be blocked are:

- SIGKILL: Used to forcefully terminate a process. (Process becomes a zombie)
- SIGSTOP: Used to suspend the receiving process. (Make it sleep) The signals is sent when the user presses Ctrl+Z in the terminal. Note: In truth Ctrl+Z sends the SIGTSTP signal, however, we don't learn about the differences between the two signals in this course.
- SIGCONT: Used to resume a suspended process, usually sent after a SIGSTOP signal. The handler for this signal can be customized but it will always resume the process.

SIGSTOP and SIGCONT are useful for debugging purposes, allowing the user to pause and resume the execution of a process.

Signal Handling A process can define a custom signal handler for a specific signal using the signal() or sigaction() preferred system calls. To ignore a signal, the process can set its handler to SIG\_IGN. To restore the default action for a signal, the process can set its handler to SIG\_DFLT. codesignal\_struct is the kernel structure in PCB that holds the signal handlers for the process.

**Signal Masking** A process can block signals using the sigprocmask() system call, which allows the process to specify a set of signals to block. This is allows the process to overcome *Race Conditions* resulted from the asynchronous nature of signals.

This is achieved by maintaining a set of currently blocked signals & a set of masked signals which is saved in the PCB.

Blocked Signals = mask array.

Pending Signals = signals that were sent to the process while it was blocked, and will be handled when the process unblocks them.

When handling a signal, the handler masks signals of the same type (of the one being handled), to prevent problems of reentrancy.

#### **Common Signals** the following are some of the most common signals:

- 1. SIGSEGV, SIGBUS, SIGILL, SIGFPE: These are driven by the associated (HW) interrupts The OS gets the associated interrupt, then the OS interrupt handler sees to it that the misbehaving process gets the associated signal, lastly the signal handler is invoked.
  - SIGSEGV: Segmentation violation (illegal memory reference, e.g., outside an array).
  - SIGBUS: Dereference invalid address (null/misaligned, assume it's like SEGV).
  - SIGILL: Illegal instruction (trying to invoke privileged instruction).
  - SIGFPE: Floating-point exception (despite the name, all arithmetic errors, not just floating point. e.g., division by zero).
- 2. SIGCHLD: Parent (and then real parent) get it whenever fork()ed child terminates or is SIGSTOP-ed.
- 3. SIGALRM: Get a signal after some specified time, can be set using the alarm() & setitimer() system calls.
- 4. SIGTRAP: When debugging/single-stepping a process, the debugger can set a breakpoint in the code, which will cause the process to receive a SIGTRAP signal when it reaches that point.
- 5. SIGUSR1, SIGUSR2: User-defined signals, user can decide the meaning of these signals and their handlers.
- 6. SIGPIPE: Write to pipe with no readers.
- 7. SIGINT: Sent when the user presses Ctrl+C in the terminal. The default action is to terminate the process, but it can be customized.
- 8. SIGXCPU: Delivered when a process used up more CPU than its soft-limit allows: soft-hard limits are set using the setrlimit() system call. Soft-limits warn the process its about to exceed the hard-limit, Exceeding the hard-limit will cause SIGKILL to be sent to the process.
- 9. SIGIO: Can configure file descriptors such that a signal will be delivered whenever some I/O is ready.
  - Typically makes sense when also configuring the file descriptor to be *non-blocking*, e.g., when read()ing from a non-blocking file descriptor, the system call immediately returns to user if there's currently nothing to read. In this case, errno will be set to EAGAIN=EWOULDBLOCK.
- 10. **Signal 0:** The null signal, which is used to test for the existence of a process.


#### Signals Vs. Interrupts

	interrupts	signals
Who triggers them?	Hardware:	Software (OS),
Who defines their	CPU cores (sync) & other	HW is unaware
meaning?	devices (async)	
Who handles them?	OS	processes
Who (un)blocks them?		
When do they occur?	Both synchronously &	Likewise, but, technically,
	asynchronously	invoked when returning
		from kernel to user

# Topic 3: IPC - Inter-Process Communication

#### Threads & IPC

**Multiprocessing** Using several CPU cores (=processors) for running a single job to solve a single "problem".



Threads A process can have multiple threads, which share (nearly) everything, including the process's memory space, file descriptors, heap, static data, code segment and more.

However, each thread has its own stack, registers, and program counter. But they can still access each other's stack since they share the same memory space.

Note that *Global/Static Variables & Dynamically Allocated Memory* are shared between threads since they are stored in the Static Data Segment and the Heap, respectively, which are shared between all threads of a process. However, *Local Variables* are not shared between threads since they are stored in the stack, which is unique to each thread.

	Unique to Process	Unique to pthread
Registers (notably PC)	Y	Y
Execution stack	Y	Y
Memory address space	Y	N
Open files	Y	N
Per-open-file position (=offset)	Y	N
Working directory	Y	N
User/group credentials	Y	N
Signal handling	Y	N

**OpenMP** Open Multi-Processing (OpenMP) consists of a set of compiler 'pragma' directives that allows the compiler to generate multi-threaded code for parallel execution.

**Pthreads** POSIX threads (pthreads) is a standard for multi-threading in C/C++. It provides a set of functions to create and manage threads, as well as to synchronize them.

#### **Common Functions**

# The following are some of the most commonly used pthread functions:

- pthread\_create(...): Creates a new thread that starts executing a given function. The thread ID is stored in a pointer.
- pthread\_self(): Returns the thread ID of the calling thread. This ID is internal to the pthread library.
- pthread\_exit(...): Terminates the calling thread and makes its exit status available to any thread that joins it.
- pthread\_cancel(...): Sends a request to terminate a specified thread. The thread's exit status is set to PTHREAD\_CANCELED.
- pthread\_join(...): Blocks the calling thread until a specified thread terminates, then retrieves its exit status and frees its resources.

Thread Termination

Reason for Termination	Thread Termi- nates?	Process Termi- nates?
Calling	Yes	Not
$pthread_exit()$		necessarily
Calling	Yes	Not
<pre>pthread_cancel()</pre>		necessarily
Return from	Yes	Not
$\mathtt{start\_routine}$		necessarily
Calling exit()	Yes	Yes
Illegal operation	Yes	Yes
Return from main	Yes	Yes

**Threads in Linux** In Linux, threads are implemented as \*processes\* with a shared memory space. Each thread has its own PCB, but they share the same memory address space, file descriptors, and other resources. Threads do not have family ties between one another.

**Thread Groups** A thread group is a collection of threads that share the same process ID (PID) and are managed by the same process. In Linux, each thread group has a unique group ID (TGID), which is the PID of the first thread in the group. The TGID is used to manage signals and other resources shared by the threads in the group.

Since each thread has his own PCB and PID, to send a signal to all threads in a thread group, the signal must be sent to the TGID (the PID of the first thread in the group). Each PCB contains a field thread\_group which points to the head of the linked list of all threads in the group.

The syscall getpid() returns the TGID of the calling thread. The personal "PID" of each thread is called TID (Thread ID), which is the same as the personal "PID" of the thread's PCB. The syscall gettid() returns the TID of the calling thread.

clone() The syscall: clone(int (\*fn)(void \*), void \*child\_stack, int flags, void \*arg); is used to create a child process that shares resources with the parent process. The parameters are:

- fn: A pointer to the function that will be the main function of the child process.
- child\_stack: A pointer to the user stack that will be used by the child process. The highest address of the stack is passed, i.e. the top of the stack.
- arg: A pointer to the argument that will be passed to the function fn.
- flags: A bitmask that specifies which resources will be shared between the parent and child processes. The flags can include:
  - CLONE\_VM: Share the same memory address space.
  - CLONE\_FS: Share the same filesystem information (e.g., current working directory).
  - CLONE\_FILES: Share the same file descriptor table.
  - CLONE\_PARENT: Share the same parent process as the parent of the calling thread.
  - CLONE\_THREAD: Create a new thread in the same thread group.

The return value is the TID of the child.

**File Descriptors** A non-negative integer representing an I/O "channel" on some device. File descriptors are saved in the process's PCB inside the FDT (File Descriptor Table), which is an array of pointers to *file objects*, each representing an open file or device. So in fact, an FD is an index to a kernel array of channels.

Processes don't share PCB nor FDT but they can share file descriptors, i.e. two processes can have the same file descriptor pointing to the same file object, which allows them to share the same open file or device. Upon forking, the child process inherits a copy of the parent's FDT. Note: Threads do share the same FDT.

Pipes A pipe is a unidirectional communication channel between two processes, allowing one process to send data to another. Pipes are a pair of two file descriptors int pipe\_fd[2]. Each integer is a handle to a kernel communication object ("file"), pipes reside only on DRAM (memory) and never on the disk, and they are not in the filesystem. (pipes are anonymous shared pages)

• pipe\_fd[0] = read side of the communication channel.

- pipe\_fd[1] = write side of the communication channel.
- Everything written via pipe\_fd[1] can be read via pipe\_fd[0].
- Blocking: If the read side is empty, the read operation will block until data is written to the write side. If the write side doesn't have enough space for <u>all</u> the data, the write operation will block until space is available.
- EOF: If the write side is closed and the pipe is empty, the read operation will return 0, indicating EOF (End of File).
- SIGPIPE: Writing to a pipe whose read end is close()d will result in a SIGPIPE signal.

**FIFO** (Named Pipe) A FIFO is a named pipe that allows for communication between unrelated processes (no family connection), i.e. it's a public "file". FIFO is a file even though it is NOT on the disk, though it can be swapped there.

To make a FIFO, use the mkfifo(const char \*pathname, mode\_t mode) system call, which creates a special file in the filesystem with path pathname and permissions mode. The FIFO can then be opened by any process using the open() system call, just like a regular file. The FIFO is bidirectional, thus having one FD.

A process that opens FIFO for read only, will block until another process opens it for write, and vice versa. If one opens it as both read & write (O\_RDWR) then it will not be blocking. \*The read write rules are similar to the one of pipe.

FIFOs are not removed from the system automtically (unlike pipes whom do), so they have to be *explicitly* removed by rmunlink for example. Meaning a closed FIFO can be reopened until removed completely.

Multi-tasking	Multi-programming	Multi-processing
Having multiple	Having multiple jobs in the	Using multiple processors
processes time slice	system (either on the same core	(CPU cores) for the same
on the same CPU	or on different cores). i.e. the	job in parallel. i.e. creating
core.	existence of multiple processes in	multiple threads to run on
	the system, regardless of whether	different cores for the same
	they are running on the same	process.
	core or not.	

#### Intro. Context Switching & Caching

Context Switching is the process of saving the state of a currently running process and restoring the state of another process to allow it to run. This is done by the OS kernel and is necessary for multitasking, allowing multiple processes to share the CPU.

- Context = the state of a process, including its registers, program counter, stack pointer, and memory management information.
- Context Switch = the process of saving the context of the currently running process and restoring the context of another process.

Context Switch Overhead consists of two components:

- **Direct Overhead:** The measurable time it takes to perform the context switch, which includes saving the current process's state and restoring the next process's state.
- Indirect Overhead: The time it takes for the CPU to cache the new process's data, which can be significant if the new process's data is not already in the CPU cache.

Cashing The CPU cache is a small, fast memory that stores frequently accessed data to speed up access times. The Cache allows the CPU access to a fast memory that is closer to the CPU than the main memory (DRAM), and a larger one than the CPU registers. The cache works because of the *Principle of Locality*:

- **Temporal Locality:** If at one point in time a particular memory location is referenced, then it is likely that the same location will be referenced again soon.
- Spatial Locality: If a particular memory location is referenced at a particular time, then it is likely that nearby memory locations will be referenced soon.

Copy-on-Write (COW) The fork() system call creates a copy of the address space of the parent, but:

- It only creates a *logical* copy.
- There is no physical duplication of the memory pages, until we really need to write to them (from either process). And even then, only the page that is being written to is duplicated. (More details in the virutal memory lectures)

User Level Threads (ULTs) are threads that are managed by the user-level library, rather than the OS kernel. ULTs are not visible to the OS, which means that the OS does not know about them and does not schedule them. This allows for faster context switching between ULTs, but it also means that the OS cannot take advantage of multiple CPU cores to run ULTs in parallel.

The usage of ULTs is mainly for concurrent programming, where we want multiple multiple tasks to progress in parallel without the overhead of kernel-level threads.

### Topic 4: Boot & Modules

#### Booting the OS

**Operating System at Power ON** When powering on a PC, the OS has yet to load into the memory, as it resides on the disk. So we need to load the OS from the disk to the memory, but we need the OS to do that! So the solution is hierarchal booting:

- 1. The BIOS code is loaded into the memory (DRAM) and the CPU starts executing it.
- 2. The BIOS loads the first sector of the disk (MBR) to the memory
- 3. The MBR code loads the boat loader
- 4. The boot loader loads the kernel of Linux
- 5. The kernel loads the init process (/init) and runs it

BIOS (Basic Input/Output System) The BIOS is located in the motherboard, loaded to the same memory location always, and is the first code that runs when the computer is powered on. It performs the following tasks:

- Identify the hardware components of the system that are connected.
- Check if basic hardware components are working properly (screen, keyboard, etc)
- Search for the device (from a pre-defined list) that enables booting (bootable device)
- If the device is not found, the BIOS shows an error message and stops the booting process. Otherwise, it loads the first sector of the device to a constant place in memory.

MBR (Master Boot Record) The bootable device holds in the first sector (512 bytes), the MBR, which is a very basic assembly program that is used to load the boot loader, since it requires more space than the MBR can provide.

**Boot Loader (Grub)** GRUB (GRand Unified Bootloader) is a boot loader package from the GNU Project. It allows users to choose between multiple operating systems at boot time and can load a variety of operating systems, including Linux, Windows, and others.

Loading the Kernel The boot loader loads the kernel in the following steps:

- 1. Load the compressed kernel image from the disk to the memory.
- 2. Load a basic initial filesystem (initramfs or initrd)
  - The initial filesystem includes the necessary modules for the linux kernel to find and load the real filesystem.
- 3. The kernel runs the script /init (typically a shell script) from the initial filesystem.
- 4. The /init script loads the necessary drivers and mounts the real filesystem instead of the initial one.
- 5. After the real filesystem is mounted, the linux kernel runs the /sbin/init program.

#### **Modules**

Kernel Modules are pieces of code that can be loaded into the kernel at runtime, without need to recompile the kernel. New modules can be loaded only in kernel mode (CPL=0). The primary use for modules is to implement drivers for hardware devices, but they can also be used to implement new system calls, filesystems, and other kernel features. Beware Modules run in kernel mode so they have access to everything.

The advantages of using kernel modules are: (1) Allowing to add functionality without rebooting, (2) Allowing for faster compile time of the kernel, (3) The kernel will use less space, (4) Allowing to add support for new hardware.

To implement a module we use (Beware to use kernel functions and not user functions, e.g. "kprintf" instead of "printf"):

- int init\_module(void): The function that is called when the module is loaded into the kernel.
- void cleanup\_module(void): The function that is called when the module is unloaded from the kernel.
- module\_param(name, type, perm): A macro to declare a module parameter. each parameter must have a default value.

**Devices & Drivers** Devices are represented by special files in the filesystem, which are called **device files**, which are located in /dev. To communicate with a device, we use the standard file operations (open, read, write, close) on the device file. The kernel uses **device drivers** to handle the communication with the device. Device drivers are kernel modules that implement the necessary functions to communicate with the device.

Block vs Character Devices Character devices are ones that can be accessed as a stream of bytes (e.g. keyboard, mouse, etc.), typically for transferring data and in a sequential matter. Block devices are ones that can be accessed only in multiples of blocks (e.g. hard drives), typically for storing data in random-access data.

Character Devices Each character device is represented by a major number (1-512) and a minor number (0-255). The major number identifies the driver associated with the device, while the minor number identifies the specific device. Each major number can have multiple minor numbers, and vice versa. Both numbers are found in the inode of the device file.

Registering a new device is done by: (default permissions are write for owner, read for others)

**Pseudo-Devices** Linux provides pseudo-character devices that are not connected to any physical hardware. All of these devices share a major number of 1.

write()	read()	device file
Succeeds and does nothing (data is discarded).	Immediately returns EOF (end of file).	/dev/null
	Returns a sequence of null bytes (\0) of the requested	/dev/zero
Immediately returns ENOSPC (no space left on device).	length.	/dev/full
		/dev/random
Contributes to the kernel's entropy pool from "noise".	Returns a stream of random bytes generated at runtime.	/dev/urandom
		/dev/arandom

```
struct file {
...
loff_t f_pos;
...
void *private_data;
...
struct file_operations* *f_op;
...
struct file_operations* *f_op;
...
```

Figure 2: File struct and file operations

file operations Each file struct has a file\_ops field, which is a pointer to a struct that contains pointers to functions that implement the file operations for that file. These functions include:

- int (\*open) (struct inode \*, struct file \*): Called when the file is opened. If open is null, it will succeed.
- int (\*release) (struct inode \*, struct file \*): Called when the <u>last</u> instance of the file is closed. If release is null, it will succeed.
- int (\*flush) (struct file \*): Called when the file is closed (every time an FD is closed, not just the last one). If flush is null, it will succeed.
- ssize\_t (\*read) (struct file \*, char \*, size\_t, loff\_t \*): Called when the file is read. If read is null, it will return (-EINVAL).
- ssize\_t (\*write) (struct file \*, const char \*, size\_t, loff\_t \*): Called when the file is written to. If write is null, it will return (-EINVAL).
- loff\_t (\*llseek) (struct file \*, loff\_t, int): Called when the file's offset is to be changed.
- int (\*ioctl) (struct inode \*, struct file \*, unsigned int cmd\_id, unsigned long arg): Allows adding additional functionality to the device. Arg is an optional parameter.

**Drivers as Modules** Drivers can be implemented as kernel modules, where <code>init\_module()</code> will register the driver using <code>register\_chrdev()</code>. Note that registering a driver only connects it with a major number, and not to a device. Unregistering a driver is done through <code>cleanup\_module()</code> that uses <code>unregister\_chardev()</code>.




Figure 3: Driver and Module File Flows

Registering a Driver To register a driver, we use the register\_chrdev() function, which adds the driver to the kernel's array of character drivers, chrdevs[], where the index is the major number. It also adds the driver to /proc/devices file, which lists all registered drivers and their major numbers (both character & block drivers), character & block devices use different arrays thus multiples of the same number can exist. chrdevs[] is an array of driver names + pointers to their file\_ops structs.

To allocate a major number, Linux allows 512 number options, and each driver can register itself with a major number of its choice (could cause conflicts), or could use 0 which then returns the first available number from 512 to 1.

Unregistering a driver using unregister\_chrdev() will remove the driver from chrdevs[], but will not remove the device from /dev.

# Topic 5: Scheduling

#### Batch (Non-Preemptive) Scheduling

**Supercomputers** Supercomputers are compromised of multiple nodes, each with multiple CPU cores, and are used for running large-scale computations. Users submit **batch jobs** to the supercomputer with a specified time limit and size. Terminology:

- **Size** = the number of CPU cores to use for the job. Jobs are said to be *wide/big* or *narrow/small*.
- Runtime = the time limit for the job to run. Jobs are said to be *short* or *long*.

Metrics for Performance Evaluation When evaluating the performance of a <u>batch</u> scheduling algorithm, we use the following metrics:

• Average Wait Time: The wait time of a job is the interval between the time the job is submitted to the time the job starts to run. i.e.

$$waitTime = startTime - submitTime$$

• Average Response Time: The response time of a job is the interval between the time the job is submitted to the time the job is terminated. i.e.

$$responseTime = terminateTime - submitTime$$


**Note:** Average wait time and response time differ only by a constant factor, which is the job's average runtime.

• The Slowdown / Expansion Factor: The ratio between a job's response time and its runtime. i.e.

$$slowdown = \frac{responseTime}{runtime}$$
$$= \frac{(waitTime + runtime)}{runtime}$$
$$= 1 + \frac{waitTime}{runtime}$$

- Utilization: The percentage of time the resource (CPU) is busy.
- Throughput: How much work is done in one time unit.

#### Batch Scheduling Algorithms




First-Come, First-Served (FCFS) Jobs are scheduled by their arrival time. If there are enough free cores, a newly arriving job starts to run immediately, otherwise it wait, sorted by arrival time, until enough cores are available.

- **Pros:** Simple to implement (FIFO Queue), fair to all jobs.
- Cons: Creates <u>fragmenation</u>, small/short jobs might wait a long time.

EASY Scheduling (= FCFS + backfilling) Backfilling optimization: A short waiting job can jump over the head of the wait queue (i.e. start at an earlier time) provided that it doesn't delay the job head of the FCFS queue.

The algorithm: whenever a job arrives or terminates, try to start the job head of the FCFS wait queue. Then, iterate over the rest of teh waiting jobs (in FCFS order) and try to backfill them.

- **Pros:** Better utilization (less fragmentation), short jobs have a better chance of running sooner.
- Cons: Must know runtimes in advance.



Shortest Job First (SJF) Instead of ordering jobs by their arrival time, we order them by their (typically estimated) runtimes.

- Pros: Optimal in terms of performance (min. avg. wait time).
- Cons: Unfair as it may cause starvation of long jobs. starvation = can theorically wait forever

Convoy Effect Slowing down all (possibly short) processes due to currently servicing a very long process. FCFS suffers from this effect, as does EASY scheduling but to a lesser

extent. SJF without assumptions also suffers from this effect but to an even lesser extent.

**Optimality of SJF** As mentioned above, SJF is optimal in terms of performance, in particular, it minimizes the average wait time. **Claim:** Given:

- 1. A 1-core system where all jobs are serial.
- 2. All process arrive together.
- 3. Their runtimes are known in advance.

Then: The average wait time of SJF is equal to or less than the average wait time of any other batch scheduling order.

Fairer Varients of SJF Motivation: disallow job starvation.

- Shortest-Job Backfilled First (SJBF): Exactly like EASY in terms of servicing the head of the wait queue in FCFS order (and not allowing anyone to delay it), but the *backfilling* traversal is done in SJF order, i.e. the next job to be backfilled is the one with the shortest estimated runtime.
- Largest eXpansion Factor (LXF): LXF is similar to EASY, but instead of ordering the wait queue in FCFS, it orders jobs based on their current slowdown (greater slowdown = higher priority).

On every job arrival or termination, the expansion factors are recalculated and the wait queue is resorted, so that the job with the largest expansion factor is always at the head of the queue. Both the head of the queue and the backfilled jobs are serviced in LXF order.

#### Preemptive Schedulers

**Preemption** is the act of suspending one job (process) in favor of another even though it is not finished yet.

Why do we need preemption? Preemption is necessary for **responsiveness** and when the runtime of jobs vary or unknown in advance.

**Quantum** is the maximum amount of time a process is allowed to run before it is preempted. Quantum is typically milliseconds to 10s of milliseconds, and is often set per-process. Usually a CPU-bound process gets long quanta while an I/O-bound process gets short quanta with higher priority.

#### Performance Metrics for Preemptive Schedulers we use the following:

- Average Wait Time: As before, the wait time of a job is the interval between the time the job is submitted to the time the job starts to run. Note that the wait time does not include the preemption wait times (i.e. the time the job is waiting for its turn to run again after being preempted).
- Response Time (=Turnaround Time): Like before, the response time is the time from process submission to process completion. *Note* that with preemption we get:

responseTime > waitTime + runtime

due to the preemption wait times and Context Switches cost.

- Overhead: How long a context switch takes, and how often context switches happen. (Should be minimized)
- Utilization & Throughput: Same as before, but we may want to account for context switch overhead.
- Makespan Time: The time it takes for the system to finish all jobs in the system.

Round Robin (RR) Scheduling Processes are arranged in a cyclic read-queue. The algorithm works in the following steps:

- 1. The head process runs until its quantum is exhausted.
- 2. The head process is then preempted (suspended) and moved to the tail of the queue.
- 3. The scheduler resumes the next process in the circular list.
- 4. When we've cycled through all processes in the run-list (and we reach the head process again), we say that the current "epoch" is over, and the next epoch begins.

**Note:** RR Requires a timer interrupt; Typically it's a periodic interrupt (fires every few milliseconds) and upon receiving the interrupt, the OS checks if its time to preempt. **Note 2:** For small enough quantum, it's like everyone of the N processes advances in 1/N of the speed of the core called sometimes virtual time. With huge quantum infinity, RR becomes FCFS.

Gang Scheduling Think of it as RR for parallel systems. It works as follows:

- Time is divided to slots (seconds or minutes).
- Every job has a "native" time slot.
- Algorithm attempts to fill holes in time slots by assigning to them jobs from other native slots (called "alternative" slots).
- Algorithm attempts to minimize slot number using **slot unification** when possible.
- Rarely used in practice, if lots of memory is swapped out upon context switch, context switch overhead is too high.

Detailed explanation about alternative slots and slot unification:

Alternative Slots To further enhance resource utilization, the gang scheduling algorithm attempts to fill holes in time slots. A job has a "native" time slot where it is primarily scheduled to run. However, if there are idle processors in other time slots (termed "alternative" slots), the scheduler can assign jobs from their native slots to run in these otherwise unused resources. This allows jobs to get more processing time without interfering with the primary scheduling of other jobs.

**Slot Unification** This technique aims to minimize the total number of active time slots. If, after some jobs have completed, the remaining jobs in two different time slots can fit into a single slot without conflict, the scheduler can merge them. By unifying slots, the overall cycle time of the matrix is reduced, which can lead to shorter job turnaround times and improved system throughput.




Figure 4: Gang Scheduling

**Batching vs. Preemption** Assume: (1) A single core system (2) All jobs arrive together (3) Context switch price = 0. Then: There exists a non-preemptive algorithm such that:

avgResponseTime(non-preemptive) < avgResponseTime(preemptive)

As a result, SJF is also optimal relative to preemptive scheduling (if our assumptions hold).

 $avgResponseTime(SJF) \le avgResponseTime(batch or preemptive scheduler)$ 

Connection Between RR & SJF Assume: (1) A single core system (2) All jobs arrive together (and only use CPU, no I/O) (3) Quantum is uniform + no context switch overhead. Then:

$$avgResponse(RR) \le 2 \cdot avgResponse(SJF)$$

i.e. RR at best is as good as SJF, and at worst is 2X slower.

Shortest Remaining Time First (SRTF) If we remove the assumption that all jobs arrive together, then SJF is not optimal anymore, as it may cause a convoy effect. SRTF is a preemptive version of SJF, where the scheduler always runs the job with the shortest remaining time. i.e. when a new job arrives or an old one finishes, the scheduler runs the job with the shortest remaining time, even if it means preempting the currently running job. This is optimal in terms of average response time, but it can cause starvation for long jobs.

**Selfish RR** Selfish RR is a variant of RR where only "old enough" processes are running in the run-queue. i.e.

- New processes wait in a FIFO queue, not yet scheduled.
- Older processes scheduled using RR.
- New processes are scheduled when either of the following happens:
  - 1. The run-queue is empty (i.e. no ready-to-run "old" processes exist).
  - 2. "Aging" is being applied to new processes (a per-process counter increases over time); When the counter passes a certain threshold, the "new" process becomes "old" and is transferred to the RR queue.
- Fast Aging = Algorithm resembles RR, Slow Aging = Algorithm resembles FCFS.

#### General Purpose Schedulers (Priority-Based & Preemptive)

**Scheduling using priority** Every process is assigned a priority. The priority reflects how "important" it is in that time instance, and it changes dynamically over time. Process with higher priority are favored, as they are scheduled before lower priority processes. The concept of priority can be also applied in batch scheduling. e.g. SJF:priority = runtime (smaller runtime = higher priority), FCFS:priority = arrival time (earlier arrival = higher priority), etc.

Negative Feedback Principle The schedulers of all general-purpose OSes employ a negative feedback policy: Running reduces priority to run more & Not running increases priority to run. As a result, I/O-bound processes (that seldom use the  $\overline{CPU}$ ) get higher priority than  $\overline{CPU}$ -bound processes (that use the  $\overline{CPU}$  a lot). This ensures that I/O-bound processes are responsive.

Multi-Level Priority Queue A multi-level priority queue consists of several RR queues, each associated with a priority. processes migrate between the queues so they have a dynamic priority, "important" processes move up (e.g. I/O-bound) and "unimportant" processes move down (e.g. CPU-bound). Priority is greatly affected by the **negative feedback principle**, i.e. by CPU consumption:

- I/O-bound  $\iff$  move up
- CPU-bound  $\iff$  move down

Some schedulers allocate short quanta to higher priority queues, and some don't or even do the opposite.

#### $Linux \leq 2.4$ Scheduler

All of the definitions below are relative only to the Linux  $\leq 2.4$  scheduler, which is a preemptive priority-based scheduler that uses a multi-level priority queue. **Note:** A task is either a process or a thread.

**Standard POSIX Scheduling Policies** POSIX dictates that each task is associated with one of three scheduling policies:

- "Realtime" Policies:
  - 1. SCHED\_RR (round-robin): The time slice is calculated as (100 \* HZ)/1000 HZ = number of times interrupts per second.
  - 2. SCHED\_FIFO (first-in, first-out): doesn't give up the CPU unless: (1) voluntarily using sched\_yeild(), (2) I/O operation, (3) preempted by a higher priority task.
- The default policy:
  - 3. SCHED\_OTHER (the default time-sharing policy)

POSIX defines the meaning of SCHED\_OTHER (aka SCHED\_NORMAL in Linux) is decided by the OS. Typically employs some multi-level priority queue with the negative feedback loop.

Realtime tasks are always favored by the scheduler. Only an <u>admin</u> can set a task to run with a realtime policy, the users can set a policy using the sched\_setscheduler syscall. The multi-level priority queue is leveled from 0-99: <u>In kernel</u> - 0 is the highest, <u>In user</u> - 99 is the highest (e.g. syscalls), as kernel calculates (99-input).

**Epoch** As mentioned before, every runnable task gets allocated a quantum, which is the CPU time the task is allowed to consume before is it's stopped by the OS. Whenever all quanta of all *runnable* tasks become zero a **new epoch** begins. In this case we allocate additional running time to *all tasks* (runnable or not).

#### **Definitions**

• Task's Priority: Every task is associated with an integer, the higher the value the higher the priority to run. Every task has a *static* priority and a *dynamic* priority.

- Static Priority: A fixed value that indirectly determines the maximal quantum for the task. Fixed unless the user invokes nice() or sched\_setscheduler syscalls.
- Dynamic Priority: Is the both the remaining time for the task and its current priority. The dynamic priority decreases over time (while running), if it reaches zero the task is preempted until the next epoch. The dynamic priority is *reset* to the static priority at the beginning of each epoch.
- **HZ:** Linux gets a timer interrupt HZ times per second, i.e. it gets a timer interrupt every  $\frac{1}{HZ}$  seconds. The default value of HZ is 100 for x86/Linux2.4.
- Tick: A tick can mean either of the following:
  - The time that elapses between two consecutive timer interrupts, i.e.  $\frac{1}{HZ}$  seconds.
  - The timer interrupt itself that fires every  $\frac{1}{HZ}$  seconds.

Ticks are used to determine the scheduler timing resolution, the OS measures the passage of time in ticks. The units of the *dynamic priority* are ticks.

- task\_struct: Every task is represented by a *task\_struct* object, which contains (among other things):
  - 1. nice static priority
  - 2. counter dynamic priority
  - 3. processor the last CPU core the task ran on
  - 4. need\_resched boolean
  - 5. mm task's memory address space
- task's nice There are two types of nice, user nice and kernel nice. The kernel's nice is the *static priority* of the task, which is between 1...40 (higher is better) and the default is 20. The user's nice is the parameter passed to the nice() syscall, which is between -20...19 (lower is better). Values below 0 require superuser privileges.

 $kernel\_nice = 20 - user\_nice$ 

- task's counter The dynamic priority of the task. It is calculated as follows:
  - Upon task creation:

```
child.counter = parent.counter/2; (round down)
parent.counter = child.counter; (round up)
```

- Upon a new epoch:

```
task.counter = task.counter/2 + NICE_TO_TICKS(task.nice)
= half of prev dynamic + convert_to_ticks(static)
```

- When running: decrement each tick by 1 (task.counter-) until it reaches 0.

The **NICE\_TO\_TICKS** function scales 20 (=DEF\_PRIORITY) to number of tick compromising **50+ ms**. By default, scales 20 to 5+ ticks:

```
#define NICE_TO_TICKS(kern_nice) ((kern_nice) / 4 + 1) So the quantum range is therefore: (recall that 1 \text{ tick} = 10 \text{ ms})
```

```
-(1/4 + 1=) 1 \text{ tick} = 10 \text{ ms (min.)}

-(20/4 + 1=) 6 \text{ ticks} = 60 \text{ ms (default)}

-(40/4 + 1=) 11 \text{ ticks} = 110 \text{ ms (max.)}
```

- task's processor Logical ID of CPU core upon which task has executed most recently, if task is currently running, then this is the core it is running on.
- task's need\_resched A boolean flag that is checked by kernel just before switching back to user-mode. If set, check if there's a "better" task than the one currently running, and if so, switch to it. Can be thought of as a per-core rather than per-task flag as it is checked only for the currently running task.
- task's mm A pointer to the task's memory address space. (More details in the virtual memory lectures)

The scheduler is implemented in the kernel/sched.c file, and the task structure is defined in include/linux/sched.h. The scheduler is compromised of 4 main functions:

- 1. goodness(task, cpu) Given a task and a CPU core, returns how "desirable" it is for that CPU. We compare tasks by this value to determine which task to run next.
- 2. schedule() Actual implementation of the scheduler. Uses goodness to decide which task to run on a given core.
- 3. \_\_wake\_up\_common(wait\_queue q) Wakes up task(s) when waited-for event has happened. e.g. completion of I/O operation, or a signal being sent to the task.
- 4. reschedule\_idle(task t) Given a task, check whether it can be scheduled on some core. Preferably on an idle core, but if not then by preempting a less "desirable" task on a busy core. Note: used by the schedule() & \_\_wake\_up\_common() functions.

Counter Convergence Claim: The counter value of an I/O-bound task will quickly converge to  $2\alpha$  geometric series. Corollary: By default, an I/O-bound task will have a counter of 12 ticks (=120 ms) as long as it remains I/O-bound and consumes negligible CPU time.

**The Drawback** The scheduler is a linear scheduler, i.e. it runs in O(n) time. It was replaced by the "O(1)" scheduler which then was replaced by the "Completely Fair Scheduler" (CFS) which is  $O(\log n)$ .

#### CFS (Completely Fair Scheduler)

**CFS** The CFS is a preemptive, priority-based scheduler that aims to provide a fair distribution of CPU time among all tasks while maintaining efficiency and scalability  $(O(\log N))$ .

vruntime - Virtual Run Time Every running task obtains virtual run-time. Ideally all tasks maintain an equal amount of virtual run time, and that's the goal. The algorithm stores the minimum & maximum virtual run times at all times. The minimal virtual runtime task is always the next task to run.

sched\_latency The CFS uses a sched\_latency parameter to determine the length of an epoch (48 ms). Each task gets a quantum of  $Q_i = \text{sched\_latency}/N$ , where N is the number of tasks.

The algorithm also defines a minimum quantum length, sched\_min\_granularity, which is the smallest time slice a task can receive (6 ms). So in practice, tasks can have a longer epoch than defined by sched\_latency.

**CFS Algorithm** The CFS uses a red-black tree (similar to AVL tree) to maintain the tasks in the system, ordered by their vruntime. New tasks are inserted into the tree, with their vruntime set to the max\_vruntime. Tasks that come back from I/O operations or are woken up have their vruntime set to the min\_vruntime.

**CFS Priorities & Weights** The CFS uses a priority system based on the *nice* value of the task. The **vruntime** is adjusted based on the task's priority, with higher priority tasks gaining lower **vruntime**. The lower the nice the higher the priority, and for each nice value, there is a corresponding weight (high weight for high priority)

Let  $W_0$  be the weight of nice=0, then:

$$VR_i = \frac{W_0}{W_i} \cdot \Delta T$$

$$Q_i = \frac{W_i}{\sum_k W_k} \cdot \text{sched\_latency}$$

# Topic 6: Context Switch

Caller Rules	Callee Rules
Before the function call:	On function entry:
• Save caller-saved registers on the stack (rax, rcx, rdx, rdi, rsi, r8{r11).	• Create a new stack frame (save the old rbp and point to the new top of the stack).
• Pass the first 6 arguments in registers	• Allocate space for local variables.
(from left to right: rdi, rsi, rdx, rcx, r8, r9).	• Save callee-saved registers on the stack (rbx, r12{r15}).
• Pass the rest of the arguments (beyond the first six) on the stack.	
• Use the call machine instruction. Upon return from the function:	On function exit:
• Restore the saved registers.	• Place the return value in the rax register.
	• Restore the saved registers.
	Deallocate local variables.
	• Return to the old stack frame (restore the previously saved rbp).
	• Use the ret machine instruction.

Two types of context switches:

Forced Context Switch (Preemption)	Initiated Context Switch
The kernel preempts (i.e., forcibly takes) the CPU from the process, for example, following:	The process voluntarily gives up the CPU, for example, by means of:
<ul> <li>A timer interrupt (scheduler_tick) which reveals that the time slice allocated to the current process has expired.</li> <li>An asynchronous event that wakes up a process with a higher priority than the currently running process. For example: a disk interrupt or the release of a lock for which a process was waiting.</li> </ul>	<ul> <li>A blocking system call (such as wait(), read(),), which puts the process into a waiting state.</li> <li>The exit() system call, which terminates the process.</li> <li>The sched_yield() system call - a dedicated system call to yield the CPU.</li> </ul>

**Preemption in Kernel** The (new) linux kernel is preemptive, meaning that a process running in the kernel can be preempted!

When switching context we switch the kernel stacks of the tasks (each task has a corresponding kernel stack in the kernel space).

The only gateway in linux for context switches is the function schedule(), which can not be interrupted.

#### **Context Switch Saving** when a context switch occurs we save:

- The stack, heap, code (memory regions) are in the memory space of the process, so they do not need to be backed up.
- open files and other data are already residing in the PCB, which is in the memory.
- Registers & flags (the CPU state) are backed up to the kernel stack of the thread on a field called thread\_struct.
- The base of the kernel stack base is pointed to by TSS.sp0 (the top of the kernel stack) so it needs to be backed up.

TSS (Task State Segment) is a unique data structure for each CPU core that contains the state of the currently running task. It is pointed to by TR, and it contains the TSS.sp0 field which points to the top of the kernel stack of the currently running task.

Each PCB contains a thread\_struct field which contains the state of the task, including the CPU registers, flags, and most importantly, the head of the kernel stack.

To do a context switch we do the following steps:

- 1. context\_switch(): This function calls for switching the memory space, and calls the next function -
- 2. \_\_switch\_to\_asm(): The macro that saves the current context and loads the next one. More specifically, it backs the registers & the rsp of the kernel and loads the new one, pops the backed registers (of the new one) and then calls the next function -
- 3. \_\_switch\_to(): This function updates the TSS.sp0 field to point to the new kernel stack, and returns to return address of \_\_switch\_to\_asm() or ret\_from\_fork().

do\_fork() is the kernel function used by fork() and clone() to create the new context of the new thread:

- 1. It allocates a new PCB for the new thread, and a new kernel stack
- 2. Calls for copy\_thread(), which fills the kernel stack of the child process to be as it was the one who called fork() and then \_\_switch\_to\_asm()
- 3. Copies to the child process most of the PCB fields and data from the father.
- 4. Connects the child process to its family connections.
- 5. Adds the child process to the global process list. and to the pid hash table
- 6. Transfers the child task to TASK\_RUNNING state and adds it to the runqueue.
- 7. The functions returns the pid of the child, and this value is returned from the father too.

copy\_thread() copies the registers from the parent to the child, sets the rax register of the child to 0, and updates the return address that is saved on the stack to the ret\_from\_fork() function, and finally sets the task kernel stack head (rsp) to the new kernel stack of the child process.

ret\_from\_fork() is the function that pops the registers from the kernel stackand returns
to the user code (using sysret)

do\_exit() is the function that is called when a process exits (either by calling exit() or by signals/interrupts). It does the following:

- 1. Frees the resources of the task, closes all open files, frees memory, etc.
- 2. Sets the exit value to the exit\_code field of the PCB.
- 3. Updates family ties: all children become orphans (children of init), the parent keeps the pointer to the exiting child, all siblings lose their pointer to the exiting process.
- 4. Updates the task state to TASK\_ZOMBIE
- 5. Calls the function schedule() to run a different task. The task runtime is finished by \_\_switch\_to\_asm().

# Topic 7: Synchoronization (& Deadlocks)

Race Condition We say that the program suffers from a race condition if the outcome is nondeterministic and depends on teh timing of uncontrollable, un-synchronized events

Memory (Cache) Coherency is the mechanism that ensures that any change to a shared piece of data in one cache is eventually propagated to all other caches, preventing processors from working with outdated information.

Cache Consistency it dictates how memory operations (reads and writes) from one processor can be observed by other processors in the system. If store operations are immediately seen by other cores and they can't be reordered with load operations, then consistency holds. (but it's not a necessary condition)

Cache **coherency** relates to a **single** memory location, while cache **consistency** relates to **multiple** memory locations. coherency ensures cores see writes in some order that makes sense, and is uniform across all cores. Consistency is about the order of different read and write operations across multiple memory locations, and how they are observed by different cores.

To enforce ordering for memory consistency, explicit **memory fence** (memory barrier) must be used. The fence makes all store-s that happened before the fence visible to all load-s after the fence, notably, flushes the store buffer to teh memory system.

**Atomicy** In programming, atomicity means an operation, or a series of operations, appears to happen all at once, without any interruption from other processes. This ensures that either the entire operation completes successfully, or it has no effect at all, preventing partial or incomplete results.

In <u>single core</u> CPUs each instruction is atomic, i.e. it can't be interrupted by another instruction. In <u>multi-core</u> CPUs, atomicity is only achieved by using special instructions or locks that ensure no other thread can access the data while the operation is being performed. (e.g. lock; instruction)

**Critical Section** A group of operations we need to atomically execute is called a **critical section**. Atomicity will make sure other threads don't see partial results! The critical section can be a uniform code across all threads, or it can be a different.

Mutual Exclusion (mutex) is a property of a critical section that ensures that only one thread can execute it at a time and never simultaneously. Thus a critical section is a "serilaization point".

#### Locks

Lock A lock is an abstraction that supports two operations: acquire(lock) and release(lock). Semantically: It's a memory fence, only one thread at a time can acquire the lock and other simultaneous attempts to acquire are postponed until the lock released. Implementing a lock is nowadays done using hardware support with special instructions that ensure mutual exclusion.

**Spinlock** A spinlock is a lock that uses busy-waiting to acquire the lock. i.e. it repeatedly checks if the lock is available and only then acquires it. Spinlocks are typically used in low-level code where the overhead of sleeping and waking up is too high, or when the critical section is very short. If interrupt or signal handlers access the same data as the critical section, then the we must disable them, or make sure they acquire the lock too!

```
struct spinlock {
       uint locked; // 0 = unlocked, 1 = locked
2
  };
3
5 // The volatile keyword is crucial here. It tells the compiler that the value at addr
       can be changed by external factors (like another CPU core or hardware) at any time.
       This prevents the compiler from making optimizations like caching the value in a
       register, forcing it to read directly from memory every time.
   inline uint xchg(volatile uint *addr, uint newval) {
       // atomic [oldval = *addr, swap(*addr, newval)]
       // xchq is atomic
       // lock adds a memory fence
9
       uint oldval;
       asm volatile("lock; xchg %0, %1"
11
                    : "+m" (*addr), "=r"(oldval):
12
                    "1"(newval):
13
                    "cc");
14
       return oldval;
15
16 }
17
   void acquire(struct spinlock *lock) {
18
       disable_interrupts();
19
       while (xchg(&lock->locked, 1) != 0) {
20
           // busy-wait until the lock is available
21
           enable_interrupts(); // if we want to enable
22
           disable_interrupts(); // interrupts while spinning
23
       }
24
  }
25
26
27
   void release(struct spinlock *lock) {
       xchg(&lock->locked, 0); // set the lock to unlocked
28
       enable_interrupts();
29
```

30 }

#### Listing 1: Spinlock Implementation

Other Atomic Operations We know of 3 atomic operations that are used to implement spinlocks:

- 1. **xchg(addr, newval)** Atomically exchanges the value at **addr** with **newval** and returns the old value.
- 2. test\_and\_set(bool \*b) Atomically sets \*b to true and returns the old value of \*b.
- 3. cas(int \*p, int old\_val, int new\_val) (Compare-and-Swap) Atomically compares the value at \*p with old\_val, and if they are equal, sets \*p to new\_val and returns true. Otherwise, it returns false and does not change \*p.

#### **Mutex Lock**

Spinning or Blocking A lock can be implemented using either spinning or blocking:

- Spin (busy wait) The thread repeatedly checks if the lock is available, consuming CPU cycles while waiting. This is suitable for short critical sections where the wait time is expected to be very short. Note that the user can not block context switches.
- Block (go to wait/sleep) The thread goes to sleep and is woken up when the lock is available. This is suitable for longer critical sections where the wait time can be significant.

Rule of thumb: If the critical section is shorter than the time a context switch takes, then use spinning, otherwise use blocking.

Unlike spinning which can be done by the user, going to sleeping is done by a request to the OS (since it involves changing process states).

Mutex interface the following are the common ops:

- mutex\_init(mutex\_t \*mutex, const mutex\_attr\_t \*att): Initializes the mutex object. The att parameter can be used to set attributes.
- mutex\_lock(mutex\_t \*mutex): Acquires the mutex lock. If the lock is already held by another thread, the calling thread will block until the lock is available.
- mutex\_trylock(mutex\_t \*mutex): Attempts to acquire the mutex lock without blocking. If the lock is available, it acquires it and succeeds. Otherwise if the lock is already held by another thread, it fails and continues.
- mutex\_unlock(mutex\_t \*mutex): Releases the mutex lock. If there are threads waiting for the lock, one of them will be woken up.
- mutex\_destroy(mutex\_t \*mutex): Destroys the mutex object and releases any resources associated with it. The mutex must not be locked when this function is called, otherwise it fails.

**Undefined Actions** In a correct implementation of a mutex, only the thread that holds the lock can call mutex\_unlock(). The following are undefined behaviors:

- re-locking the mutex by the same thread that holds it.
- unlocking the mutex by a thread that does not hold it.
- unlocking a mutex that is not locked.

Condition Variables A condition variable is a synchronization primitive that allows threads to wait for certain conditions to be met, while inside a critical code section without the need to block the CPU! A condition variable is always associated with a mutex, and it allows threads to wait for a condition to be signaled by another thread. The typical usage pattern is as follows:

- A thread acquires the mutex lock.
- The thread checks the condition. If the condition is not met, it calls <code>cond\_wait(cond\_var, mutex)</code> to release the mutex (it must be held by the thread beforehand) and block until another thread signals the condition variable.
- When the condition is met, another thread can call cond\_signal(cond\_var) to wake up one waiting thread or cond\_broadcast(cond\_var) to wake up all waiting threads.
- The waiting thread must re-acquire the mutex lock before continuing execution. (part of the cond\_wait() operation)
- The thread should then check the condition again and proceed if it is met.

# Semaphores

The Basics A semaphore is usually implemented as a counter and a queue of waiting threads. A task that announces it's waiting for a resource will get the resource if it is available or will go to sleep otherwise. In case it goes to sleep it will be awakened when the resource becomes available to it.

The fields of the semaphore are as follows:

• Value (integer) (the counter):

If value is Non-negative, it indicates the number of available resources. If value is negative, it indicates the number of tasks waiting for the resource.

• A queue of waiting task:

Every task that is waiting for the resource to become available is stored in this queue. When the value is negative, |value| = queue.lenght|/

The functions used to manipulate the semaphore are:

- wait(sem): Decrements the value of the semaphore. If the value after decrementing is negative, the task goes to sleep and is added to the queue of waiting tasks. Otherwise, it continues execution.
- signal(sem): Increments the value of the semaphore. If the value was negative before incrementing, it wakes up one task from the queue of waiting tasks.

**Semaphore Implementation** The semaphore is implemented in the kernel and not part of the course material. However, the following is a demonstration of the problem known as **lost wakeups**.

```
struct semaphore_t {
       int value;
2
       wait_queue_t wait_queue;
3
       lock_t lock;
4
  };
5
6
   void wait(semaphore_t *sem) {
       lock(&sem->lock);
8
       sem->value--;
9
       if (sem->value < 0) {</pre>
10
           enque(self, &sem->wait_queue);
11
           unlock(&sem->lock);
                                               // This is the problem!
12
           block(self);
13
       } else
14
           unlock(&sem->lock);
   }
16
   void signal(semaphore_t *sem) {
18
       lock(&sem->lock);
19
20
       sem->value++;
       if (sem->value <= 0) {</pre>
21
           p = dequeue(&sem->wait_queue); // Part of the problem too!
22
           wakeup(p);
23
       }
24
25 }
```

Listing 2: Lost Wakeups Problem

The problem with the above implementation is that we release the the lock before going to sleep but after joining the queue, so if another task calls signal() redbefore we go to sleep, it will wake us up (without being asleep) and we will exit the wait queue so no one will be

able to wake us up again. This is known as the lost wakeups problem.

Spinlock vs. Semaphore

	spinlock	semaphore
wait by	spinning	sleeping
granularity	fine	coarse: might wait for a long
		time
complexity	lower	greater: typically uses lock
expressiveness	lower	greater: equivalent to lock if
		maximal value=1 (called "binary
		semaphore"); otherwise,
		counting how many resources are
		available
interface	strict: must acquire	relaxed: may signal(s) without
ordering	before release, must	wait(s), may wait(s) without
	release after acquire	signal(s)
interface	strict: release only	relaxed: signal may be invoked
dependence	invoked by locker	by threads that didn't previously
		wait and vice versa

**Amdahl's Law** Amdahl's Law is a formula that gives the maximum improvement to an overall system when only part of the system is improved.

So what is the maximal expected speed when parallelizing?

- Let n be the number of threads.
- Let s be the fraction of the program that is strictly serial  $(0 \le s \le 1)$ .
- Let  $T_n$  be the time it takes to run the algorithm with n threads.
- Then, optimally:

$$T_n = T_1 \times \left(s + \frac{1-s}{n}\right) \ge T_1 \times sem$$

• The speedup is defined as:

$$speedup = \frac{T_1}{T_n} = \frac{1}{s + \frac{1-s}{n}} \le \frac{1}{s}$$

#### Deadlocks & Livelocks

**Progress** At any given time, at least one thread is able to do the critical section, i.e. No "deadlock" or "livelock" occur.

- **Deadlock** A situation in which two or more competing actions are each waiting for the other to finish, and thus no one ever finishes. e.g. two threads waiting for each other to release a lock.
- Livelock A situation in which two or more competing actions are each trying to finish, but they keep interfering with each other, and thus no one ever finishes. e.g. two threads trying to acquire a lock, but they keep releasing it and trying again.
- Starvation A situation in which a thread is unable to finish its critical section because it is always preempted by other threads. e.g. a low-priority thread that is never scheduled because high-priority threads keep running.

**Deadlock State** We say that a <u>system</u> is in a deadlock state, and not a given process. **The popular definition:** A set of processes is deadlocked if each process in the set is waiting for an event that only a process in the set can cause. **Our definition:** A set of processes is deadlocked if each process in the set is waiting for a resource held by another process in the set (The set can be a subset of the set of all process). **Note:** Deadlocks are tough to deal with since the system is not guaranteed to enter a deadlock if it is prone to deadlocks.

Resource types Resource types can be either physical (e.g. Disk/Disk Block, NIC (network controller), Keyboard, etc.) or logical (e.g. Process Table / node in a tree, etc.).

Some resources only have one instance (e.g. keyboard) and others have multiple instances (e.g. producer-consumer ring).

Therefore, **Locks** are a synchronization construct that reflect a single instance, while **Semaphores** are a synchronization construct that reflect multiple instances of a resource type. **Note:** A binary semaphore is equivalent to a mutex lock.

**Resource Allocation Graph** When considering resource management, it is convenient to represent the system state with a directed graph. We can represent the system in one of two ways:

- Multi-Resource Allocation Graph: A directed graph where: (1) "round" nodes are processes (2) "square" nodes are resources with the dots in them representing the number of instances (3) edges from process to resource represent request (4) edges from resource to process represent allocation.
- Single Instance Resources (Simplified): We can simplify the system with a directed graph where: (1) nodes are processes (2) edges mark dependencies between processes, i.e. an edge from process A to process B means that A is waiting for a resource held by B.




Figure 5: Resource Allocation Graph

Necessary Conditions for Deadlocks All of the following must hold for a deadlock to occur:

#### 1. Mutual Exclusion:

At least one resource must be held in a non-shareable mode, i.e. only one process at a time can use the resource. if every resource is shareable or used by a single process, then no deadlock can occur.

#### 2. Hold & Wait:

Processes holding resources are allowed to request additional resources without releasing the resources they already hold. If processes must release all resources before requesting new ones or atommically request all resources, then no deadlock can occur.

#### 3. Circular Wait:

There must be a circular chain of two or more processes, each waiting for a resource held by the next process in the chain. i.e. P(i) wait for resource held by P((i+1)%n). Otherwise there exists at least one process that doesn't need to wait

#### 4. No Resource Preemption:

Resources cannot be forcibly taken from a process holding them, they must be voluntarily released. If resources held can be released after some period of time, then no deadlock can occur.

**Dealing with Deadlocks** There are 3 main strategies to deal with deadlocks:

- Deadlock Prevention: Violate one of the 4 conditions necessary for deadlock to occur.
- Deadlock Detection & Recovery: Allow the system to enter deadlock state, but put in place mechanisms that can detect, and then recover from this situation. Typically refers to killing one or more processes in the deadlock state, using the algorithmic resource-graph problem.

• Deadlock Avoidance: Use a resource allocation graph to detect potential deadlocks and avoid them by not allocating resources that would lead to a deadlock. (e.g. Banker's Algorithm). Requires full knowledge of the system's resource requirements and current allocation.

**Deadlock Prevention** There are 4 conditions for deadlock to occur, and we can prevent deadlocks by violating one of them:

#### 1. No Mutual Exclusion:

Making all resources sharable, by implementing some data structure using only hardware-supported atomic operations. These algorithms are called "lock free".

#### 2. No Hold & Wait:

Each process must request all resources it needs at once, or release all resources before requesting new ones. The system either grants all resources or none and block the process. **Con:** Processes will hold on to their resources for more time than they actually need them, which limits concurrency and hence limits performance.

3. No Circular Wait: the most usable flexible method

Impose a strict ordering on resources, i.e. number all resources in one sequence. Processes can only request resources in increasing order, a process that wants to acquire a resource that has a lower order must first release all resources it holds that have a higher order.

#### 4. No "No Resource Preemption":

When needed, choose a victim process and release its resources, allowing other processes to continue.

e.g. if there isn't enough memory, we can backup the victim's state to disk and release all its memory, or just kill the process.

Deadlock Detection & Recovery If there is <u>only one instance</u> of each resource type, then a deadlock can be detected by checking for cycles in the <u>simplified resource allocation</u> graph. In the <u>general case</u> (multiple instances of each resource type), Necessary conditions for deadlock are not sufficient, nevertheless, we can still detect deadlocks but it is *outside the scope of this course*.

After a deadlock is detected, we can recover from it by: (1) Killing one or more processes in the deadlock state until the deadlock is resolved, or (2) Forcibly preempting resources from one or more processes in the deadlock state. Finding the minimal set of processes to kill/preempt is a hard problem.

In literature, Detection and Recovery refer to the algorithmic problem of finding the minimal set of processes to kill/preempt in the resource graph.

**Deadlock Avoidance** The system can avoid deadlocks by not allocating resources that would lead to a deadlock. This is achieved by the **Banker's Algorithm**, which is a resource allocation and deadlock avoidance algorithm that tests for safety before allocating resources. The algorithm maintains a *safe state* and only allocates resources if it can guarantee that the system will remain in a safe state after the allocation. The algorithm requires knowledge of the maximum resource requirements of each process and the current allocation of resources.

Safe State: A system state where we are sure that all processes can be executed in some order, one after the other, such that each one will obtain all the resources it needs to finish. We assume once a process receives all the resources it needs, it will finish and release all its resources.

#### Rules of the Banker's Algorithm The Banker's Algorithm works as follows:

- There are n processes and k resource types (each resource can have multiple instances).
- Upon initialization, each process p declares the maximal number of resource-instances it will need for each type,  $\max[p]$ .
- While running, OS maintains how many resources are currently allocated to each process, cur[p].
- And how many resource instances are currently available (free), avail.
- Upon a request for resources by a process p, R, the OS allocates iff the system will stay in a safe-state after the allocation. If not, the process is blocked until the resources are available.

**Note:** The Banker's Algorithm is conservative, i.e. it will not allocate resources even if there is possibility to allocate them without deadlocking the system. The OS doesn't take chances! With Time Complexity  $O(n^2)$ .

```
// *Assume* that request R was granted to process q
                                            // vector addition
2 cur[q] += R;
3 avail -= R;
  // Check if the system is in a safe state (i.e. all processes can finish in some order)
  P = ... // All non-terminated processes (processes that are not finished yet)
  while(P is *not* empty){
      found = false
                                            // true = found a process that can finish
                                            // find a process that can finish
      for each p in P {
8
           if (max[p] - cur[p] <= avail) { // can finish? (by maxing its resources)</pre>
9
               avail += cur[p]
                                            // release resources (pretend p finishes)
               P.remove(p)
               found = true
           }
13
14
       if (!found) return FAILURE
  }
16
17 return SUCCESS
```

Listing 3: Banker's Algorithm

# Topic 8: Networking

**Protocol** A protocol is a set of rules defining the *format & order* of messages sent & received, and what actions are taken upon message transmission or receipt.

# **Network protocol stack consists of layers**




Figure 6: Network Layers Overview

In a nutshell, networks can be divided into 5 layers as follows:

- Application Layer L5: The top layer, where applications communicate with each other. Examples include HTTP, FTP, SMTP, etc.
- Transport Layer L4: Responsible for end-to-end communication between applications. It provides reliable or unreliable delivery of data. Examples include TCP (reliable) and UDP (unreliable).
- Network Layer L3: Responsible for routing data between devices on different networks. It provides logical addressing and routing. Examples include IP (Internet Protocol).

- Data Link Layer L2: Responsible for node-to-node communication within the same network. It provides physical addressing and error detection. Examples include Ethernet, Wi-Fi, etc.
- Physical Layer L1: The lowest layer, responsible for the physical transmission of data over a medium. It includes the hardware components such as cables, switches, and network interface cards (NICs).

layer	name	protocols	data unit	addressing	implemented by
5	application	HTTP, SMTP	stream, messages	N/A	user-level code
4	transport	TCP, UDP	segments, datagrams	ports	kernel-level code
3	network	IP	packets	IP	
2	link	ethernet	frames	MAC	
1	physical	802.11	bits	N/A	hardware (NIC)

Table 1: A five-layer network model describing protocols, data units, and implementation levels.

# Application Layer (L5)

The Application Layer is the topmost layer in the network architecture. It provides network services directly to the user's applications. This layer is responsible for facilitating communication between software applications and lower layers of the network stack.

The Application Layer interacts with the Transport Layer (L4) to establish connections and manage data flow between applications on different devices. One can easily invent a new protocol as needed.

There are **Standard** protocols (determined by multiple organizations): HTTP, HTTPS, NFS, SSH, Bitcoin... And **Proprietary** protocols (determined by a single organization): Microsoft Exchange, Skype, Zoom, Whatsapp...

**Problems In Networking -** There are 2 main problems to consider when discussing networks:

- Lossiness: Networks are inherently lossy, meaning that data sent won't always arrive at the destination. This can be due to various reasons such as hardware failures... But more commonly, it is due to running out of memory buffer space in network elements.
- Reordering: Networks may mess up the order of the messages sent.

## Transport Layer (L4)

Protocols in Layer 4 provide host-to-host communication services for processes, they are implemented (typically) by the OS. Two most common protocols are: **TCP** (Transmission Control Protocol) and **UDP** (User Datagram Protocol).

**TCP** "The protocol that cares", i.e. it cares about data loss & reordering. It ensures that data is delivered reliably and in the correct order. Provides **stream** of bytes between two processes. Said to be **connection-oriented** because it establishes a connection before transmitting data. Simplified view of TCP:

#### • Sender

- 1. Establish a connection with the receiver by performing a 3-way handshake.
- 2. Split bytes into contiguous chunks called *segments*.
- 3. Assign a sequence number to each segment, and keep them around until they are acknowledged by the receiver.
- 4. Resend segments that are not acknowledged for some time, or receiver says they are missing.
- 5. Slow down the sending rate if segments sent are not reaching the receiver.
- 6. Implement Congestion Control = changing the rate in response to drops.

#### • Receiver

- 1. Send ack messages (acknowledgments) upon receiving chunks.
- 2. Ask sender to resend chunks that appear to be missing for some time.
- 3. "Advertise" free buffer space to the sender, so it knows how much data it can send without overflowing the receiver's buffer.
- 4. Implement **Flow Control** (advertising) = Receiver controls sender transmission rate, thereby preventing its own buffer overflow.
- 5. Deliver the bytes in-order to receiving user-level app.

TCP Sequence Numbers TCP uses sequence numbers to ensure that data is delivered in the correct order. Each byte in the stream is assigned a unique sequence number, and the receiver uses these numbers to reassemble the data in the correct order. The sequence number is included in each segment header, allowing the receiver to detect missing segments and request retransmission.

For each segment sent, the sender waits for an acknowledgment message from the receiver, if he doesn't receive any (the original message or the acknowledgment were lost) he resends the same segment with the same number. The receiver checks the number to prevent multiplicity in case of lost acknowledgment messages.

**UDP** "The protocol that doesn't care", i.e. it does not guarantee reliable delivery nor inorder delivery of data. Provides **datagrams** (as opposed to a stream) of bytes between two processes. Chunks might get lost or be delivered out of order, **but** per-chunk bytes integrity is supported. Said to be **connectionless** because it does not establish a connection before transmitting data. Compared to TCP, UDP is simpler and has less overhead, lower latency, and no congestion control.

Note: To clarify, UDP still offers some level of reliability, as it uses *checksums* CRC error detection to ensure that the data received is not corrupted. However, it does not guarantee that the data will be delivered or that it will be delivered in the correct order.

Sockets Apps communicate with the Transport Layer through socket file descriptors, created via the socket() system call, instead of open(). A sockfd constitutes a communication endpoint.

Note: It is recommended to understand what IPs are before continuing this section (read next section - IP)

**Ports** Ports exist on the same host, and there can be a multiple of them. Each communicating process utilizes **sockfds** to identify its own communication channel, each with its own associated **port**. As IPs are not sufficient, we use a unique port for each socket, which is an unsigned 16-bit integer that identifies it on the host. Each chunk transmitted is associated with IP-address + port.

Ports can either be **Ephemeral** (temporary, dynamically assigned by the kernel), or **Well-Known** (static, determined by standards/known values). Ports  $\leq 1023$  are reserved for well-known protocols, such as HTTP (80), HTTPS (443), etc.

Each socket is identified by a **5-tuple** consisting of:

- 1. Source IP address
- 2. Source port number
- 3. Destination IP address
- 4. Destination port number
- 5. Transport protocol (e.g. TCP, UDP)

# Client-Server Model (TCP)

In the client-server model, a server listens for incoming connections from clients, and clients initiate connections to the server. The **server** passively waits for client requests and then reacts, "request-response" paradigm. The server has a well-known domain name (and/or IP address) & port. The **client** asynchronously/intermittently connects to the server, sends requests, and waits for responses. The client may have dynamic IP, and may use ephemeral port.

Sockets are initialized using values from addrinfo structure, which contains the following info: (1) Protocol family (e.g. IPv4, IPv6), (2) Protocol type (TCP), (3) Socket type

(stream), (4) server/client.

Creating and Using TCP Sockets	Creating	and	Using	TCP	Sockets
--------------------------------	----------	-----	-------	-----	---------

server	${ m message}$	client
srvfd =		sockfd =
socket()		socket()
<pre>bind( srvfd , port )</pre>		
listen( srvfd )		
loop:		
<pre>clifd = accept( srvfd )</pre>	request service (transport)	<pre>connect( sockfd , host+port )</pre>
read(clifd )	$\xleftarrow{\text{request (application)}}$	write( sockfd )
write( clifd )	$\xrightarrow{\text{response (application)}}$	read( sockfd )

Event Oriented Programming - select() In the client-server model, the server can handle multiple clients simultaneously by using the select() system call. This allows the server to monitor multiple sockets for incoming data and handle them as they arrive, without blocking on any single specific socket (we block on them all together until one is available). The server can use select() to wait for data on multiple sockets, and when data is available, it can read from the corresponding socket and respond accordingly.

- int select(int nfds, fd\_set \*readfds, fd\_set \*writefds, fd\_set \*errorfds, struct timeval
   \*restrict timeout);
  - nfds: The highest-numbered file descriptor in any of the three sets, plus one.
  - readfds: A set of file descriptors to be monitored for reading.
  - writefds: A set of file descriptors to be monitored for writing.
  - errorfds: Not part of the course material.
  - timeout: A pointer to a timeval structure that specifies the maximum time to wait for an event. If NULL, it will block indefinitely until an event occurs.

# Network Layer (L3) - IP

The Network Layer is responsible for routing data between devices on different networks. It provides logical addressing and routing. The most common protocol in this layer is the Internet Protocol (IP).

**Domain & Host Names** Computers are associated with hierarchical human-readable "domain" names, sometimes referred to as host names, e.g. www.google.com. Each domain names can be backed by one or more host machines, but we will use the term host name assuming it corresponds to a single host machine.

IP Address Domain names are only for humans to read, but computers need to know the IP address of the host they want to communicate with. An IP address is a unique identifier assigned to each device connected to a network. Each host is mapped to a 32-bit IP address obtained via a domain name resolution protocol called **DNS** (Domain Name System). "IP" for us stands for IPv4 (Internet Protocol version 4), but there is also IPv6 which is a 128-bit address space which we will ignore.

Each IP address corresponds to a single host, unlike domain names. Domain names can point to multiple IP addresses (e.g. load balancing), while each IP address is unique to a specific host. The opposite is also not true, i.e. one host can have multiple IP addresses. For simplicity we will assume there's a 1-to-1 host-to-IP mapping.

Note: IP is used to identify host machines, while ports are used to identify individual communication channels of processes on the host.

For example, the IP of csa.cs.technion.ac.il is
---

Notation	IP address
Decimal	2219057153 (not terribly convenient)
Binary $(8x4 = 32 \text{ bits})$	$10000100 \mid 01000100 \mid 00100000 \mid 00000001$
Dot-decimal	132.68.32.1 (a bit more convenient)

# Physical-Layer (L1) & Link Layer (L2)

**LAN** (Local Area Network) A LAN is a network that connects devices within a limited geographical area, such as a home, office, or campus. It typically uses Ethernet or Wi-Fi technologies to connect devices. Each LAN device is equipped with **Network Interface** Card (NIC), which is a hardware component that allows the device to connect to the network.

We will focus on Ethernet, which is the most common LAN technology.

**Ethernet** Ethernet is a protocol that combines hardware, firmware, and software (OS). Ethernet is both a link-layer protocol (L2) as it allows nodes to communicate within the LAN by sending **frames** (byte chunks in layer L2), and a physical-layer protocol (L1) as it defines raw bits are transmitted over the physical medium.

MAC (Media Access Control) Address Each device on a LAN has a unique identifier called a MAC address. It is a 48-bit address that is assigned to the NIC by the manufacturer. The MAC address is used to identify devices on the same LAN and is used by Ethernet to deliver frames to the correct destination. The 48-bits are usually represented as 6 hexadecimal numbers separated by colons, e.g. 00:1A:2B:3C:4D:5E, where the first 3 bytes are the device's manufacturer ID and the last 3 bytes are the device's unique identifier.

**Ethernet Frame Structure** An Ethernet frame is the basic unit of data transmission in Ethernet networks. It consists of several fields that provide information about the frame and its contents. The structure of an Ethernet frame is as follows:






Figure 7: Diagram of an Ethernet Frame Structure.

- 1. **Preamble:** Its purpose is purely for timing and synchronization.
- 2. Start Frame Delimiter (SFD): The actual frame starts with the very next bit.
- 3. **Destination/Source MAC Address:** This is the MAC of the NIC that the frame is *intended for* (Destination) and the MAC of the NIC that *sent* the frame (Source).
- 4. **Size:** Represents the length of the frame.
- 5. **data:** Contains the actual data from the upper layers, such as an IP packet from the Network Layer (L3).
- 6. Cyclic Redundancy Check (CRC): It is an error-detection code. i.e. the frame is dropped in case of a CRC error.
- 7. **Gap:** After a frame is sent, devices on the network must wait for a brief period before any device is allowed to send the next frame. This gives device interfaces time to process the frame they just received and prepare for the next one.

#### The Internet

IP & Routers The problem for now is LAN hardware communicate through L2, meaning two different LANs cannot communicate with each other. The solution is to use **routers**, which are devices that connect different networks and **forward** packets between them. Thus the internet is a inter-network of networks, where each inter-network is connected by routers. This is made possible using the IP (L3) protocol, which provides a way to route packets between different networks. The routers "peel off" the L2 headers of the source LAN and re-encapsulate the data within L2-headers of the destination LAN.





- (a) The Internet Layers and Encapsulation.
- (b) Hourglass Model of the Internet.

**Hourglass Model** The hourglass model is a conceptual framework that illustrates how the Internet is structured. It shows that the Internet has a narrow waist, which is the IP protocol, and that all other protocols (e.g. TCP, UDP, HTTP) are built on top of it. The model emphasizes the importance of IP as the foundation of the Internet, allowing different protocols to coexist and communicate with each other.

IP address structure An IP consists of two parts: Subnet Part (high order bits) and Host Part (low order bits). The subnet part identifies the network, while the host part identifies the specific device within that network. The subnet part is determined by the subnet mask, which is a 32-bit number that specifies how many bits are used for the subnet part and how many bits are used for the host part. An IP address is always coupled with a subnet mask; e.g. 192.168.1.1/24 means that the first 24 bits are the subnet part and the last 8 bits are the host part. Meaning of subnet is that all devices in the same subnet can communicate with each other directly, without going through a router. i.e. it defines the boundaries of the Ethernet LAN.

#### ARP (Address Resolution Protocol): $IP \Longrightarrow MAC$

ARP is a protocol used to map IP addresses to MAC addresses. When a device wants to communicate with another device on the same local network, it needs to know the MAC address of the destination device. If it only knows the IP address, it broadcasts an ARP query packet (containing the destination IP and -1 as the MAC) to the local network, asking "Who has IP address X.X.X.X? Tell me your MAC address." The device with the matching

IP address responds with its MAC address, allowing the sender to encapsulate the data in a frame and send it to the correct destination. If the destination is not on the same local network, the sender will get the MAC to **its default gateway (router)**, its first-hop router, which will then forward the packet to the correct destination network.

#### NAT (Network Address Translation): private IPs

NAT is a technique used to allow multiple devices on a local network to share a single public IP address. NAT defines new private IP addresses for each device on the local network, allowing them to communicate with each other using these private addresses. When a device wants to communicate with the outside world, NAT translates its private IP address to the public IP address, allowing the device to access the internet. This helps conserve the limited pool of public IP addresses and provides an additional layer of security by hiding the internal network structure from external entities. To do so, NAT maintains a mapping between pairs of (private IP addresses + port) and (public IP address + port).

#### DHCP (Dynamic Host Configuration Protocol): get an IP

DHCP is an L5 protocol used to dynamically assign IP addresses to devices on a network. The goal of DHCP server is to allow client's host to dynamically get IP address when joining LAN, which can provide: (1) subnet mask, (2) Default gateway (first hop router), (3) Name + IP of DNS server for client. DHCP uses UDP to communicate allowing the ability to broadcast to all hosts in LAN. When a device connects to a network, it sends a DHCP request to the DHCP server, which responds with an available IP address and other configuration information.

# Topic 9: Virtual Memory

NOTE: ALWAYS say if you are talking about **physical memory** (RAM) or **virtual memory** in your answers.

## Virtual Memory Concepts

**Virtual Memory** Virtual memory is the abstraction of physical memory, allowing processes to "think" they have access to the entire memory space, even if the physical memory is limited. The motivation for virtual memory (vmem):

- Per-Program Contiguous Memory Illusion: Each process has its own virtual address space, which is contiguous simplifying memory management and allowing processes to use the same address space without conflicts.
- **Isolation:** Virtual memory provides isolation between processes, ensuring that one process cannot access the memory space of another process.
- Dynamic Growth: Virtual memory allows processes to grow their heap/stack (and mmap regions) as needed.
- Illusion of Large Memory: Virtual memory allows processes to use more memory than is physically available. Allowing for memory overcommitment.
- Access Control Deciding if individual memory chunks (pages) can be read/written/executed.

**Fragmentation** Virtual memory also solves the problems of fragmentation: (1) External fragmentation - wasting external chunks of data due to lack of contiguity, caused by spreaded allocations and deallocations, (2) Internal fragmentation - wasting internal chunks of data within allocated pages, due to allocating too much memory for a process, which is not used.

**Terminology Virtual Address (VA)** is the address used by a process (& programmer) to access its own memory space, the CPU processes VAs. **Physical Address (PA)** is the actual address in RAM where data is stored. **Page** = chunk of contiguous data (in virutal or physical space), **Frame** = physical memory exactly big enough to hold one page.  $|Page| = |Frame| = 2^k$ , typically 4KB (k=12).

The basic idea The OS maps virtual addresses to physical addresses using a **page table**, such that VA spaces are contiguous. Pages can be mapped to: (1) memory, (2) disk, (3) unallocated yet (allocated on-demand).all programs are written using VAs, OS sets the VA  $\Longrightarrow$  PA mapping (governs control plane), HW does on-the-fly translation from VA to PA (governs data plane).

Use per-process "page table" (in DRAM)

#### virtual address (32bit) 31 virtual page number (20bit) page offset (12bit) frame# V D AC page table base register of 2^20 ≈ 1M entries the CPU, holding physical address, which is different for every process; set upon context switch) valid bit dirty bit access control per-process page table

# Figure 9: Virtual Memory Page Table

physical frame number (20bit)

physical address (32bit)

page offset (12bit)

The basic premise of **page tables** is that each process has its own page table, which maps virtual pages to physical frames. Using the virtual page number (VPN) we check the page table entry (PTE) associated with it to find the physical frame number (PFN) it is mapped to, in addition to other flags. One important flag is the **valid bit**, which indicates whether the page is currently mapped to a physical frame or not. If the valid bit is set, the page is mapped to a physical frame, and the OS can access it. If the valid bit is not set, then if all other bits are zero it means the page has not been allocated yet. Otherwise it means it resides on the disk in the written address.

Memory Access steps the following is the basis of how the CPU accesses memory:

```
if (valid == 1)
                                         // Otherwise HW raises a page fault interrupt
      page is in main memory @ PA stored in table \(\Longrightarrow\) data can be used
2
  else if (page resides on disk)
                                         // "Major" page fault
      OS suspends process
      Fetches page from disk and adds VA\(\Longrightarrow\)PA mapping to page table
5
      Resumes process, which will re-execute faulting instruction
6
  else if (should be but still is not allocated ||
            in page cache but not in page table) // "Minor" page fault
      OS allocates page if needed & adds VA\(\Longrightarrow\)PA mapping to page table
9
  else if (some other legal situations for which OS is responsible)
      Resolve (example: CoW; see later)
12
  else
                                 // process performed an illegal memory ref
      OS (which handles the page fault interrupts) delivers a signal
13
       (SIGSEGV/SIGBUS) to the offending process
14
```

The matching signal handler terminates process by default

Listing 4: Memory Access Steps in Virtual Memory

If access type is incompatible with specified access rights, then a protection violation fault happens raising an interrupt, which the OS resolves if it is its fault, or delivers a signal to the offending process.

Major Page Fault Flow Major = need to fetch page from disk.

- 1. **CPU detects** the situation (valid bit = 0)
- 2. CPU generates interrupt and transfers control to the OS
- 3. **OS regains control**, realizes page is on drive, initiates I/O read ops
- 4. **OS** suspends the process & context switches to another process
- 5. Upon read completion, OS makes the process runnable again
- 6. When the **process is scheduled** again, it <u>re-executes the faulting instruction (which</u> will succeed this time)

Minor Page Fault Minor = NO need to go to drive to resolve. Examples: (1) CoW (Copy on Write) which is used to implement fork for example, (2) Demand-based (Lazy) memory allocation, (3) reading a file content that already is found in the page cache, possibly by other processes.

Note: Minor page faults may cause access to disk if there is not enough memory on DRAM (will cause swapping).

Page in & out a chunk of data: Paging is the process of swapping pages in and out of physical memory to disk storage.

Page in  $\iff$  Copy page from disk to DRAM (read)

Page out ← Copy page from DRAM to disk (write)

mmap syscall The mmap syscall is used in one of two ways: (1) map a given file to a given virtual address range in the process's memory space. (2) allocate a new annonymous memory region in the process's memory space.

1. Named Pages: When mapping a file, the OS maps the file's as if it was an "array of bytes" (backed by the disk) in the VA space of the process. Reads/writes to the mapped region will read/write the file's content, and the OS will update the file accordingly every few seconds, in batches. To force the OS to write the changes to disk, the process can use fsync(fd) syscall. This helps making programming easier, and saves on the overhead of syscalls to read/write (as reads/writes to the mmap are equivalent to memory reading/writing), which in turn saves on I/O copying.

2. **Anonymous Pages:** are heap/stack pages, or pages of mmap with fd=-1, flag=MAP\_ANONYMOUS which are not backed by any file/disk. i.e. we can implement malloc using mmap (for heap we use sbrk syscall).

We also divide the mmap pages into two types: (1) MAP\_SHARED = changes affect the actual file (& visible to other processes), (2) MAP\_PRIVATE = changes don't affect the actual file; rather, there will be a CoW for the process (other processes will not see changes)

**Swapping Swap Space** is a disk area where anonymous pages are written, if the OS decided they have no room in DRAM (memory is full). Pages are said to be "swapped out" when this occurs (and "swapped in" on return). Nowadays we don't distinguish between the terms swapping and paging.

NOTE: Kernel memory never swaps out, it is always in DRAM, and it is not paged in/out.

Exceptions (for page faults) are divided to: (1) illegal access rights, (2) user access to kernel memory, (3) access to address that is not mapped to any page. The kernel decides the exception using bits for each one and the CPU loads the virtual address to register CR2 (not to be confused with CR3).

**On-demand Paging** A memory management technique where pages are loaded into memory only when they are needed, rather than preloading all pages at once. i.e. pages are allocated/brought into DRAM only when the process attempts to access it for the first time (resulting in a page fault)

The steps are: (1) Update the memory region list, (2) Set the page table entry (PTE) present bit as 0, (3) The page is allocated/copies from disk upon first access.

Readahead Prefetching When read() identifies sequential accesses to file, the read() reads ahead pages not yet requested, prefetching them, so they would be ready, in an attempt to minimize page faults. (same with the on-demand paging page fault handler)

**Deduplication** A technique to save on physical memory by allocating a single shared page for all processes who use the same data as *read only*.

TLB (Translation Lookaside Buffer) The TLB is a cache used by the CPU to reduce the time taken to access memory locations. It stores recent translations of virtual memory addresses to physical memory addresses, allowing the CPU to quickly find the physical address corresponding to a virtual address without having to go through the entire page table. When a virtual address is accessed, the CPU first checks the TLB; if the translation is found (a TLB hit), the physical address is retrieved quickly. If not (a TLB miss), the CPU must consult the page table, which is slower. TLBs are typically small and fast, and they use various replacement policies to manage the limited space.

Typically, HW fills TLB automatically by reading the page table on its own (without SW help), and OS invalidates TLB entries (upon context switches, for non-global entries).

## Virtual Memory Implementation

#### Intel x86 Architecture

**32-bit x86 address translations** 32-bit address means  $2^{32}$  virtual addresses, which is 4GB of virtual memory space. The virtual address space is divided into pages, typically 4KB in size. The page table maps these virtual pages to physical frames in memory.


The job of the x86 virtual memory subsystem is to translate 20-bits (=virtual page number - VPN) to 20-bits (= physical frame - PFN). Every process holds a **Page Directory** (= 4KB page) holding 1024 PDEs (page directory entries) each containing a pointer to a **Page Table** (= 4KB page) holding 1024 PTEs (page table entries) each containing a point to a **Page Frame** (= 4KB page). The offset is the last 12 bits of the virtual address, which is used (as is) to access the data in the page frame (same offset). This structure is called Radix Trees.


Each PDE/PTE holds additional flags, such as  $\mathbf{P}$ resent,  $\mathbf{A}$ ccessed,  $\mathbf{D}$ irty,  $\mathbf{U}$ ser,  $\mathbf{W}$ riteable, Cache  $\mathbf{D}$ isabled, etc.

**CR3 Register** The CR3 register holds the physical address of the page directory for the currently running process. When a context switch occurs, the operating system updates the CR3 register to point to the new process's page directory. (Or more generally, the CR3 register holds the physical address of the first layer of page tables).

# Present Writable User / Supervisor Write-Through Cache Disable Accessed Dirty Page Table Attribute Index (PAT) Global Page Available for OS Use Page Base Address 31:12 AVAIL B AVAIL AVAIL AVAIL B AVAIL B AVAIL AVAIL B AVAIL

**4KB-page PTE format** 





(b) 32-bit Page Tables

Global + User/Supervisor bits The "user/supervisor" bit is used to indicate that only the OS (ring 0) can access the page, while user processes (ring 3) cannot. The "global" bit is used to indicate that the page is shared across all processes and should not be flushed from the TLB on context switches. This is used to implement shared kernel space across all memory spaces.

**HW/OS Cooperation** HW defines the data structures (hierarchy, PTE bits, etc.). While the OS determines most of the content of page directories & page tables (setting the values & mappings). The HW sets the bits of dirty and accessed, and does the table walk automatically:

- 1. If VA \Rightarrow PA translation not found in TLB, "TLB miss"
- 2. HW knows where to find the root page directory (CR3 register)
- 3. HW walks the tables, hierarchially, until it reaches the data page
- 4. It inserts the VA⇒PA mapping into the TLB

The HW populates the TLB, and the OS invalidates TLB entries when needed (e.g. on context switches, or when a page is evicted from memory). The OS is also responsible for Synchronizing between TLBs of different cores (TLB shootdown).

#### 64-bit x86 address translations

**64-bit x86 address translations** 64-bit address means  $2^{64}$  physical addresses, which is 16 Exabytes of physical memory space. The virtual address is only 48-bits, which is  $2^{48}$  virtual addresses, which is 256TB of virtual memory space. The page size is still 4KB, but the PTE is now 8 bytes (64 bits) instead of 4 bytes (32 bits). The page table structure is similar to the 32-bit x86 architecture, but with additional levels of indirection.




Figure 11: 64-bit Page Tables

**Increased TLB convergence** To make the TLB more useful we use two concepts:

• TLB hierarchy: We use multiple TLB caches (like the L1, L2, ...) each bigger but slower than the last. Usually we use only two levels.

- Superpages/Hugepages: Different sizes are supported by different architectures;
  - 32-bit x86: 4KB, 4MB pages
  - 64-bit x86: 4KB, 2MB, 1GB pages

We merge the last N levels of page table bits in the VA into one offset of the superpage, allowing us to have fewer page table levels but larger pages.

## 64-BIT Power-PC (PPC) Virtual Memory

A completely different architecture, but similar concepts, used in IBM PowerPC processors.

- 3 Address Types effective Longrightarrow virutal Longrightarrow real
  - Effective: Each process uses 64-bit effective addresses, which are not unique across processes. The equivalent of virtual addresses in x86.
  - Virtual: A huge 80-bit address space, which is unique and shared by all processes. If two processes have the same effective address, they will can different virtual addresses, but if they have the same virtual address, they will have the same real address.
  - **Real:** The actual physical address in memory, which is 62-bit addresses.

**PPC Segments** Effective & virtual spaces are partitioned into **segments**, which are 256MB in size. Each segment is contiguous in the per-process effective address space, and each segment is contiguous in the virtual address space.

**PPC SLB (Segment Lookaside Buffer)** The SLB is a cache used to speed up the translation of effective addresses to virtual addresses. OS manages the SLB, and HW searches the SLB for the effective address. Upon a miss, the OS is notified, and it will insert right segment table entry (STE) to SLB. Upon context switch, the OS invalidates the SLB entries.

**PPC TLB (Translation Lookaside Buffer)** The TLB is a cache used to speed up the translation of virtual addresses to real addresses. The TLB is managed by both OS & HW. The virtual addresses are shared so no need to invalidate the TLB upon context switch.

**PPC ERAT (Effective-to-Real Address Translation)** The ERAT is a cache used to speed up the translation of effective addresses to real addresses. Analogous to the TLB (in x86).

PPC HTAB (Hash Table) The HTAB is a hash table used to store the mappings between virtual addresses and physical addresses. Each PTE contains both PPN & VPN, and the OS uses a hash function to map the VPN to a PPN. PTEs are divided into PTEG (Page Table Entry Groups), each containing 16 PTEs. Each PTE can either reside in a "primary" or a "secondary" PTEG. If a PTE is missing, a page-fault interrupt is raised, and the OS will place the PTE in either the primary or secondary PTEG.




Figure 12: PPC Virtual Memory Architecture

# Linux Implementation (OS)

Memory Descriptor The memory descriptor (mm\_struct) is a data structure used by the Linux kernel to manage a process's memory. It contains information about the process's virtual memory layout, including the location and size of each memory region. Threads share the same memory descriptor, while processes have their own memory descriptor.




Figure 13: Memory Descriptor Structure in Linux

Kernel Threads are threads created by the operating system to execute specific tasks in the kernel space. E.g kswapd thread is responsible for managing memory by swapping pages in and out of physical memory. Kernel threads do not have their own memory descriptor, they point to NULL, so they keep the memory descriptor of the last process that was running (in CR3).

Every kernel thread has his own kernel stack in the kernel space, thus it does not need a memory descriptor of its own. They use the page tables of the last process, since kernel space exists (the same) in all user spaces.

Kernel vs User Space In x64-bit intel we use 48-bit virtual memory (256TB) and 52-bit physical memory (4PB). The kernel space is the upper half of the virtual address space, while the user space is the lower half. The kernel space is reserved for the operating system and its kernel threads, while the user space is reserved for user processes. The kernel space is not accessible by user processes, and vice versa. The kernel space is shared by all processes thus ensuring it can be accesses at any point from the kernel, using the page tables of the user process.

Memory Descriptor Fields The memory descriptor contains several fields, including:

- $\bullet$  mm\_users The number of \*user\* processes that share this memory descriptor.
- $mm\_count$  The number of \*kernel\* threads + (all user process counter together as 1, if exist) that share this memory descriptor.
  - If mm\_users==0 then the OS frees all memory regions of the user (stack, heap, etc)
  - If mm\_count==0 then the OS frees the memory descriptor, and the page tables.
- mmlist Pointer (of type list\_head) to the global list of all memory descriptors.

- pgd The root addresss of the page tables, the value loaded to CR3.
- mmap Sorted linked list of the memory regions used (fig. 13).
- rss The number of frames in use by the process in the DRAM.
- total\_vm The total number of virtual pages allocated by the process, including those that are not in DRAM (e.g. not allocated yet, or swapped out).

Memory Regions The memory descriptor contains a linked list of memory regions, each represented by a vm\_area\_struct structure. Memory regions structs contain the following fields:

- 1. vm\_start The starting virtual address of the memory region.
- 2.  $vm_end$  The ending virtual address + 1 of the memory region.
- 3. vm\_next Pointer to the next memory region in the linked list.
- 4. vm\_mm Pointer back to the memory descriptor that this region belongs to.
- 5. vm\_flags Flags that describe the memory region, such as:
  - VM\_READ, VM\_WRITE, VM\_EXEC Access rights for the region (read, write, execute).
  - VM\_MAYREAD, VM\_MAYWRITE, VM\_MAYEXEC Upper values of the access rights, indicating whether the region can have these rights or not (can their access rights be set or not).
  - VM\_SHARED Indicates that the memory region is shared between processes
  - VM\_LOCKED Prevents swapping out the memory region, ensuring it remains in physical memory.
- 6. vm\_page\_prot The bit values to be set in all PTEs of this region.

	Anonymous	Named (File-Backed)
Private	Not backed by any file + Exclusive to a single process.  Use Case: A process's heap (malloc) and stack. On fork(), these pages are handled with Copy-on-Write (CoW).	The page is initialized with data from a file, but modifications are private to the process and are not written back to the original file (Copy-on-Write).  Use Case: Loading a file into memory using mmap with MAP_PRIVATE.
Shared	Shared between multiple processes but not associated with any file on the filesystem. All processes see the same physical page of memory.  Use Case: Inter-Process Communication (IPC) where processes need a fast shared memory segment without needing a temporary file, E.g pipes.	The page is initialized with data from a file, and it is shared among multiple processes. Any modifications are visible to all processes and are written back to the underlying file.  Use Case: Created with mmap with MAP_SHARED. The disk updates every few seconds, in batches, to avoid performance issues, or using fsync(fd) to force immediate write.

#### Classification of Memory Pages

Note: Heap + Stack pages are always anonymous pages, and they are always private to the process. Code (text) region is always named (file-backed) and shared between processes. Note 2: execv() replaces the current process's memory with a new program, effectively replacing all vm\_area\_structs in the memory descriptor with new ones.

More on CoW (Copy on Write) When a process forks, the OS creates a new memory descriptor for the child process, and new page tables. For each memory region, the OS copies the vm\_area\_struct of the parent to the child process, then copies the PTE from the parent to the child. For each frame used by the parent process (that is private + writable), the OS adds the counter of threads using the frame and unsets the write access for this page from everyone.

Upon write access we hit a page fault, if the vm\_area\_struct allows writing (VM\_WRITE is on), then the OS copies the frame to a new one to allow writing (if this was the last thread then it doesn't copy as there is no need, it just sets the write access on).

Note: CoW doesn't always improve performance, as if we copy all of the memory page by page, it would have been more efficient to copy it all at once.

# Topic 10: Interrupts

**Interrupts & Exceptions** Our interrupts are Intel's interrupts and exceptions, such that: exceptions = internal (synchronous) implicit interrupts, and interrupts = all the rest. There are two sources for interrupts:

- 1. **External / Asynchronous** Triggered by devices external to the core's compute circuitry. Assynchronous because they can occur at any time.
- 2. **Internal / Synchrounous** Triggered by the core's compute circuitry (CPU intructions). Sometimes called "Software interrupts" as they are triggered by the CPU executing an instruction.

Internal Interrupts Internal interrupts can be further divided into:

- Explicit Triggered by the CPU executing an instruction that deliberately causes an interrupt, such as int instruction, or syscall instruction, or Ptrace-ing.
- Implicit Triggered by the CPU executing an instruction that causes an error or exception, such as division by zero, invalid memory access, or illegal instruction. i.e. the CPU can't complete the instruction so it transfers control to the OS. Two types of exceptions:
  - Error condition tells the OS that the app did something illegal.
  - Temporary problem such as a page fault, which can be resolved by the OS.

Interrupt Handling Each interrupt is associated with a Number (called interrupt vector), which is used to identify the interrupt handler. Handlers are pointed to by and array [256] of pointers-to-functions. The interrupt handler saves the state of the current running processes and then executes the handler.

Context Type If the interrupt is asynchronous then the kernel is said to be in interrupt context, meaning it doesn't server the process that has just been stopped. If the interrupt is synchronous then the kernel is in process context as it needs to provide some service to the process that invoked it.

NOTE: interrupt handlers are not schedulable entities, they run immediately (without invoking the scheduler), unless the interrupt is masked. We can mask using a bitmap, incase of making an interrupt the HW will remember at most 2 instances of each interrupt that was blocked by the mask (the rest get lost, if they exist).

Top & Bottom Halves Interrupt handling is often divided into two parts: the top half and the bottom half. The top half is the part of the interrupt handler that runs in response to the interrupt and does the minimal amount of work necessary to handle the interrupt. The bottom half is the part of the interrupt handler that can be deferred and run later, allowing the top half to return quickly and minimize the impact on the system's responsiveness.

#### Resuming an interrupted process We split to multiple cases:

- Asynchronous (external) interrupts: Resume in the next process instruction, right after the last instruction that was exectued. Note that asynchronous interrupts are caught and handled between instructions.
- Synchronous (=internal) + explicit: Likewise, resume in the next instruction.
- Synchronous (=internal) + implicit: Resume in the same instruction that caused the HW failure, called restartable instruction. For temporal problems the OS will fix the problem, but for error conditions it doesn't make sense so a signal will also be sent to the process.

**Interrupt handling in multicores** Internal (synchronous) interrupts are always handled by the core that executed the instruction that caused the interrupt. External (asynchronous) interrupts can be handled by any core, so we can do any kind of partition between the cores (static/dynamic/...).

Polling Polling is a technique used to check the status of a device or resource at regular intervals. In the context of interrupts, polling can be used as an alternative to interrupts for handling events. Instead of relying on the hardware to generate interrupts, the CPU actively checks the status of devices and resources to determine if they require attention. This can be useful in situations where interrupts are cause an interrupt storm (too many interrupts in a short time), leading to performance degradation.

**Interrupt Coalescing** The hardware tries to not create an "interrupt storm" by coalescing multiple events into a single interrupt. And the Software also temporarily switches to polling mode when the flow of incoming interrupts exceeds a certain thershold.

**DMA & interrupts** DMA = Direct memory access, which is when an I/O device can directly read/write to memory without involving the CPU. Conceptually devices fire an interrupt when a DMA operation is finished, not only when reciving (reading) data, but also when sending (writing) data. This allows to notify OS when the send buffer has become free.

Note: All interrupts are handled in kernel mode, CPL=0, including the timer interrupt.


System Calls / Exceptions	Hardware Interrupts
If the processor is running user	The kernel immediately handles
code, a system call or exception	any incoming hardware interrupt,
transitions control to the kernel for	even if it is already in the middle of
handling.	handling an exception, system call,
	or another interrupt.
System calls can be blocking and	A hardware interrupt handling
cause the process to yield the	routine never yields the processor.
<pre>processor (e.g., read(), wait()).</pre>	
Handling for a system call or	An interrupt handler will not make
exception can be preempted by an	system calls or cause exceptions
incoming hardware interrupt.	(with the exception of a page
	fault). After handling the interrupt,
	the kernel may switch to a different
	process than the one that was
	previously running.

**Kernel Control Paths** A kernel control path is block of instructions that the kernel uses to handle: (1) Syscalls, (2) Hardware Interrupts, (3) Exceptions. Different control paths can interleave with each other as follows:

System Calls / Exceptions	Hardware Interrupts
A handler for a system call or	An interrupt handler will not make
exception will not cause a new	a system call or cause an exception
exception (with the notable	(other than a page fault). After
exception of a page fault).	handling is complete, the kernel
	may schedule a different process to
	run.
Single Processor: the handler	Single Processor: the handler
can be preempted by a hardware	can only interleave a different
interrupt, and it can interleave with	hardware interrupt handler.
all other control paths.	
Multi-Processor: the handlers	Multi-Processor: the handlers
can interleave with each other, from	can interleave with each other, from
all control paths.	all control paths.

**Disabling Interrupts** Disabling interrupts is a technique used to prevent the kernel from being interrupted by hardware interrupts while executing critical sections of code. This is typically done to ensure that the code can execute atomically without being preempted. However, disabling interrupts can lead to performance issues and should be used sparingly.

To disable an interrupt we set the flag IF in the RFLAGS register to 0, and to enable it we set the flag to 1. In critical code, we turn off the IF, but at the end we set it back to the previous value.



# Topic 11: Page Cache

**Page Cache** The page cache is a memory area used by the operating system to cache disk pages in RAM. It is used to speed up disk I/O operations by keeping frequently accessed pages in memory, reducing the need to read from or write to the disk. The page cache is managed by the operating system and is transparent to user processes.

Every I/O operation on the disk is done via the page cache; If the page is already on the page cache (in DRAM) (either from the process, or a different process) then it will use said page, else it will obtain the page from the disk and place it in the page cache.

Write-Back write ops to the disk are delayed and done in batches. This allows for minimising the number of disk access ops, but at the cost of validicy since data on the disk is not correct at all times.

**Read-Ahead** If the kernel recognizes a sequential pattern of accesses to the file, it will preemptively read the next few pages into the page cache. This allows for less page-faults, but might waste memory on wrong predections.

**Frame Table** The frame table is a data structure used by the operating system to manage physical memory pages. It keeps track of which physical pages are in use, which are free, and their associated metadata. Each entry in the frame table corresponds to a physical page frame in memory and contains information as follows:

- refcount How many memory spaces point to this frame.
- mapping Pointer to the inode this frame belongs to, NULL in case of anonymous frame.
- index The offset in the file this frame corresponds to, empty in case of anonymous frame.
- flags Flags that describe the frame, such as: PG\_dirty, PG\_active, PG\_referenced.
- next\_hash, prev\_hash Pointers to the next/previous frames in the page hash table (explained next).

**Page Hash Table** The page hash table is a data structure used by the operating system to manage the mapping (mapping + index) to frames in the DRAM. All conflicting hashes are connected using chain-hashing, with the pointers next\_hash,prev\_hash from the frame table.




Figure 14: Frame Table + Page Hash Table; Note: that both structures are implemented in software, not in hardware

mmap vs read/write mmap and traditional read/write operations are two different methods for performing file I/O.

### • read/write System Calls:

- The system call brings data from the disk into the page cache.
- It then copies the relevant data from the page cache to the user's buffer.

#### • mmap System Call (File Mapping):

- The system call creates a new memory region but does not read data from the disk at that time.
- It uses lazy/deferred memory management.
- An attempt to access the mapped memory region will cause a page fault. This fault prompts the system to read the data from the disk into the page cache and then updates the page table to point directly to the frames within that page cache.

**PFRA** (Page Frame Reclaim Algorithm) The PFRA is a mechanism used by the operating system to manage the page cache and reclaim memory when needed:

- Page cache pages (named pages): If the page is dirty (modified), it is written back to the disk before being reclaimed. If it is clean, it is simply removed from the page cache.
- Anonymous pages: These pages are not backed by any file and therefore must be backed to the swap area before removing them, whether dirty or clean.

Note: PFRA only reclaims (frees) user pages, and never kernel pages.

Note 2: Multiple swap areas can exist, improving performance by parallelizing the swap operations.

Note 3: As mentioned earlier, the swap area is the only area in the disk that is partitioned to slots of 4KB isntead of blocks of 512B.

When to Swap? PFRA runs according to the amount of the free pages in the memory based on:

- if  $free\_pages > pages\_high$ : Stop running PFRA. Reason: To not free too many pages and hurt performance.
- if free\_pages < pages\_low: Start running PFRA in background asynchronously (kswapd thread). Reason: To lower the time of new allocation requests (making available space in advance)
- if free\_pages < pages\_min: Start running PFRA synchronously, in foreground, blocking processes that try to allocate memory until enough pages are reclaimed. Reason: PFRA requires memory to run, if the number of free pages is below a certain threshold, the kernel might crash.




Figure 15: PFRA swap limits

**PFRA Rules** The PFRA uses the following rules to decide which pages to reclaim:

- 1. Prefer freeing *page cache pages* that are not in use by any process (i.e., pages with a refcount of 0) or/and clean pages (not dirty).
- 2. Dynamically follow the level of activity of the pages, and prefer freeing "cold" pages (i.e., pages that have not been accessed recently).
- 3. Freeing shared frames must be done atomically at once from all processes that share the frame.

Note: Anonymous pages can't be "not pointed to by processes" because they will be freed as soon as they are not used anymore.

Page Replacement Algorithms using an intelligent page replacement policy helps with virtual memory performance:

- Belady Optimal (theoretical) Replace the page that will not be used for the longest period of time in the future.
- LRU (least recently used) (impractical) Replace the page that has not been used for the longest period of time in the past.
- Clock (practical LRU) A circular list of pages in memory, where each page has a reference bit. When a page is accessed, its reference bit is set to 1. When a page needs to be replaced, the algorithm checks the pages in a circular manner, clearing the reference bit of each page until it finds a page with a reference bit of 0, which is then replaced.
- NRU (not recently used) (practical more sophisticated LRU) Keep to bits for each page, dirty & referenced, and periodically turn off referenced (as in clock). Replace victim page with the lowest class from the following: (class 0) not referenced, not dirty, (class 1) not referenced, dirty, (class 2) referenced, not dirty, (class 4) referenced, dirty.
- PFRA (page frame reclaim algorithm) (used) As mentioned, each frame keeps flags for PG\_referenced and PG\_accessed (the latter is set by the hardware on each access). Both bits together define a level of activity (as seen in fig. 15), where lower activity pages are more likely to be reclaimed. At each access, the kernel increments the activity level, and we periodically decrement the activity (to prevent long history). We keep all frames in an active list and an inactive list, and we move frames between the lists based on their activity level.




Figure 16: PFRA swap limits

# Topic 12: Storage

## Files & Directories

**File** A file is a logical unit of information which is an ADT (abstract data type), with a name, content, metadata, and can be manipulated via operations (read, rename,...)

**File Metadata** Metadata is information about the file and its content, such as: (1) file name, (2) file size, (3) owner, (4) permissions, (5) timestamps (creation, modification, access), (6) physical location, (7) file type.

**File Descriptors** A file descriptor (FD) is a nonnegative integer that uniquely identifies an open file within a process. An FD is an index into a per-process file descriptor table (FDT), which maps the FD to a file object in the kernel. Threads share the FDT of their process. Some POSIX syscalls operate on FDs and others operate on file names (chmod, unlink, ...).

**File Operations** The following are the most common file operations:

- Creation (syscalls: creat, open; C: fopen)
  - Associate with a name; allocate physical space (at least for metadata)
- Open (open; C: fopen, fdopen)
  - Load required metadata to allow process to access file
- Deletion (unlink, rmdir; C: remove)
  - Remove name/file association & (possibly) release physical content
- Close (close; C: fclose)
  - Mark end of access; release associated process resources
- Rename (rename; -)
  - Change associated name
- Stat (stat, 1stat, fstat; -)

- Get the file's metadata (timestamps, owner, etc.)
- Chmod (chmod, fchmod; -)
  - Change readable, writable, executable properties
- Chown (chown, fchown; -)
  - Change ownership (user, group)
- Seek (lseek; C: fseek, rewind)
  - Each file is typically associated with a "current offset"
  - Pointing to where the next read or write would occur
  - lseek allows users to change that offset
- Read (read, pread, readv; C: fscanf, fread, fgets)
  - Reads from "current offset"; pread gets offset from caller
  - Need to provide buffer & size
  - "v" = vector of buffer+size; this version is called "scatter-gather" (why?)
- Write (write, pwrite, writev; C: fprintf, fwrite, fputs)
  - Change content of file; pwrite gets the offset explicitly; v=vector
  - Likewise, need to provide buffer & size
  - If the current offset (or the given offset in the case of pwrite) points to end of file, then file grows
- Sync (sync<fs>, fsync<fd>;  $\neq$  C: fflush)
  - Recall that
    - \* All disk I/O goes through OS "page cache", which caches the disk
    - \* OS sync-s dirty pages to disk periodically (every few seconds)
  - Use this operation if we want the sync now
  - 'sync' is for all the filesystem, and 'fsync' is just for a given FD
  - Sync  $\neq$  fflush; the latter flushes user-space (fprintf, cout) buffers to the kernel
- Lock (flock, fcntl; C: flockfile)
  - "Advisory" lock (= processes can ignore it, if they wish)
  - There exists mandatory locking support (in Linux and other OSes)
    - \* E.g., every open implicitly locks; and can't open more than once
    - \* But that's not POSIX

File Types In UNIX (POSIX) we classify files into:

- Regular files Contain user data, such as text files, binary files, etc. They are the most common type of file.
- Directories Special files that contain a list of files and
- Symbolic links (soft links) Special files that point to another file or directory, allowing for easy access to files in different locations.
- **FIFOs** (named pipes) Special files that allow for inter-process communication (IPC) by providing a way for processes to communicate with each other through a named pipe.
- Sockets Special files that allow for communication between processes over a network. They are used for network communication and can be either stream-oriented (TCP) or datagram-oriented (UDP).
- Device files Special files that represent hardware devices, such as disks, printers, and terminals. They allow processes to interact with hardware devices as if they were regular files. Can be either character devices (e.g., terminals) or block devices (e.g., disks).

Magic Numbers Magic numbers are a semi-standard Unix way to tell the type of a file by looking at the first few bytes of the file. Each file type has a unique magic number that identifies it. For example, a PDF file starts with the ASCII string: %PDF. Not all files have magic numbers, but many do, since nowadays it is a more complex scheme.

File Protection (Ownership & Mode) For each file, POSIX divides users into 3 classes: "User" (the owner of the file), "group", "all" (all other users). Each class has 3 permissions: "read", "write", "execute". The file mode is a 9-bit number, where each bit represents a permission for a class. The first 3 bits are for the user, the next 3 bits are for the group, and the last 3 bits are for all users. Note: Users can belong to several groups, but not files.

Other operating systems (NOT POSIX) use Access Control Lists (ACLs), where it allows a finer more detailed control of what each user/group can do (delete, rename,...).

**Directories** A filesystem has a hierarchial (tree) structre of directories, where each directory can contain files and subdirectories. Each directory is a special file that contains a list of files and subdirectories, along with their metadata.

Absolute & Relative File Paths File name = File path = path. Every process has its own "working directory" (WD). A path is absolute if it starts with "/" (the root directory), e.g. "/users/admin/jon". A path is relative (to the WD) otherwise, e.g. if WD="/home" then "admin/jon" is the relative to "/home/admin/jon".

**Directory Operations** Each directory contains 2 special subdirectories, "."=Current directory, ".."=Parent directory. To create a directory we use mkdir, and to remove an empty one rmdir.

**Hard Links** File  $\neq$  file name. They are not the same thing, in fact, the name is not even part of the file's metadata! A file can have multiple names, and therefore appearing in multiple unrelated places. Every file has a "reference count" to keep track of how many hard links it has, once it reaches zero, if no process is using it through FDs, then and only then we can remove the file's content.

Hard links to directories are usually disallowed, since it causes infinite circular looping and nesting. However, remember that each directory contains "." & ".." hence each directory has a minimum of 2 hard links, and a maximum depending on the number of subdirectories it contains.

Note: Hard links can only exist on the same filesystem, as they use the same file\_object or as seen later, same inode.

Symbolic Links A symbolic link (or soft link) is a special file that points to another file or directory. It is a way to create a shortcut to a file or directory, allowing you to access it from a different location. Symbolic links are not hard links, and they can point to files or directories that do not exist. Soft links contain target file path, and not a pointer to a file object like hard links. They are no counted in the target file's ref count, they can refer to files, directories, and even files outside the filesystem. (since they only save a path)

When applying a syscall to a symlink, the syscall is applied to the target file. Except, (1) unlink, which removes the soft link. (2) symlink-specific syscall, such as symlink (create a symlink) and readlink (read the content of the symlink, i.e. the path of the target file).

**inode** An inode (index node) is a data structure used to represent a file in a filesystem. Each file has its own (single) inode, which can be thought of as the "file". File names (hard links) point to inodes, and the inode contains all metadata of the file.

Note: file objects (which represent open files) are not the same as inodes, as they contain additional information such as the current offset, number of file descriptors pointing to it, etc. However, file objects point to the inodes, as they are the ones holding to the actual data.

**inode \*stat syscall** POSIX gurantees that at leas the following fields will be found in the stat structure and have meaningful values:

```
ID of device containing file
 1.
    st_dev
 2.
                   inode number, unique for st_dev
    st_ino
 3. st_mode
                   specifies file type & permissions (S_ISREG(m), ...
                   number of hard links to the file
 4. st_nlink
                   file size in bytes
 5.
    st_size
 6. st_uid
                   user ID of owner
 7. st_gid
                   group ID of owner
 8. \text{ st\_ctime}
                   last time metadata (=inode) or data changed
 9.
   st\_mtime
                   last time data modified
                   last time metadata (=inode) or data accessed
10. st_atime
                   block size of this file object (preferred size for I/O ops)
11. st_blksize
                   number of sectors allocated for this file object
12.
    st_blocks
```

lstat is like stat but it applies to the symbolic links when used on one, i.e. it returns the metadata of the symlink, not the target file. The only guaranteed metadata fields to be found are: st\_mode (which will specify it is a symlink) and st\_size (which will be the length of the symlink's target path).

It is not specified in POSIX whether a symlink gets an inode or not (could be either depending on implementaion).

**Directory Entries**) A directory file is compromised of directory entries (directs), which point to the inodes of the files and subdirectories it contains. Each direct contains the following fields: (1) inode number, (2) file type, (3) file name, (4) offset to the next direct, (5) length of the direct. In **FAT** (more on that later) directs are the actual files as there are no inodes, preventing multiple hard links.

**Path Resolution** Resolving a path means finding the inode of the file or directory that the path points to. The algorithm that syscalls use to resolve paths is called "namei". Each path is compromised of "atoms", where an atom is a single file or directory name in the path. The algorithm works as follows:

```
int my_open(char *fname) {
     if (fname is absolute){
       // Start from the root directory
3
       chdir("/");
4
5
       make fname relative;
     }
6
     foreach atom in fname do // e.q. atoms of "x/y" are "x" and "y"
       if (is symlink) SYS (fd = my_open(atom symlink target))
8
                       SYS (fd = open(atom)) // this checks permissions too
       else
9
10
       if (!terminal){
         // If not the last atom, change the current directory to the opened one
12
         chdir(fd directory);
13
         close(fd);
14
       }
15
16
         // If terminal, return the file descriptor of the last opened file
17
         break;
18
```

```
return fd;
return fd;
return fd;
```

Listing 5: Path Resolution Algorithm (namei)

For each non-symlink atom in the path, a user must be able to <u>search</u> all directories leading to the file. This means that the user must have the appropriate permissions to access each directory in the path. x bit = **search** allows the user to search for files in the directory. r bit = allows the user to list the contents of the directory (with 1s for example). w bit = allows the user to create or delete files in the directory.

FDT & GFDT Each process has a File Descriptor Table (FDT), which is an array of file descriptors that the process has opened. The FDT is indexed by file descriptor numbers, and each entry in the FDT points to a File Object in the kernel, which contains information about the open file, such as the current offset, the inode, and the file operations that can be performed on it.

All opened files for every process in the system are saved in one global table, GFDT.

By default, every process has the following three standard FDs: (fd=0) STDIN, the standard input channel, (fd=1) STDOUT, the standard output channel, (fd=2) STDERR, the standard error channel.

file object A file object is a kernel data structure that contains all the information about an open file, including its current offset, the inode it refers to, and the file operations that can be performed on it, the number of file descriptors pointing to it, the mode it was opened with, etc.

# File Systems

Note: The CPU can't directly access/process data on the disk, it must reside on the DRAM.

**HDD Latency** HDD latency is **seek time** + **rotational latency**. Seek time is the time it takes for the read/write head to move to the correct track on the disk. Rotational latency is the time it takes for the disk to rotate to the correct sector.

Sectors & Blocks A disk is divided into sectors, which are the smallest addressable units on the disk. Each sector is typically 512 bytesor 4096 bytes in size. Sectors are grouped into blocks, which are the equivalent of pages in memory, thus each block is 4KB in size, and 8 sectors.

Note: Only the swap area is divided into frames (like the memory) instead of sectors.

Note 2: The disk gurantees that operations on sectors are atomic, meaning that a read or write operation on a sector will either complete successfully or fail without leaving the sector in an inconsistent state.

Partitions & Mounts A disk can be divided into partitions using fdisk, which are contiguous disjoint part of the disk that can host a filesystem. Disks are typically names "/dev/sda", "/dev/sdb", while partitions are named "/dev/sda1", "/dev/sda2", etc.

To create an empty filesystem on a partition we use mkfs, which then after it need to be mounted to make it accessible. Mouniting is done using mount -t <filesystem> <partition> <path> which will then make the filesystem reachable from <path>. If any files existed at <path> before mounting, they will become unavailable until we unmount the filesystem.

# VSFS (Very Simple File System) Blocks are divided into 5 categories:

- Superblock (S) Contains metadata about the filesystem, such as the magic number of the filesystem, the inode of the root directory "/", amount of inodes and data blocks, start of inode table, etc. It is used when mounting the filesystem.
- Inode Table (I) Contains the inodes of all files in the filesystem.
- Data Blocks (D) Contains the actual data of the files in the filesystem.
- bitmap of allocated inodes (i) A bitmap that indicates which inodes are allocated and which are free. Each bit corresponds to an inode.
- bitmap of allocated data blocks (d) A bitmap that indicates which data blocks are allocated and which are free. Each bit corresponds to a data block.

# **VSFS layout**

Figure 17: VSFS File System Layout

VSFS - Finding an inode to find the address of an inode, we can simply do

```
inodeAddr = inodeStartAddr + inodeSize \times inodeIndex
```


and to find the block:

blockAddr = inodeAddr/blockSize

#### **Pointers to data** in VSFS could be:

- **Direct:** An array of pointers pointing directly to all data blocks (limited amount  $\Longrightarrow$  limits file size)
- Indirect: Multi-level array, like in virutal memory page tables.
- Linked List: Linked list of pointers from one data block to the next

Multi-Level Index: Each inode will have an array of 15 pointers such that: (0-11) The first twelve are direct pointers to data blocks, (12) a single-indirect pointer that points to a block completely comprised of pointers to data blocks, (13) a double-indirect pointer that points to a block that contains pointers to single-indirect blocks, and (14) a triple-indirect pointer that points to a block that contains pointers to double-indirect blocks. Note: each indirect access requires an additional disk access, so it is slower than direct access.



**Extents** An extent is a contiguous block of data blocks that are allocated together. Instead of having a separate pointer for each data block, an extent is a single pointer that points to the first block of the extent and contains the length of the extent. This allows for more efficient allocation and reduces fragmentation. Extents are used in modern filesystems such as ext4.

- ext2 = the "extended file system", does not support extents, instead uses the multilevel index.
- $\bullet$  ext3 = ext2 + journaling. journaling = keeping track of uncommitted changes.
- ext4 = ext3 + extents. (so "ext" name unrelated to "extent")

**FAT** (File Allocation Table) Keeping track of a linked list using the data blocks is inefficient. So to solve that, FAT keeps a file allocation table that for each data block, it registers that pointer to the next data block from the same file. The starting block for the file is pointed to by the dirent, which holds all of the metadata too, so no inodes are needed! (but no multipicity of hard links is allowed)

The advantage for FAT is that it will be copied to (cached in) the memory, which allows fast lookup in the table. The disadvantage is that it can become huge.

In the FAT, 0=Free block, (-1)=Broken block (can't be used), (FF)=End of chain, (Other numbers)=Next block in the chain.

# RAID

**RAID** (Redundant Array of Independent Disks) RAID is a technology that allows us to combine multiple physical disks into a single logical disk. It is based on striping, which is the process of dividing data into blocks and distributing them across multiple disks. And redundancy, which is the process of storing multiple copies of data to protect against disk failures.

• **RAID 0** - Striping without redundancy.

- Files are stripped in **block** resolution.
- Pros: Increased performance, as multiple disks can be accessed in parallel.
- Cons: No redundancy, if one disk fails, all data is lost. and increased chance of failure.

# • **RAID 1** - Mirroring.

- Files are striped across half the disks, and each block is mirrored on the other half.
- Pros: Increased reliability, as data is stored on multiple disks. Read performance is as good as RAID 0.
- Cons: Write performance is slower than RAID 0, as data must be written to multiple disks.

# • RAID 4 - Dedicated parity disk.

- Data blocks are striped across multiple disks, and a dedicated parity disk is used to store parity information. RAID 2 is bit resolution, RAID 3 is byte resolution.
- Pros: Improved read performance, as data can be read from multiple disks in parallel. Fault tolerance, as data can be reconstructed from parity information.
- Cons: "small write problem", as writing to a single block requires reading the old data + the parity block, computing the new parity, and writing both the data and the parity block. However, if we write to the entire stripe (whole block on each disk) then we don't have to read the parity to update it, hence "small write problem".

# • RAID 5 - Distributed parity.

- Data is striped across multiple disks, and parity block is distributed each time on a different disk.
- Pros: Like RAID 4 + No hotspot disk.

#### • RAID 6 - Double distributed parity.

- Data is striped across multiple disks, and two independent parity blocks are distributed across the disks.
- Pros: Fault tolerance for up to two disk failures, as data can be reconstructed from the remaining disks.
- Cons: wastes 2/N instead of 1/N of the disk space for parity (compared to RAID 5).
- RAID n+k n data blocks and k parity blocks (in each stripe).

Erasure (n+k) vs. Replication (r) Erasure is the "k parity" blocks, which allows us to reconstruct the data from the remaining blocks. Replication is duplicating the data r times. Erasure is less wasteful but slower, while replication is faster but more wasteful.

# Part II Overall Summary

# **Introduction to Operating Systems**

#### **Core Concepts**

- Operating System (OS): Software that acts as an intermediary, coordinating application execution, providing common services, and managing hardware resources.
- An OS is a reactive, "event-driven" system, unlike typical programs that run start-to-finish. It waits for events and responds to them.
- **Kernel**: The central part of the OS that manages all tasks and hardware. A **bare metal OS** is a non-virtualized OS.
- Events: Can be asynchronous (from external devices like keyboards, networks) or synchronous (from program execution like syscalls, page faults).
- Core OS Services:
  - Isolation: Prevents processes from interfering with each other, often via multiplexing.
  - Abstraction: Hides hardware complexity and provides high-level, portable interfaces.
  - Resource Sharing: Manages hardware like the CPU and memory among multiple applications.
- Privilege Levels (CPL): The CPU defines Kernel Mode (CPL = 0) for privileged instructions and User Mode (CPL = 3) for applications.
- System Call (Syscall): The gateway for user-mode apps to request kernel services. It raises the privilege level to CPL=0 and transfers control to the kernel. On error, they often set the global errno variable.
- **POSIX**: A set of standard OS interfaces based on the Unix operating system.

#### Virtualization

- Virtualization: An abstraction that presents each process with virtual versions of resources (CPU, memory). This provides convenience, portability, and protection, but adds overhead.
- Multiplexing: Creating the illusion that each process has its own dedicated resources when they are actually shared. The OS decides how to divide them.
- Hypervisor: The underlying OS in a virtualized environment that allows running multiple virtual servers on a single physical server.

#### **Basic Hardware**

- **Processor/Core**: Executes machine instructions. Multiple cores run in parallel. (Typical access time: ∼3ns).
- Memory (DRAM): Fast, volatile storage accessible to all cores. (Typical access time: ∼100ns).
- Disk (Storage): Slow, non-volatile (durable) storage.
   Information must be moved to memory for the CPU to process it. (Typical access time: ~1ms).

## Processes & Threads

#### **Processes**

- Process: An instance of a program in execution.
- Multiprogramming: Running multiple processes concurrently on a single core by multiplexing the CPU.

- Multiprocessing: Using more than one core to run a single process.
- Address Space:
  - Code (Text): Program instructions.
  - Static Data: Global/static variables.
  - **Heap**: For dynamic memory allocation (malloc).
- Stack: For function calls and local variables.
- PCB (Process Control Block): OS data structure (task\_struct) to manage a process, pointed to by the current pointer. The process list is a cyclic doubly-linked list.
- PCB Fields: Contains PID, TGID, state, registers, memory info (mm\_struct), family pointers (parent, children), exit code, etc.
- Process States:
  - Running: Executing on the CPU.
  - Ready: Runnable, but waiting for the CPU.
  - Waiting (Sleeping): Waiting for an event (e.g., I/O). States can be TASK\_INTERRUPTIBLE (can be woken by signals) or TASK\_UNINTERRUPTIBLE (cannot, e.g., during a critical I/O operation).
  - Stopped: Execution suspended (e.g., by a debugger via Ctrl+Z).
  - Zombie: Terminated, but its PCB still exists for the parent to collect the exit status via wait().
- Process Family: Idle Process (PID 0) is the first process, which creates the init process (PID 1). Real Parent is the original creator. Parent is the process currently tracing it. Orphans are adopted by the init process.
- Syscalls: fork() (create child), exec() (replace program image), wait()/waitpid() (wait for child), exit() (terminate), kill() (send signal), getpid() (get Thread Group ID), getppid() (get parent PID).
- fork() returns 0 to the child and the child's PID to the parent.

#### Threads

- Threads: Units of execution within a process. In Linux, they are implemented as processes that share resources.
- Multithreading: A process with multiple threads of execution.
  - **Shared**: Memory space (heap, data, code), file descriptors (FDT), working directory, signal handlers.
  - Unique: Stack, registers (incl. PC, SP), Thread ID (TID).
- Thread Group: A set of threads sharing a process ID (PID), which is the Thread Group ID (TGID). getpid() returns TGID, gettid() returns the unique TID.
- An exit() call by any thread terminates the entire thread group.
- Pthreads: POSIX API for threads. pthread\_create(), pthread\_join(), pthread\_exit().
- User Level Threads (ULTs): Managed by a user-level library, invisible to the kernel. Faster context switching but no true parallelism on multi-core systems.
- Kernel Threads: Processes created by the OS to perform kernel tasks. They do not switch the memory space on context switch.

#### **Signals**

- Signal: An asynchronous notification sent to a process about an event. Handled in user mode when returning from the kernel.
- A signal can wake a waiting process (e.g., from a blocking syscall).
- Handling: A process can define a custom handler (signal(), sigaction()), ignore the signal (SIG\_IGN), or use the default action (SIG\_DFL, usually "die" or "ignore").
- Masking: A process can block signals using sigprocmask() to prevent race conditions. Blocked signals become "pending".
- Unblockable Signals: SIGKILL (terminate) and SIGSTOP (suspend) cannot be caught, blocked, or ignored. SIGCONT (resume) is also special.
- Common Signals: SIGSEGV (segfault), SIGILL (illegal instruction), SIGCHLD (child status changed), SIGINT (Ctrl+C), **Signal 0** (null signal to check if a process exists).

# IPC & System Calls

- clone(): Linux syscall to create processes/threads. Arguments control resource sharing:
  - CLONE\_VM: Share memory space.
  - CLONE\_FILES: Share file descriptor table.
  - CLONE\_SIGHAND: Share signal handlers.
  - CLONE\_THREAD: Place in same thread group (implies parent is caller's parent).
- Copy-on-Write (COW): A fork() optimization. The parent's memory pages are not physically copied for the child. A page is only duplicated when the parent or child
- Pipe: Unidirectional kernel memory buffer (int fd[2]) for communication between related processes. blocks if the pipe is empty; write blocks if it is full.
- FIFO (Named Pipe): A special file in the filesystem (mkfifo()) for IPC between unrelated processes. A process opening a FIFO for read-only will block until another opens for write, and vice-versa.

#### Boot & Modules

- Booting Sequence:
  - 1. **BIOS**: Initializes hardware, finds a bootable device. loads the MBR.
  - 2. MBR (Master Boot Record, 512 bytes): Loads the boot loader.
  - 3. Boot Loader (GRUB): Loads the kernel (bzImage) and initramfs (initial RAM filesystem with essential drivers).
  - 4. **Kernel**: Uses initramfs, mounts the real root filesystem, and runs /sbin/init (PID 1).
- Kernel Modules: Dynamically loadable code (e.g., drivers) that can be added at runtime without rebooting. Handled by init\_module() and cleanup\_module().
- Device Files: Special files in /dev representing hardware. Identified by a **major** number (driver) and a **minor** number (device instance).
  - Character: Stream-based (e.g., /dev/tty).

- Block: Block-based, addressable (e.g., /dev/sda).
- Pseudo: Virtual, e.g., /dev/null, /dev/zero.
- file\_operations struct: Kernel struct with function pointers (open, read, etc.) that a driver implements to define its behavior. Registered with register\_chrdev().

# CPU Scheduling

# Concepts

- Time Sharing: The OS virtualizes the CPU by dividing its time among multiple processes, creating an illusion of
- Process Types: I/O-bound tasks are latency-sensitive (e.g., interactive shells). CPU-bound tasks need raw computation speed.
- Preemption: Forcibly stopping a running process to run another. This is managed using a timer interrupt and a time slice called a Quantum.
- Scheduling Metrics:
  - Wait Time:  $T_{wait} = T_{start} T_{submit}$ .
  - Response Time:  $T_{resp} = T_{end} T_{submit}$ .
     Slowdown:  $1 + \frac{T_{wait}}{T_{run}}$ .

# Batch (Non-Preemptive) Schedulers

- FCFS (First-Come, First-Served): Simple and fair, but can suffer from the "convoy effect" where short jobs get stuck behind long ones.
- SJF (Shortest Job First): Optimal for average wait time but requires knowing runtimes in advance and can starve long jobs.
- EASY: An FCFS-based scheduler with backfilling, which allows short, later-arriving jobs to run early if they won't delay the job at the head of the queue.

#### Preemptive Schedulers

- Round Robin (RR): Each process gets one quantum in a circular queue. Good for interactivity. With a very large quantum, it behaves like FCFS.
- SRTF (Shortest Remaining Time First): Preemptive version of SJF. Optimal for average response time but still risks starvation.
- Selfish RR: A two-level queue system. New processes wait in a FIFO queue while "old" processes are scheduled with RR. Promotes fairness using an "aging" mechanism to eventually move new jobs to the old queue.
- Gang Scheduling: An RR variant for parallel jobs, where all threads of a job are scheduled to run concurrently in the same time slot.

#### Linux Schedulers

- Linux  $\leq$  2.4 (O(n) scheduler):
  - Policies: SCHED\_RR, SCHED\_FIFO (real-time), SCHED\_OTHER (default).
  - **Epoch**: A period where every runnable task gets a chance to run. At the end of an epoch, priorities are recalculated for \*all\* tasks.
  - Priority: A combination of fixed static priority (user-space nice value from -20 to +19) and a dynamic priority, or counter, which is the remaining time slice.

- The counter is recalculated for a task at a new epoch:  $C_{new} = \lfloor \frac{C_{old}}{2} \rfloor + P_{static}$ . This formula favors I/O-bound tasks, as they often don't use their full quantum, so their old counter is not zero when recalculated.
- Core Function: schedule() iterates all runnable tasks to find the one with the best goodness() value (based on counter and other factors).
- CFS (Completely Fair Scheduler,  $O(\log N)$ ):
  - Goal: Give each task a fair share of the processor. It aims to keep each task's virtual runtime (vruntime) equal.
  - vruntime: An accounting variable. The task with the minimum vruntime is chosen to run next.
  - Vruntime advances more slowly for higher-priority (higher-weighted) tasks:  $\Delta vruntime = \Delta T_{actual} \times \frac{W_{ideal}}{W}$ .
  - Data Structure: Uses a red-black tree to store runnable tasks, ordered by vruntime. This makes picking the next task to run very efficient.

### Context Switch

- Context: The complete state of a process (CPU registers, Program Counter, stack pointer, memory state).
- Overhead: Direct (time to save/load CPU state) and Indirect (performance loss from cache pollution, TLB flushes, etc.).
- Types: Forced (involuntary, due to an interrupt) vs. Initiated (voluntary, due to a syscall like wait()).
- Mechanism: The CPU state is saved to the task's kernel stack (in the thread\_struct field of the PCB). A percore hardware struct, the TSS (Task State Segment), is updated to point to the new task's kernel stack.
- Flow: schedule() → context\_switch() → \_switch\_to\_asm() (saves/restores general-purpose registers) → \_switch\_to() (updates kernel stack pointer in TSS).

# Synchronization

# Concepts

- Race Condition: Program outcome depends unpredictably on the timing of concurrent executions.
- Critical Section: A piece of code that accesses shared data and must not be concurrently executed by more than one thread.
- Atomicity: An operation that executes as a single, indivisible, all-or-nothing unit. On multi-core CPUs, this requires hardware support (e.g., lock prefix on x86 instructions).
- Memory Consistency: Defines the order in which memory operations from one CPU core are visible to others. Enforced with a memory fence (or barrier).
- Amdahl's Law: Max speedup from parallelization, where s is the serial fraction and n is processors.

$$Speedup = \frac{1}{s + \frac{1-s}{n}} \le \frac{1}{s}$$

#### **Mechanisms**

- Lock: A primitive with acquire() and release() operations to enforce mutual exclusion.
- Spinlock: A lock that causes a thread to "busy-wait" (spin in a tight loop) until the lock is free. Implemented with atomic instructions like test\_and\_set or compare-and-swap. The volatile keyword is used to prevent compiler reordering of accesses to the lock variable.
- Mutex: A lock that may cause the thread to sleep (block) if the lock is unavailable. Use a spinlock if the expected wait time is less than a context switch; otherwise, use a mutex.
- Semaphore: An integer counter with a waiting queue. wait() (P) decrements (and potentially blocks if 0); signal() (V) increments (and potentially wakes a waiting thread). Can be binary (like a mutex) or counting.
- Condition Variable: Used with a mutex to allow threads to wait for a specific condition to become true (cond\_wait) without busy-waiting. Another thread uses cond\_signal to notify waiters that the condition may now be true.

#### **Deadlocks**

- **Deadlock**: A set of processes are blocked, each waiting for a resource held by another process in the set.
- Livelock: Processes continuously change state in response to each other but make no forward progress.
- Starvation: A process is perpetually denied necessary resources to proceed.
- Four Necessary Conditions for Deadlock:
  - Mutual Exclusion: At least one resource must be non-sharable.
  - 2. Hold and Wait: A process holds at least one resource and is waiting for another.
  - 3. **No Preemption**: A resource cannot be forcibly taken from a process.
  - Circular Wait: A cycle of processes exists, e.g., P<sub>0</sub>
    waits for P<sub>1</sub>'s resource, P<sub>1</sub> waits for P<sub>2</sub>'s, and P<sub>2</sub> waits
    for P<sub>0</sub>'s
- Handling Methods:
  - Prevention: Violate one of the 4 conditions. A common method is to enforce a total ordering on lock acquisition to prevent circular wait.
  - Avoidance: Use algorithms like the Banker's Algorithm to ensure the system never enters an unsafe state by analyzing resource requests.
  - **Detection & Recovery**: Allow deadlocks to occur, detect them (e.g., find a cycle in the resource allocation graph), and recover (e.g., kill a process).

# Virtual Memory

# Concepts

- Virtual Memory (VM): An abstraction that provides each process with a private, large, contiguous address space, isolating it from other processes and from the physical memory layout.
- Page & Frame: VM is divided into fixed-size pages (e.g., 4KB). Physical memory is divided into same-sized frames.

- Address Translation: The MMU (Memory Management Unit) is hardware that translates Virtual Addresses (VAs) to Physical Addresses (PAs) using page tables.
- Page Table: A per-process data structure that maps virtual pages to physical frames.
- PTE (Page Table Entry): An entry in the page table. Contains the physical frame number and control bits: Present (is page in RAM?), Dirty (has page been written to?), Accessed, Read/Write, User/Supervisor.
- Page Fault: A hardware trap to the OS, triggered when a program accesses a page that is not mapped in physical memory (e.g., 'Present' bit is 0).
  - Major Fault: Page must be fetched from disk.
  - Minor Fault: Page is in memory, but the mapping is missing (e.g., first access, Copy-on-Write).
- TLB (Translation Lookaside Buffer): A fast hardware cache on the CPU for recent VA → PA translations to accelerate address translation. A TLB miss requires a hardware page table walk.

## Paging & Swapping

- On-Demand Paging: Pages are loaded from disk into memory only when a page fault occurs for them.
- Swap Area: A dedicated space on the disk used to store pages that are temporarily evicted from physical memorv.
- Paging out: Copying a page from DRAM to the disk (to the swap area for anonymous pages, or its file for named pages). Paging out a named page is only needed if its dirty bit is set.
- **kswapd**: A kernel thread that runs when free memory is low to reclaim page frames by paging them out.
- Thrashing: A state where the system spends excessive time paging data between memory and disk, making little progress on actual computation, because there is not enough physical memory to hold the working sets of active processes.

#### Page Replacement Algorithms

- Goal: When memory is full, choose a victim page to evict.
- Belady's Optimal: Replace the page that will be used furthest in the future (unrealizable, used for benchmarking).
- LRU (Least Recently Used): Replace the page that has not been used for the longest time. Hard to implement perfectly.
- Clock Algorithm: An efficient approximation of LRU using a circular list and a single "referenced" bit per page frame.
- Linux PFRA: Uses two lists (active, inactive) and promotes/demotes pages between them to approximate LRU.

#### Linux Implementation

- Multi-Level Page Tables: x86-64 uses a 4-level hierarchy (PML4, PDPT, PDT, PT) to avoid needing large, contiguous page tables. The CR3 register points to the top-level table (PML4).
- mm\_struct: The kernel's primary memory descriptor for a process address space. Contains pointers to page

- tables (pgd), a list of memory regions (mmap), and usage counters (mm\_users, mm\_count).
- vm\_area\_struct (VMA): Represents a contiguous memory region (e.g., stack, heap, code, mapped file). Has permissions like VM\_READ, VM\_WRITE, VM\_EXEC, and flags like VM\_SHARED.
- mmap(): Syscall to create a new VMA, mapping files into the address space (file-backed) or allocating anonymous memory.
- Copy-on-Write (COW): On fork(), the parent's writable, private pages are shared with the child and marked as read-only in both processes' page tables. A page fault on a write triggers the kernel to make a private, writable copy for the writing process.

# Storage & Filesystems

#### Storage Devices

- HDD (Hard Disk Drive): Mechanical storage. Access time = seek time + rotational latency. Performance is best for sequential access.
- SSD (Solid State Drive): Flash memory-based. Much lower latency for random access than HDDs. Cannot overwrite data in place; must erase larger blocks.
- DMA (Direct Memory Access): A hardware mechanism allowing devices (like disks) to transfer data directly to/from main memory without involving the CPU, which is notified by an interrupt upon completion.

#### **RAID**

- RAID 0 (Striping): Data is striped across disks. Provides the best performance but no redundancy. One disk failure leads to total data loss.
- RAID 1 (Mirroring): Data is duplicated across disks. Provides full redundancy but has a 50% capacity cost.
- RAID 4 (Striping with Parity Disk): Stripes data and stores parity information on a single dedicated disk. The parity disk becomes a write bottleneck.
- RAID 5 (Striping with Distributed Parity): Stripes data and distributes parity blocks across all disks, avoiding the RAID 4 bottleneck. Protects against a single disk failure.
- RAID 6 (Striping with Dual Parity): Distributes two independent parity blocks. Protects against two concurrent disk failures.

#### Filesystem Concepts

- File: A logical, non-volatile unit of information with a name, content, and metadata.
- inode (index node): A data structure containing file metadata: permissions, size, owner, timestamps, and pointers to the file's data blocks. The filename is not in the inode.
- direct (directory entry): An entry in a directory file that maps a human-readable filename to an inode number.
- Links:
  - Hard Link: A second directory entry pointing to the same inode. Must be on the same filesystem. The file is deleted only when its link count (in the inode) drops to zero.

- Symbolic (Soft) Link: A special file that stores a
  path string to another file. Can cross filesystems and
  can be "dangling" if the target is removed.
- File Descriptor (FD): A small, per-process integer handle for an open file. It is an index into the per-process File Descriptor Table (FDT).
- Each FDT entry points to a system-wide File Object (representing an open file instance), which in turn points to the file's inode.

# Filesystem Implementation

- Layout: A filesystem on disk typically contains a superblock (global FS metadata), bitmaps (to track free inodes and data blocks), an inode table, and data blocks.
- Allocation Methods:
  - Multi-Level Index: An inode contains direct pointers to data blocks, plus single, double, and triple indirect pointers to handle very large files.
  - Extents: A contiguous run of data blocks, stored as (start block, length) pairs. Reduces fragmentation and metadata overhead compared to block pointers. Used in ext4.
  - FAT (File Allocation Table): A simple FS that uses a table in memory to form linked lists of data blocks for each file. No inodes; metadata is in the directory entry.
- **Journaling**: Writing metadata changes to a transaction log (**journal**) before applying them to the main filesystem. This ensures filesystem consistency after a crash. Used in ext3/ext4.
- Path Resolution: Translating a path like '/home/user/file.txt' to an inode involves reading each directory in the path to find the next component's inode number. The user needs execute (search) permission on all directories in the path.

# Networking

- Protocol Stack: Layered model for network communication. e.g., L5-Application (HTTP), L4-Transport (TCP/UDP), L3-Network (IP), L2-Data Link (Ethernet).
- TCP (Transmission Control Protocol): Reliable, connection-oriented, stream-based protocol. Uses a 3-way handshake to establish connections, sequence numbers and ACKs for reliability, and manages flow control and congestion control.
- UDP (User Datagram Protocol): Unreliable, connectionless, datagram-based. Low overhead, but packets can be lost, reordered, or duplicated.
- IP Address: A logical address for a host, composed of a **network part** and a **host part**, as defined by the subnet mask.
- Socket: A communication endpoint represented by a file descriptor. A TCP connection is uniquely identified by a 5-tuple: (protocol, source IP, source port, destination IP, destination port).
- Client-Server Flow (TCP): Server: socket → bind
   → listen → accept. Client: socket → connect.
- Ethernet (L2): The dominant LAN technology. Uses MAC addresses (48-bit unique hardware addresses) for local delivery.
- Key Protocols:
  - ARP (Address Resolution Protocol): Translates an IP address to a MAC address on a local network.
  - DHCP (Dynamic Host Config. Protocol): Allows a host to automatically obtain an IP address and other network settings.
  - NAT (Network Address Translation): Allows multiple devices on a private network to share a single public IP address.

# Part III Highlights and Notes

# Processes & Threads

#### **Processes**

- Process: Program in execution.
- Multiprogramming: Concurrent processes on one
- Multiprocessing: One process on multiple cores.
- Address Space: Code (Text), Static Data, Heap, Stack.
- PCB (Process Control Block): task\_struct, pointed to by current.
- PCB Fields: PID, TGID, state, registers, mm\_struct, family pointers, exit code.
- Process States:
  - Running: On CPU.
  - Ready: Waiting for CPU.
  - Waiting (Sleeping): For event. TASK\_INTERRUPTIBLE, TASK\_UNINTERRUPTIBLE.
  - **Stopped**: Suspended.
  - **Zombie**: Terminated, PCB exists for wait().
- Process Family: Idle (PID 0)  $\rightarrow$  init (PID 1). Real Parent, Parent, Orphans (adopted by init).
- Syscalls: fork(), exec(), wait()/waitpid(), exit(), kill(), getpid(), getppid().
- fork(): returns 0 to child, PID to parent.

#### **Threads**

- Threads: Execution units within a process.
- Multithreading: Process with multiple threads.
  - Shared: Memory space, FDT, directory, signal han-
  - Unique: Stack, registers (PC, SP), TID.
- Thread Group: Threads sharing a PID (TGID).  $getpid() \rightarrow TGID, gettid() \rightarrow TID.$
- exit() terminates the entire thread group.
- pthread\_create(), pthread\_join(), • Pthreads: pthread\_exit().
- User Level Threads (ULTs): Managed by userlibrary, no true parallelism.
- Kernel Threads: OS-level tasks, no memory space switch.

#### **Signals**

- Signal: Asynchronous notification.
- Wakes a waiting process.
- Handling: Custom handler (sigaction()), ignore (SIG\_IGN), default (SIG\_DFL).
- Masking: Block signals (sigprocmask()), becomes "pending".
- Unblockable Signals: SIGKILL, SIGSTOP.
- Common Signals: SIGSEGV, SIGILL, SIGCHLD, SIGINT, Signal 0.

# IPC & System Calls

- clone(): Creates processes/threads. Flags: CLONE\_VM, CLONE\_FILES, CLONE\_SIGHAND, CLONE\_THREAD.
- Copy-on-Write (COW): fork() optimization, duplicates page on write.
- Pipe: Unidirectional buffer (int fd[2]).

• FIFO (Named Pipe): Filesystem pipe (mkfifo()) for unrelated processes.

# Boot & Modules

- Booting Sequence: BIOS  $\rightarrow$  MBR  $\rightarrow$  Boot Loader  $(GRUB) \rightarrow Kernel (/sbin/init).$
- Kernel Modules: Dynamically loadable code (init\_module(), cleanup\_module()).
- Device Files: In /dev. Major (driver), minor (instance).
  - Character: Stream-based.
  - **Block**: Addressable.
  - Pseudo: Virtual (/dev/null).
- file\_operations struct: Driver function pointers, registered with register\_chrdev().

# CPU Scheduling

# Concepts

- Time Sharing: CPU virtualization.
- Process Types: I/O-bound (latency-sensitive), CPU-bound.
- Preemption: Forcible process stop, via Quantum.
- Scheduling Metrics:
  - $-T_{wait} = T_{start} T_{submit}.$

  - $T_{resp} = T_{end} T_{submit}.$   $Slowdown: 1 + \frac{T_{wait}}{T_{run}}.$

# Batch (Non-Preemptive) Schedulers

- FCFS: First-Come, First-Served.
- SJF: Shortest Job First.
- EASY: FCFS with backfilling.

#### Preemptive Schedulers

- Round Robin (RR): Quantum-based circular queue.
- SRTF: Shortest Remaining Time First.
- Selfish RR: Two-level queue with aging.
- Gang Scheduling: RR for parallel jobs.

#### Linux Schedulers

- Linux < 2.4 (O(n)):
  - **HZ**: Time interrupts per second.
  - **Tick**: Time between time interrupts.
  - Policies: SCHED\_RR, SCHED\_FIFO, SCHED\_OTHER.
  - **Epoch**: Cycle for all runnable tasks.
  - **Priority**: Static (nice) + Dynamic (counter).
- New epoch counter:  $C_{new} = \lfloor \frac{C_{old}}{2} \rfloor + P_{static}$ .
- schedule() finds best goodness().
- **CFS** (O(log N)):
  - Goal: Fair CPU time via equal vruntime.
  - **vruntime**: Task with lowest runs.
  - $-\Delta vruntime = \Delta T_{actual} \times \frac{W_{ideal}}{W_{tank}}$ .
  - Red-black tree ordered by - Data Structure: vruntime.

# Context Switch

• Context: Process state.

Overhead: Direct (save/load state), Indirect (cache pollution).

• Types: Forced (interrupt), Initiated (syscall).

• Mechanism: State saved to kernel stack. TSS updated.

 Flow: schedule() → context\_switch() -\_switch\_to\_asm() → \_switch\_to().

# Synchronization

# Concepts

• Race Condition: Timing-dependent outcome.

• Critical Section: Requires mutual exclusion.

• Atomicity: All-or-nothing operation.

• **Memory Consistency**: Order of memory ops, enforced by **memory fence**.

• Amdahl's Law:

$$Speedup = \frac{1}{s + \frac{1-s}{n}} \le \frac{1}{s}$$

#### Mechanisms

• Lock: acquire() and release().

• Spinlock: Busy-waits for lock.

• Mutex: May block (sleep) if lock is unavailable.

• Semaphore: Counter with wait queue. wait() (P), signal() (V).

• Condition Variable: Wait for condition inside critical section. cond\_wait, cond\_signal.

#### **Deadlocks**

 Deadlock: Processes blocked waiting for each other's resources.

• Livelock: State changes, no progress.

• Starvation: Process perpetually denied resources.

• Four Necessary Conditions: Mutual Exclusion, Hold & Wait, No Preemption, Circular Wait.

• Handling:

Prevention: Violate one condition (e.g., lock ordering).

- Avoidance: Banker's Algorithm.

- Detection & Recovery: Find cycle and kill process.

# Networking

• Protocol Stack: L5-App, L4-Transport, L3-Network, L2-Link.

• TCP: Reliable, connection-oriented, stream-based.

• UDP: Unreliable, connectionless, datagram-based.

• IP Address: Logical host address (network part + host part).

• Socket: Communication endpoint (FD). 5-tuple identifies connection.

 TCP Flow: Server: socket → bind → listen → accept. Client: socket → connect.

• Ethernet (L2): LAN technology, uses MAC addresses.

• **Key Protocols**: **ARP** (IP → MAC), **DHCP** (dynamic IP), **NAT** (private ↔ public IP).

# Virtual Memory

# Concepts

• Virtual Memory (VM): Private, contiguous address space abstraction.

• Page (virtual, 4KB) & Frame (physical).

 Address Translation: MMU translates VA → PA via page tables.

• Page Table: Maps virtual pages to physical frames.

• PTE (Page Table Entry): Contains frame number and bits: Present, Dirty, Accessed, R/W, U/S.

• Page Fault: Trap on access to unmapped page.

Major Fault: Fetch from disk.

Minor Fault: Page in memory, mapping missing.

• **TLB**: Hardware cache for VA  $\rightarrow$  PA translations.

# Paging & Swapping

• On-Demand Paging: Load pages on first access.

• Swap Area: Disk space for evicted pages.

• Paging out: Copying page from DRAM to disk.

• kswapd: Kernel thread to reclaim page frames.

• Thrashing: Excessive paging, little progress.

# Page Replacement Algorithms

• Goal: Choose victim page to evict.

• Belady's Optimal: Replace page used furthest in future.

• LRU: Replace least recently used page.

 Clock Algorithm: LRU approximation with reference bit.

Linux PFRA: Two lists (active, inactive) to approximate LRU.

## Linux Implementation

• Multi-Level Page Tables: 4-level on x86-64. CR3 points to top level.

• mm\_struct: Process memory descriptor.

• vm\_area\_struct (VMA): Contiguous memory region.

• mmap(): Creates a new VMA.

• Copy-on-Write (COW): On fork(), share pages, copy on write.

# Storage & Filesystems

#### **Storage Devices**

• HDD: Access time = seek time + rotational latency.

• SSD: Flash memory, low random access latency.

• **DMA**: Device-to-memory transfer without CPU.

#### **RAID**

• RAID 0 (Striping): Best performance, no redundancy.

• RAID 1 (Mirroring): Full redundancy.

 RAID 4 (Parity Disk): Write bottleneck on parity disk.

- RAID 5 (Distributed Parity): No parity disk bottleneck.
- RAID 6 (Dual Parity): Protects against two disk failures.

# Filesystem Concepts

- File: Logical unit of information.
- inode: File metadata structure.
- dirent: Maps filename to inode number.
- Links: Hard Link (same inode), Symbolic Link (path

string).

- File Descriptor (FD): Integer handle for an open file, index into FDT.
- FDT entry  $\rightarrow$  system-wide **File Object**  $\rightarrow$  **inode**.

# Filesystem Implementation

- Layout: Superblock, bitmaps, inode table, data blocks.
- Allocation: Multi-Level Index, Extents, FAT.
- Journaling: Transaction log for consistency.
- Path Resolution: Traverse directories to find inode.