Mutex from Scratch

Concurrency primitives in C++

Outline

- What is the C++ concurrency model?
- Let's implement std::atomic<T> in the compiler.
- What is a mutex? how does it differ from a spinlock?
- Let's implement std::mutex using Linux futexes.
- Let's implement std::condition_variable using Linux futexes.
- What other things in the STL are "lockable"?
- Let's implement std::once_flag.

The C++ concurrency model

- When we "write to memory," what does that actually mean?
- When we write to memory, who else sees what we write?
- When do we see what someone else has written?
- Who are these "someone elses," anyway?

The C++ concurrency model

- When we "write to memory," what does that actually mean?
- When we write to memory, who else sees what we write?
- When do we see what someone else has written?
- Who are these "someone elses," anyway?

C++03 had no concept of "someone else." There was only the current program, which was single-threaded by definition.

- Memory is just kind of a "scratchpad" for the current thread. Writes may or may not propagate to other threads.
- There's the volatile keyword, but compilers don't really respect it.

The C++ concurrency model

In C++11, the "who else" is some other *thread*. C++11 still doesn't really say what a "thread" is, but at least we have a name for it.

- Each thread can use uncontended memory as its own "scratchpad."
- If two threads are both reading/writing the same memory address "at the same time," bad things happen (undefined behavior).
- To force two operations to happen "at different times," you use something like std::atomic. The C++11 memory model abstractly guarantees that if two threads are reading/writing a std::atomic, then one of the reads/writes definitely "happens-before" the other one.

Useful atomic operations

```
std::atomic<int> x(0);
                                           // lock incl (%rsi)
X++;
int former = x.exchange(43);
                                         // xchgl %eax, (%rsi)
// former now holds the previous value of x
int expected = 43;
                                 // lock cmpxchgl %edx, (%rsi)
bool success = x.compare exchange weak(expected, 44);
// expected now holds the previous value of x
```

Compare-exchange (compare-and-swap)

```
bool atomic<T>::compare exchange weak(T& expected, T desired)
   if (this->value == expected && !spurious_failure()) {
        this->value_ = std::move(desired);
        return true;
    } else {
        expected = this->value ;
        return false;
```

Compare-exchange (compare-and-swap)

```
bool atomic<T>::compare exchange strong(T& expected, T desired)
    if (this->value == expected && !spurious_failure()) {
        this->value_ = std::move(desired);
         return true;
    } else {
        expected = this->value_;
         return false;
                                                         On x86 and x86-64,
                                                         cmpxchgl does this
                                                         whole thing atomically
                                                         with no spurious failure.
```

Compare-exchange (compare-and-swap)

```
bool atomic<T>::compare exchange strong(T& expected, T desired)
    T unchanged = expected;
    do {
        if (this->compare exchange weak(expected, desired))
             return true;
    } while (expected == unchanged);
    return false;
                                                         On PowerPC, ARM, and
                                                         MIPS, CAS-weak and
                                                         CAS-strong are two
                                                         different instruction
```

sequences.

Useful atomic operations

Useful atomic operations

Short isn't always sweet

What does the compiler generate for an atomic operation that has no direct equivalent in your processor's instruction set?

```
std::atomic<int> x(0);
int y = (x &= 1); // There's no x86 instruction for this one!
```

Short isn't always sweet

```
std::atomic<int> x(0);
int y = (x \&= 1); // There's no x86 instruction for this one!
// The above one-liner compiles into the equivalent of this:
int old x = x.load();
int new x = old x & 1;
while (x.compare_exchange_weak(old_x, new_x)) {
    new_x = old_x & 1;
```

Synchronization primitives

When "(A happens-before B) xor (B happens-before A)", I'll say that "A synchronizes with B."

Synchronization primitives are simple software mechanisms provided by a platform to its users for the purpose of making it easy to express *synchronizes-with* relationships.

- mutex
- condition variable
- semaphore*
- monitor*
- barrier*

Mutex from scratch

A **mutex** (short for *mutual exclusion*) has one job — to make sure that only one thread at a time enters a given section of code.

```
// Thread A

int SafeStack::push(int value)
{
    m_mtx.lock();
    m_stack.push(value);
    m_mtx.unlock();
}

Why are these sections "critical"?

// Thread B

int SafeStack::pop()
{
    m_mtx.lock();
    int value = m_stack.top();
    m_mtx.unlock();
    return value;
}
```

Because if threads A and B are reading/writing the memory of m_stack "at the same time," bad stuff (undefined behavior) will happen. We must ensure it doesn't happen.

Mutex from scratch

A mutex is like a coffee-shop bathroom with one key.

- If Alice has the key, Barbara can't get into the bathroom. What does Barbara do instead? She must wait.
- If, while Barbara is waiting, Carol also shows up, then Carol should also wait.
- When Alice comes out and returns the key, one of Barbara and Carol should stop waiting, take the key, and go in. (Not necessarily Barbara, although that would be fair.)



Not a mutex (spinlock)

```
class spinlock {
    std::atomic<bool> m held;
public:
    constexpr spinlock() noexcept : m held(false) {}
   void lock() {
        while (m held.exchange(true)) {}
    void unlock() {
        m held = false;
```

This is like Barbara rattling the doorknob constantly.

Not only is it inelegant, it's actually counterproductive
— Alice will probably take longer to finish, what with all this rattling going on!

We need to teach Barbara how to wait patiently.


Mutex from scratch

A mutex may be **locked** or **unlocked**.

- Suppose thread B is trying to lock the mutex. If the mutex is already locked, then thread B must wait.
- In this context, wait means sleep, which means tell the operating system to deschedule your thread until... later.
- Therefore, in order to implement a mutex, we need to know something about the definition of thread and how to tell the OS to deschedule a thread "until later."



Mutex from scratch




add yourself to the waiters queue

• deschedule yourself

On unlock():

- if anyone's waiting, dequeue him...
- ...and make him runnable again

At least on Linux, "deschedule" and "make runnable" are things that happen inside the kernel, not in userland. The kernel exposes some nice primitives for our use.






Futexes in 30 seconds

WaitingThread

next

thread id


thread_id



A "futex" (fast userspace mutex) is a Linux concept. Actually a futex is just a 32-bit word anywhere in memory — what does the magic is a Linux system call.

futex wait(addr, value) checks whether *addr is equal to value; if it is, the current thread goes to sleep in the queue associated with addr.

futex wake one(addr) wakes up the thread at the front of the queue associated with addr.



The dumbest mutex

```
class mutex {
    std::atomic<int> m state;
    static constexpr int UNLOCKED = 0;
    static constexpr int LOCKED = 1;
public:
    constexpr mutex() noexcept : m state(UNLOCKED) {}
    void lock() {
        while (m state.exchange(LOCKED) != UNLOCKED) {
            futex_wait(&m_state, LOCKED);
    void unlock() {
        m state = UNLOCKED;
        futex wake one(&m state);
```

Barbara (the waiter) is actually doing the right thing here.

The problem with this mutex is that *Alice* is doing something silly!

When Alice gets out, she goes looking for someone who wants the key (futex wake one).

Most of the time, she won't find anyone waiting.

Can we communicate the idea of "nobody is waiting" to Alice, so that she can skip that expensive call?

Ulrich Drepper's mutex

```
class mutex {
    std::atomic<int> m state = 0;
    static constexpr int UNLOCKED = 0, LOCKED_WITHOUT_WAITERS = 1, LOCKED_WITH_WAITERS = 2;
public:
    void lock() {
        int x = UNLOCKED;
        if (m_state.compare_exchange_weak(x, LOCKED_WITHOUT_WAITERS)) {
           // the uncontended case
        } else {
            while (m_state.exchange(LOCKED_WITH_WAITERS) != UNLOCKED) {
                futex_wait(&m_state, LOCKED_WITH_WAITERS);
    void unlock() {
        if (--m_state == UNLOCKED) {
            // the uncontended case
        } else {
            m state = UNLOCKED;
            futex_wake_one(&m_state);
```

"Futexes Are Tricky"
Ulrich Drepper, 2003 (revised 2011)
https://www.akkadia.org/drepper/futex.pdf

Condition variable from scratch

A condition variable is **kind of** like a mutex, in that it has two operations, only one of which is blocking.

Mutex:

- Many threads can queue up on lock.
- Calling unlock unblocks exactly one waiter, who becomes the new "owner".
- You're not allowed to call unlock unless you "own" the mutex.
- If nobody "owns" the mutex then lock doesn't block.

Condition variable:

- Many threads can queue up on wait.
- Calling notify_one unblocks exactly one waiter.
- Anybody can call notify_one.
- wait always blocks.

Condition variable

A condition variable is useful if you're one of the guys who refills the paper towels in the coffee-shop bathroom.

- You want to do a task (refill the towels) if and only if a condition is satisfied (the towel dispenser is empty). If the condition is not satisfied, you must wait.
- Also, if Alice is using the towel dispenser right now, you
 must wait for her to be done. When Alice comes out, if
 you're out of towels, she'll let you know.
- Still, there's the possibility of miscommunication; you should check for yourself. (You also need to check when you arrive at work in the morning.)



Notice that we assume mutual exclusion — that you shouldn't barge in unless you have the key.

We also assume cooperation
— you will sleep, and Alice
will not shirk her duty to wake
you if she uses the last towel.

condition_variable

```
class condition_variable {
    std::atomic<int> m_value = 0;
public:
   void wait(unique_lock<mutex>& lk) {
        int sequence_number = m_value.load();
        if (sequence_number & 1) {
            if (!m_value.compare_exchange_strong(sequence_number, sequence_number + 1)) {
                if (sequence_number & 1) {
                    return;
        lk.unlock();
        futex_wait(&m_value, sequence_number);
        1k.lock();
    void notify_one() noexcept {
        m_value |= 1;
        futex_wake_one(&m_value);
};
```

"Condition variable with futex" Rémi Denis-Courmont, 2016

condition_variable_any

```
class condition_variable_any {
    std::atomic<int> m_value = 0;
public:
   template<class Lockable> void wait(Lockable& lk) {
        int sequence_number = m_value.load();
        if (sequence_number & 1) {
            if (!m_value.compare_exchange_strong(sequence_number, sequence_number + 1)) {
                if (sequence number & 1) {
                    return;
        lk.unlock();
        futex_wait(&m_value, sequence_number);
        lk.lock();
    void notify_one() noexcept {
        m_value |= 1;
        futex wake one(&m value);
};
```

"Condition variable with futex" Rémi Denis-Courmont, 2016

Lockable things in the STL

- unique_lock<mutex> an exclusive lock (pthread_mutex_t)
- unique_lock<shared_mutex> a write-lock (pthread_rwlock_t)
- shared_lock<shared_mutex> a read-lock (pthread_rwlock_t)
 We haven't covered reader-writer locks, and we aren't going to.
- unique_lock<recursive_mutex> an exclusive lock that can be "stacked"
 We won't cover this either.

All of these mutexes share a common notion of what it means to "sleep," so they all play nicely with std::condition_variable_any.

The notion of what it means to "sleep" is also shared by std::thread, by the free function std::this_thread::sleep_for(), and by thread-safe static initialization.

once_flag from scratch

```
static std::once_flag flag;
std::call once(flag, [&]() {
    // Do some complicated initialization.
});
Equivalent to this:
static int dummy = [&]() {
    // Do some complicated initialization.
    return 0;
                                                            Calling the lambda;
}();
                                                            dummy is initialized with
                                                            the lambda's result
```

once_flag from scratch

```
class LazyWidget {
   mutable std::once flag mFlag; // protects mCachedValue
   mutable int mCachedValue;
    std::vector<int> mInputs;
public:
    LazyWidget(std::vector<int> v) : mInputs(std::move(v)) {}
    int get() const {
        std::call once(this->mFlag, [this]() {
            this->mCachedValue = expensiveComputation(this->mInputs);
        });
        return this->mCachedValue;
```

once_flag from scratch

mutex:

- Many threads can queue up on lock.
- Calling unlock unblocks exactly one waiter: the new "owner".

 lock blocks only if somebody "owns" the mutex. condition_variable:

- Many threads can queue up on wait.
- Calling notify_one unblocks exactly one waiter.
- Calling notify_all unblocks all waiters.
- wait always blocks.

once_flag:

- Many threads can queue up on call once.
- Failing at the callback unblocks exactly one waiter: the new "owner".
- Succeeding at the callback unblocks all waiters and sets the "done" flag.
- call_once blocks only if the "done" flag hasn't been set.

once_flag from scratch (mtx+cvar)

```
class once flag {
    static constexpr int UNDONE = 0, IN PROGRESS = 1, DONE = 2;
    int m flag {UNDONE}; mutex m mtx; condition variable m cv;
public:
    template<class F, class... Args>
    void call_once(F&& f, Args&&... args) {
        unique lock<mutex> lk(m mtx);
        while (m flag == IN PROGRESS)
            m cv.wait(lk);
        if (m flag == DONE) return;
        m flag = IN PROGRESS;
        lk.unlock();
        try {
            std::forward<F>(f)(std::forward<Args>(args)...);
        } catch (...) {
            lk.lock(); m flag = UNDONE; m cv.notify one(); throw;
        lk.lock(); m_flag = DONE; m_cv.notify all();
```

once_flag from scratch (futex)

```
class once flag {
    static constexpr int UNDONE = 0, IN PROGRESS = 1, DONE = 2;
    std::atomic<int> m futex {UNDONE};
public:
   template<class F, class... Args>
   void call once(F&& f, Args&&... args) {
        int x = UNDONE;
        while (!m futex.compare exchange weak(x, IN PROGRESS)) {
            if (x == DONE) return;
            futex wait(&m futex, IN PROGRESS);
            x = UNDONE:
        try {
            std::forward<F>(f)(std::forward<Args>(args)...);
        } catch (...) {
           m futex = UNDONE; futex wake one(&m futex); throw;
        m futex = DONE; futex wake all(&m futex);
};
```

...at_thread_exit()

```
namespace std {
    void notify_all_at_thread_exit(
        std::condition_variable&,
        std::unique_lock<std::mutex>
    );
} // namespace std
```

Given a lock and a condition_variable, take ownership of the lock from now until the current thread exits. When the current thread exits, after running any destructors associated with the thread's scope (including TLS), unlock the lock and notify the condition variable.

How on earth does the standard library implement this?

libc++ source code

```
typedef vector<pair<condition variable*, mutex*>,
              hidden allocator<pair<condition variable*, mutex*> > > Notify;
__thread_struct_imp::~__thread_struct_imp() // Think of this as std::thread::~thread().
  for ( Notify::iterator i = notify .begin(), e = notify .end();
          i != e; ++i)
      i->second->unlock();
      i->first->notify all();
void __thread_struct_imp::notify_all_at_thread_exit(condition_variable* cv, mutex* m)
  notify .push back(pair<condition_variable*, mutex*>(cv, m));
```

Questions?

Not all at once, please!