1. 必须的依赖工具库

1.1 make版本3.80或以上

```
[linjk@iZwz955enhvt54u0sadnsvZ ~]$ make --version
GNU Make 3.82
Built for x86_64-redhat-linux-gnu
Copyright (C) 2010 Free Software Foundation, Inc.
License GPLv3+: GNU GPL version 3 or later <a href="http://gnu.org/licenses/gpl.html">http://gnu.org/licenses/gpl.html</a>
This is free software: you are free to change and redistrabute it Linjingke 32
There is NO WARRANTY, to the extent permitted by law.
```

- 1.2 GCC编译器
- 1.3 GNU Readline库: 它允许psql记住你输入的每个命令,这样就可以通过上下方向键快速输入之前的命令,默认开启,也可以通过编译参数--without-readline来禁止它,建议保留默认。
- 1.4 Zlib库

示例: sudo yum install -y readline readline-devel openssl openssl-devel zlib zlibdevel

2. 源码包下载,下载地址 https://www.postgresql.org/ftp/source/ 版本 postgresql9.6.12

3. 开始安装

3.1 解压缩

tar -zxvf postgresql-9.6.12.tar.gz cd postgresql-9.6.12 进去

- 3.2 生成makefile文件
- ./configure --prefix=/home/username/postgresql --enable-debug 其中--prefix是指定软件的安装路径, --with选项是指安装本文件依赖的库文件。如有不清 楚可以自己学习下configure命令的相关参数
- 3.3 修改makefile.global

这里要注意的是,由于我希望后面能跟踪代码的运行路径,所以我要在编译configure的时候加上--enable-debug的选项,并且修改src/Makefile.global文件: **CFLAGS = -g** CFLAGS = **-g** -Wall -Wmissing-prototypes -Wpointer-arith -Wdeclaration-after-statement -Wendif-labels -Wformat-security -fno-strict-aliasing -fwrapv 其中参数"-O2"是编译器的优化选项,如果打开了,代码的执行顺序会改变,使得追踪起代码来比较困难。当然去除了优化选项,编译后的可执行文件会比较大,而且会比较慢,所以不太适合生产环境。所以切记这个操作仅仅是在学习的时候而设置的。

3.4 重新configure

输入如下命令:

./configure --prefix=/home/**username**/postgresql --with-perl --with-tcl --with-python --with-openssl

--with-pam --without-ldap --with-libxml --with-libxslt --enable-thread-safety

--with-wal-blocksize=16 --with-blocksize=16 --enable-dtrace --enable-debug

(注释: 命令解释参考http://www.postgres.cn/docs/9.6/install-procedure.html)

缺少依赖时可以使用yum安装, demo

yum search dtrace

sudo yum search dtrace

sudo yum install -y systemtap-sdt-devel.x86 64

或者只指定debug

./configure --prefix=/home/username/postgresql --enable-dtrace --enable-debug

3.5 make

执行make

3.6 安装

make install

3.7 配置环境变量

vi ~/. bashrc

插入:

export PG_HOME=/home/username/postgresq1

export PATH=\$PG HOME/bin:\$PATH

保存后 重新source

执行 source ~/. bash_profile

3.8 目录授权

mkdir /home/username/postgresql/data

mkdir /home/username/postgresq1/log

创建log文件: touch /home/username/postgresql/log/server.log

sudo chown -R username:username /home/username/postgresq1/

4 启动

4.1 初始化 initdb -D /home/username/postgresql/data

执行完成后显示 pg_ctl -D /home/**username**/postgresql/data/ -l logfile start 提示表示成功

其中data目录下: base目录是表空间目录, global目录是相关全局变量目录, pg_hba.conf是访问控制配置文件, postgresql.conf是postgresql主配置文件

4.2 可选配置 (可配可不配)

修改pg_hba.conf:

```
all
                       all
                                                              trust
# IPv4 local connections:
       all
                                      127.0.0.1/32
host
# IPv6 local connections:
host
       all
                       all
                                       ::1/128
 Allow replication connections from localhost, by a user with the
 replication privilege.
                           https://blog.csdn.net/Litrŵstngke32
local replication
```

修改为如下 (0.0.0.0/0表示信任来自所有id连接的客户端,加密方式才有md5):

```
TYPE DATABASE
                                          ADDRESS
                                                                   trust
 IPv4 local connections:
ost all a
                        all
                                          0.0.0.0/0
                                                                   md5
nost
 IPv6 local connections:
      all
                        all
                                          ::1/128
                                                                   trust
nost
 Allow replication connections from localhost, by a user with the
 replication privilege.
local replication
                        all
                                          127.0%0 th/32//blog.cschրագրել/Linjingke32
::1/128
                         all
nost
       replication
       replication
```

修改postgresgl.conf:

```
# - Connection Settings -

# listen_addresses = 'localhost'  # what IP address(es) to listen on;

# comma-separated list of addresses;

# defaults to 'localhost'; use '*' for all

# hetange / etalings coediante t/Linjingke 32

# (change requires restart)
```

localhoat改为*,表示监听所有网络连接。

连接参数保持默认:

```
# CONNECTIONS AND AUTHENTICATION
57 # - Connection Settings -
59 #listen_addresses = '*'
                                               # comma-separated list of addresses;
60
61
62
                                               # (change requires restart)
63 \text{ #port} = 5432
                                                 (change requires restart)
64 max_connections = 100
                                               # (change requires restart)
65 #superuser_reserved_connections = 3
66 #unix_socket_directories = '/tmp'
                                               # (change requires restart)
                                               # comma-separated list of directories
                                               # (change requires restart) | injingke32
68 #unix_socket_group = ''
   #unix_socket_permissions = 0777
```

防火墙开放端口

sudo firewall-cmd --zone=public --add-port=5432/tcp --permanent sudo firewall-cmd --reload

4.3 启动PG

pg_ctl -D /home/username/postgresql/data/ -l /home/username/postgresql/log/server.log start

4.4 连接

psql -d postgres

4.5 数据库的基本操作

参考http://www.postares.cn/docs/9.6/ 第二和第三章

内容参考自:

- 1.http://www.postgres.cn/docs/9.6/installation.html
- 2.https://www.cnblogs.com/flying-tiger/p/5859393.html
- 3.https://www.2cto.com/database/201805/748632.html
- 4.http://www.postgres.cn/docs/10/