Contents
Preface 3
Translations
Windows Preparation
Shortcuts
Welcome 6
Choose a Language
Choose wallet mode
About the Simple/Bootstrap mode
Create a Wallet 11
Create new wallet
Add a password
Daemon settings
Starting a local node (full node)
Create new wallet from hardware
How hardware wallets work with Monero GUI
Prepare your device
Create a wallet from your hardware wallet device
Ledger troubleshooting
Trezor troubleshooting
Add a password
Daemon settings (Advanced mode)
Starting a local node (full node)
Receive and Send Monero with your hardware wallet
Restore wallet from keys or mnemonic seed
Restoring from seed
Restoring from keys
Open a wallet from file
Synchronization 25
Daemon synchronization
Daemon synchronization with local node
Daemon synchronization with remote node
Block height
Wallet synchronization
Wallet restore height
How to change Wallet restore height / Wrong or zero balance after synchronizing 27
How to speed up wallet initial synchronization
Monero Account 29
1
Send Monero 31
Address Book
Receive Monero 33
Merchant mode
Transactions History 36
Advanced Features 38
Solo mining
Prove - Check
Prove Transaction
Check Transaction
Shared RingDB
Sign - verify Message
Sign
Verify
Sign - verify File
Sign
Verify
Settings 48
Wallet

Interface	
Local Node	. 49
Remote Node	51
Log	52
Info	2
Seed and keys	54
Binaries Verification 56	
About remote nodes 57	
Bootstrap nodes	57
Common issues and solutions 58	
2	
Preface	

This guide is open source and maintained by ErCiccione, of the Monero community. If you have suggestio or wish to contribute to the development of this guide, feel free to open Pull Requests or Issues on the GitHubrepositorywherethisdocumentismaintained: github.com/monero-ecosystem/monero-GUI-guide. For the online version of this guide, click here

Translations

Thisdocumentwillbelocalizedintoseverallanguages. Youwillfindallavailabletranslationsinthededicated section on GitHub after the next version (1.6) of this guide will be released.

Windows Preparation

If you are on Windows:

Make sure that your antivirus does not block the program.

A miner is included in the Monero GUI software and, as a result, most anti virus software flags the Monero GUI files as malware and subsequently quarantines them. Fortunately, however, there's a fairly trivial work around you can use. That is:

- Create a new directory / folder.
- Open your AV software.
- Add an exception for the newly created directory / folder. Put differently, you have to whitelist the newly created directory / folder.
- Extract the .zip file (in case of Windows) or the .tar.bz2 file (in case of Linux or Mac OS X) to the whitelisted directory / folder.

Note: if you're using Windows and did not install custom anti virus software, Windows Defender is, most likely, acting as active anti virus software.

• The first time you start the wallet you must give permission to connect to the network via a pop-up. Check the appropriate boxes and click Allow access.

Shortcuts

Some shortcuts are available to make the user experience with the GUI easier:

On all operating systems:

Press Ctrl to view each page shortcut. Press ctrl+"shortcut" to go to that page

Figure 1: win firewall check

4

On Linux/Windows:

ctrl + tab -> go to the next page

ctrl + shift + tab -> go to the previous page

On macOS:

cmd + tab -> go to the next page

cmd + shift + tab -> go to the previous page

5

Welcome

Extract the package and click on monero-wallet-qui. The following window should open:

Figure 2: Welcome

Welcome to Monero GUI Wallet.

(1) Language: Clickheretoopenalistofavailablelanguages. Selectyourdesiredlanguagefromthelist.

(2) Continue: Click here to continue to the next screen.

6

If Monero GUI isn't displaying graphics correctly, you can try starting it in low graphics mode. If you're using Windows, please open start-low-graphics-mode.bat file located in your Monero GUI

folder. You can find it in C:\Program Files\Monero GUI Wallet or you can find a shortcut for it in Start Menu > Monero GUI Wallet > Utilities. If you're using Linux, please try using the command QMLSCENE_DEVICE=softwarecontext ./monero-wallet-gui. Most macOS users shouldn't have graphic problems with Monero GUI, since it comes with OpenGL installed.

Choose a Language Figure 3: Language

You'll see a list of available languages, click on the one of your choice to change it and continue from the welcome screen. Note: You will be able to change the language later by clicking on the flag in the upper-le corner.

(1) Close: Cancel and return to the previous screen.

Figure 4: mode

8

Choose wallet mode

This page lets you choose the mode that best suits your accessibility and privacy needs.

Note: Stagenet and Testnnet only supports Advanced mode.

- (1) Simple mode: In this mode your wallet will display a simple interface with easy access to basic functionality like sending, receiving, transactions history, address book, accounts, and merchant mode, as well as hardware wallet support. It will connect to a third-party server (a remote node), and it will not start a local node in your computer (the blockchain will not be downloaded). Choose this option if you don't have enough space to store the blockchain file (at least 90 GB), if you don't require maximumprivacyandyouaccepttheprivacyrisksofusingaremotenodetoconnecttotheMoneronetwork.

 (2) Simple mode (bootstrap): In this mode your wallet will also display a simple interface with easy
- access to basic functionality. Additionaly it will start a local node in the background. This local node will start the download of the blockchain file (at least 90 GB), which can take several hours or even days to complete. While the blockchain file is being downloaded, your local node will temporarily connect to a third-party server (a remote node known as bootstrap node), which will allow you to start using Monero immediately. After downloading and synchronizing the blockchain and the wallet, your local node will only temporarily connect to the bootstrap node when your blockchain is not updated. Be aware that using a remote node (including a bootstrap node) to connect to the Monero network may reduce your privacy.
- (3) Advanced mode: In this mode your wallet will display all advanced features available, like changing fees/transactionpriority, solomining, messageverification, transactionproof/check, offlinetransaction signing, keyimagesimporting, customremotenode (including.onionremotenodes), custombootstrap node, starting a local node without setting a bootstrap node (maximumprivacy), changing blockchain location, and daemon log. In this mode you can choose if you want to connect to the Monero network via a remote node or a local node. If you decide to run a local node, the blockchain file will be downloaded. If you want to start using Monero immediately, you can also set a bootstrap node (remote node) in the Settings > Node page. To achieve maximum privacy in your connection to the Monero network, it's recommended to avoid using a remote/bootstrap node and instead use advanced mode to start a local node without setting a bootstrap node.
- (4) Change language: This will let you choose the language from the startup page (again).

About the Simple/Bootstrap mode

Upon choosing simple mode or bootstrap mode, an acknowledgement page will be shown, explaining the features, behavior, and privacy constraints of the mode.

Please carefully read those informations before accepting the implications of this mode and proceed to the next step.

You must understand the inherent risks of using a remote node for your privacy, and you should avoid using it with large amounts of money. If you connect to a malicious remote node, it could track your IP address, your "restore height" and associated block request data, and send you inaccurate information to learn mor about transactions you make.

- (1) Region: Choose a region to pick up the remote nodes from. The closer the node is, the better the wallet performance will be.
- (2) Acknowledgement: Check This box if you have fully understood the privacy implications of a remote node and agree to weaken your privacy by using it.

Figure 5: acknowledgement

10

Create a Wallet

Figure 6: welcome

Onthispageyoucancreateanewwallet,openanexistingwallet,changewalletmodeorchangechoosehow to connect to the wallet and to the network:

(1) Create a new wallet: Start the procedure to create a new wallet file. Choose this option if this is your first time using Monero.

(2) Create new wallet from hardware: Create a new wallet file from a hardware wallet device (e.g.,

11

Ledger or Trezor).

- (3) Open a wallet from file: Choose this option to select a pre-existing wallet file from your computer (with the extension .keys).
- (4) Restore wallet from keys or mnemonic seed: Click here if you want to recover a pre-existing wallet using the mnemonic seed or the private keys, creating a new wallet file.
- (5) Change wallet mode: Clickheretoswitchbetweensimple, simple (bootstrap), and advanced modes. Advanced options (requires wallet in advanced mode):

(6) Mainnet: Select this from the dropdown list to use the main Monero network

- (7) Testnet: Select this option if you would like to use a development network instead of the main network. Testnet is designed to let developers test new features that are not available on Mainnet or Stagenet.
- (8) Stagenet: Select this option if you would like to use a network for staging instead of the main network. Stagenet mimics the features of Mainnet and is designed to let end users test Monero without the risk of losing funds.
- (9) NumberofKDFrounds: AdjustthenumberofKeyDerivationFunctionroundsinordertoenhance the overall security of the generated keys. Any random large number will increase the security. Create new wallet

Here you can create a new wallet file:

- (1) Wallet name: Give a name for your wallet (in this example testname is used).
- (2) Mnemonic seed: Write down your mnemonic seed and keep it safe. Your seed is the master key of your wallet, you can use it to recover your funds.
- (3) Wallet location: Select the destination folder of the wallet.

Add a password

Addastrong passwordtoprotect yourwallet. If youloseyourpassword, then onlyyourmnemonic seedcan recover your wallet.

Daemon settings

This page will open if your wallet is in advanced mode. Here you can choose if you are going to start a local node or connect to a remote node:

(1) Start node in background: Chock this boy to start a local node (full node) in the background; and

- (1) Start node in background: Check this box to start a local node (full node) in the background and download the blockchain.
- (2) Blockchain location (optional): To store the blockchain somewhere other than default, enter that location here.
- (3) Bootstrap node: Here you can enter the host/IP address and port of a bootstrap node (remote node). Your local node will temporarily connect to this third-party remote node while the blockchain is being downloaded, allowing you to use your wallet immediately. For a list of available remote nodes 12

Figure 7: new

13

Figure 8: add password

14

Figure 9: daemon settings

15

and info about them, check the About remote nodes section of this guide.

(4) Connect to a remote node: Check this box if you just want to use a remote node without downloading the blockchain. Enter the host/IP address and port of the remote node after checking the box.

Starting a local node (full node)

If you have selected to start a local node, every time you open your wallet you will see this pop up window Figure 10: sync

It has a countdown that allows you to change some settings before your wallet connects to the local node.

If you don't want to change any setting, just let the countdown finish and your local node will be started automatically.

Create new wallet from hardware

Monero GUI currently supports the hardware wallet models Ledger Nano S/X and Trezor Model T. How hardware wallets work with Monero GUI

- Themainfunction of your hardware wallet is to store your recovery seed in a device that never connects to the internet.
- Yourdevicehasasinglerecoveryseed, which is used to create Bit coin and alt coins wallets, like Monero.
- The recovery seed stored in your device will be used to generate two Monero private keys: a view key and a spend key.
- Your private view key is exported from your hardware wallet device to the Monero GUI wallet.
- Your private spend key never leaves your hardware wallet device. It is required to sign transactions.
- How it works: 1) Monero GUI creates an unsigned transaction; 2) The unsigned transaction is sent to your hardware wallet device; 3) Your device asks if you want to confirm the transaction (sign the transaction with your private spend key); 4) After confirmed, the signed transaction is sent back to Monero GUI; 5) Monero GUI transmits the signed transaction to the Monero network Prepare your device

If you are using a Ledger Nano S/X, please make sure: + Your device is plugged in and unlocked + Your device has already been initialized before (your device already has a recovery seed) + Your device has the most recent firmware version (available in Manager section of Ledger Live desktop app) (see instructions for Nano S/Nano X) + Your device has the Monero app installed (available in Ledger Live desktop app) + Your device is running the Monero app + Your computer has no other cryptocurrency wallet running in the background, like Ledger Live

16

If you are using a Trezor Model T, please make sure: + Your device is plugged in and unlocked + Your device has already been initialized before (your device already has a recovery seed) + Your device has the most recent firmware version (available in Trezor Wallet) (see instructions) + Your computer has no other cryptocurrency wallet running in the background, like Trezor Wallet

Create a wallet from your hardware wallet device

Figure 11: 2.4.1

On this page you can create a new Monero wallet file from your hardware wallet device. This wallet file will be stored in your computer and, every time you open it, Monero GUI will ask you to connect and unlock your hardware wallet. If your device is using a passphrase, your passphrase will also be requested.

- (1) Wallet name: Give a name for your wallet file (in this example ledger-test is used).
- (2) Wallet location: Select the destination folder of the wallet file.
- (3) Create a new wallet from device: Select this option if this is the first time you use a hardware wallet.
- (4) Restore a wallet from device: Choose this option if you already had a hardware wallet and want 17

to restore it.

Creation Date or Restore height (optional): Restore only: If you know the date or block height that your wallet was created at, you can specify it here so the wallet doesn't have to scan the entire blockchain looking for your funds. For example, if your first transaction was included on 2017-07-08 in block 1350000, you should put the previous day date (e.g. 2017-07-06) or a slightly lower height (e.g. 1330000) so the wallet will start scanning from there, saving you some time. More information about restore height on StackExchange.

- (5) Subaddress lookahead (optional): pregenerate a number of accounts with a number of subaddresses each.
- (6) Device name: Select the hardware wallet you want to use. Monero GUI currently supports the hardware wallet models Ledger Nano S/X and Trezor Model T. Ledger troubleshooting
- Ifyoucan'tconnecttoyourLedger,tryrestartingyourcomputer,usingadifferentUSBcable,changing the USB port, or connecting to a different computer. Avoid using USB hubs.
- If your Monero GUI wallet is slow while using Ledger, make sure you're allowing your Ledger device to export the private view key to your computer. You should only export the private view key when using o■icial Monero software.
- Step by step guide for all operating systems (StackExchange): How do I generate a Ledger Monero wallet with the GUI (monero-wallet-gui)?

Trezor troubleshooting

- Ifyoucan'tconnecttoyourTrezor,tryrestartingyourcomputer,usingadifferentUSBcable,changing the USB port, or connecting to a different computer. Avoid using USB hubs.
- If you still can't connect, try installing Trezor Bridge. It's usually not necessary to install Trezor Bridge, but some systems may require it to communicate with Trezor.
- Step by step guide for all operating systems (StackExchange): How do I generate a Trezor Monero wallet with the GUI (monero-wallet-gui)?

Add a password

Add a strong password to protect your wallet file. If you forget the password of a wallet created from your hardware wallet, you will be able to create another wallet from your hardware device.

Daemon settings (Advanced mode)

Here you can choose if you are going to run a full node or use a remote one:

- (1) Start node in background: Check this box to run a full node and begin blockchain sync.
- (2) Blockchain location (optional): To store the blockchain somewhere other than default, enter that location here.
- (3) Bootstrap node: To use a bootstrap node enter the host and port. A bootstrap node allows you to use your wallet while you are downloading the blockchain by connecting to a remote node. For alistofavailableremotenodesandinfoaboutthem, checkthe About remotenodes section of this guide.
- (4) Connect to a remote node: Check this box if you want to use only a remote node without downloading the blockchain. You will need to put the host and port of the remote node after checking the box.

18

Figure 12: add password

19

Figure 13: daemon settings

20

Starting a local node (full node)

If you have selected to start a local node, every time you open your wallet you will see this pop up window Figure 14: sync

It has a countdown that allows you to change some settings before your wallet connects to the local node. If you don't want to change any setting, just let the countdown finish and your local node will be started automatically.

Receive and Send Monero with your hardware wallet

WhenusingMoneroGUIwithahardwarewallet, everytime you click on the send button, you will first have to confirm your transaction in your hardware wallet device, and then you will have to confirm it a second time in Monero GUI.

Sometimes you will also have to confirm in your device that you accept exporting the private view key (Ledger and Trezor) and key images (Trezor).

Whenusingahardwarewallet, Monero GUIReceive page will display an additional "Show on device" button. By clicking this button, the address being displayed in Monero GUI should be displayed in your device. If both addresses match, you can be sure that the receiving address being displayed in Monero GUI was indeed created by your hardware wallet, and that it has not been changed by a virus infecting your computer. Restore wallet from keys or mnemonic seed

Restoring from seed

Restoring from your mnemonic seed is the easiest way to recover your wallet. You need to put the following information:

- (1) Wallet name: Give a name for your wallet (in this example testname is used).
- (2) Mnemonic seed: Paste your seed made of 25 (or 24) words.
- (3) Creation Date or Restore height (optional): If you know the date or block height that your wallet was created at, you can specify it here so the wallet doesn't have to scan the entire blockchain looking for your funds. For example, if your first transaction was included on 2017-07-08 in block 1350000, you should put the previous day date (e.g. 2017-07-06) or a slightly lower height (e.g. 1330000) so the wallet will start scanning from there, saving you some time. More information about restore height on StackExchange.
- (4) Wallet location: Select the destination folder of the wallet.

A detailed guide is available on getmonero.org: 'How to restore your account'

21

Figure 15: restore from seed

Restoring from keys

Figure 16: restore from key

Restoring from keys is quite easy and can be extremely useful, especially if you are moving your wallet fro an online service like MyMonero. You need to put the following information:

(1) Wallet name: Give a name for your wallet (in this example testname is used).

(2) Account address: The address of the wallet you are recovering.

(3) View key: Your private view key (needed to be able to check your funds).

(4) Spend key: Your private spend key (needed to spend your funds).

(5) Creation Date or Restore height (optional): If you know the date or block height that your wallet was created at, you can specify it here so the wallet doesn't have to scan the entire blockchain looking for your funds. For example, if your first transaction was included on 2017-07-08 in block 1350000, you should put the previous day date (e.g. 2017-07-06) or a slightly lower height (e.g. 1330000) so the wallet will start scanning from there, saving you some time. More information about restore height on StackExchange.

(6) Wallet location: Select the destination folder of the wallet.

When everything is ready click the right arrow and then the Use Monero button.

A detailed guide is available on getmonero.org: 'Restoring wallet from keys'

Open a wallet from file

Afterclickingthisoptionawindowwillpopup. Navigatetoyourfilewiththeextension.keys,selectitand click the right arrow.

24

Synchronization

Figure 17: sync_remotenode

After creating and opening a wallet file, Monero GUI will start synchronizing. This process is required to know your balance, receive and send transactions.

Monero GUI's synchronization is composed of two parts: 1) Daemon synchronization 2) Wallet synchronization

Daemon synchronization

Monero GUI wallet uses a daemon (monerod), which is a program running in the background that synchro nizes with the Monero network to scan for incoming transactions and to send new transactions.

Your daemon must have access to the Monero blockchain, which is a very large file (more than 100 GB) which contains all transactions that have been made since the beginning of Monero in 2014. The blockchafile can be stored in your computer (if your daemon run a local node) or in a computer of another person (if your daemon connect to a third-party remote node). If you decide to run a local node, you can run it as a full node, that has the whole blockchain file (more than 100 GB) or as a prunned node, that has a light version of the blockchain file (1/3 of the size, aproximatedly 35 GB).

The best way to contribute to Monero's security and decentralization is running a local node as a full node Even though local nodes running as pruned nodes also contribute to Monero's security and decentralization they are still less comprehensive than full nodes. However, pruned nodes are better for your privacy and to the Monero network than connecting to someone else's remote node.

Daemon synchronization with local node

Ifyourunalocalnodeasafullnode(requireswalletin"advancedmode"withlocalnodeselectedinSetings > Node), your wallet daemon will download the blockchain file into your computer. Since it's a very large 25

file(more than 100 GB), this can takea long time, evendays, depending on yourinternetspeed and storage unit (HDD or SSD).

If you run a local node as a full node with a bootstrap node (requires wallet in "simple mode (bootstrap)"), yourwalletdaemonwillalsodownloadtheblockchainfileintoyourcomputer, butitwillconnecttoaremote node (a bootstrap node) while the download is not finished, allowing you to immediately send/receive a transaction.

If you want to run a local node as a pruned node, see this guide.

Daemon synchronization with remote node

If you want to connect to a remote node (requires wallet in "simple mode" or in "advanced mode" with remotenodeselectedinSettings>Node), yourdaemonwillusetheblockchainofathirdpartyremotenote. Since it will not have to download the whole blockchain file, your synchronization will be faster.

Block height

After your daemon and your wallet are synchronized, your daemon progress bar will display "Daemon is synchronized (number)", see below:

Figure 18: sync_remotenode

This number between parenthesis is the current block height, which is the latest block received by your daemon. In average, this number wil increase +1 every 2 minutes, when a new block is found by a miner. Wallet synchronization

After synchronizing the daemon, your wallet will scan the blockchain file, searching for past transactions. Once a previous transaction is detected and retrieved by your wallet, your balance and your transaction biotony will be undeted

Since all transactions are encrypted in Monero, your wallet will have to decrypt a lot of transactions. This processplacesveryhighdemandsonyourcomputer's resources, including CPU processing and many readings and writings in your hard disk. Depending on your system configuration, this can take a long time, even days, so please be patient. Be aware that the synchronization speed is not always constant. Some blocks can have more transactions and/or use different technologies, therefore they may take longer to verify. Wallet restore height

The wallet restore height is the block number (block height) where your wallet will start searching for transactions. This number should be a block height before the block that included your first incoming 26

transaction. For example, if your wallet received Monero for the first time in 2020-09-20, your wallet restore height must be a block number before the block height of this date. Monero wallets usually ask you to write down your wallet restore height together with your restore seed when you are creating a wallet. You should never set your wallet restore height to 0, otherwise your wallet will scan all transactions in the whole blockchain (since 2014), which takes a lot of time.

How to change Wallet restore height / Wrong or zero balance after synchronizing

In order to see the correct balance, your wallet must be fully synchronized AND using a correct restore height. If your wallet is fully synchronized but your balance is still wrong, you're probably using a wallet restoreheightthatishigherthantheblockheightofyourfirstincomingtransaction. Tosolvethis, youhave tosetanewwalletrestoreheight. GotoSettings>Infopage, Walletrestoreheightandclickon"(Change)".

Figure 19: change_wallet_restore_height

Next, enter a new restore height or an estimate date before your first incoming transaction, and then click on "Ok".

Your wallet will now rescan the blockchain starting from the new restore height.

How to speed up wallet initial synchronization

Somefactorsthatcanincreasethespeedofyourinitialsynchronizationare: *Broadbandinternetconnection *UsingaSSD(solidstatediskdrive)insteadofanHDD(harddiskdrive)*HavingafasterCPU*Connecting to a remote node will avoid downloading the blockchain.

27

Figure 20: set_new_restore_height

28

Monero Account Figure 21: account

The Account tab provides tool to handle your different Monero accounts within your wallet. Each wallet can have multiple accounts, and each account has its own balance. Also, each account can have multiple subaddressesassociatedwithit. Forconveniencesake,theaccountaddressisconsideredthefirstaddress(or subaddress) generated for an account. Since accounts and subaddresses are deterministically derived fro the mnemonic seed, you only need to know the seed in order to restore the account/subaddress structure when restoring a wallet (although any labels you assign to the accounts/subaddresses will need to be added.

again, since they are stored in your wallet file, and not in your mnemonic seed, neither on the blockchain).

(1) Balance All: Let you see the sum of all your accounts balances, unlocked or not.

- (2) Accounts: This is the list of all accounts already generated on your wallet and their corresponding account addresses.
- (3) Create new account: Click on this button to create a new account and set its optional label.

You can change the current account by simply clicking on it on the list.

Each of your accounts are filled with their own informations:

- (4) Label: A name or description of the account for convenience.
- (5) Account Address: Thisisthepublicaddressyoushouldgivetothesenderwhenyouwanttoreceive moneyinthisaccount. Inaccount#0,itstartswith4andcorrespondstothewallet'sprimaryaddress.

In the remaining accounts it corresponds to the account's first subaddress and therefore starts with 8.

- (6) Balance: The account total balance. It cumulates the main address and all subaddresses for this account. Note: Subaddresses are managed in the Receive screen
- (7) Edit Label: Click on this button to edit this account label.
- (8) Copy Address to Clipboard: Click on this button to copy this account address to the clipboard.

Send Monero

Figure 22: send

The Send tab provides tools for creating outgoing transactions.

- (1) Address: This is where you enter the destination address of the transaction. You can either enter a Moneroaddress (a primaryaddress startingwith 4...or asubadress startingwith 8...) or an OpenAlias address (see this page for more information about OpenAlias). Best practice is to copy and paste the address to prevent errors. Since there are malwares that may replace the address of your clipboard withanaddressassociatedwithhackers, you should always verify the destination address afterpasting it. Click on the Address book button on the right side to import an address from the address book of your wallet.
- (2) Amount: This is how much Monero (XMR) you want to send. Click on the All button on the right side to create a transaction spending all the spendable (unlocked) balance available in your selected account. If you have enabled the option to display the balance in other currencies in Settings > Interface, your wallet will also display the amount converted in fiat currency.
- (3) Transaction priority (requires wallet in advanced mode): This is the priority level your transactionwillreceiveinthepooloftransactionswaitingtobeconfirmed. Thehigherthetransaction priority, the faster your transaction will be confirmed (included in a block), but the higher you will pay in transaction fee.

Currently staying with the default or the slow option is likely to get you into the next block.

(4) Description (optional): Here you can add some information regarding your transaction for future reference. This function is for your record keeping only. The description text will be stored in your 31

wallet file and only you will be able to see it. It will not be sent to the receiver, nor stored on the blockchain.

Advanced options (requires wallet in advanced mode)

- (5) Key images: This section allows you to export the key images from your cold wallet into a file, as well as to import this key images file into your view-only wallet. When your view-only wallet has the key images for all outputs, it can display the true balance. In order to import the key images into your view-only wallet, you must use a local node or be connected to a trusted remote node (you can set a trusted remote node in "Settings" > "Node" page). Click on the question mark icon to see step-by-step instructions.
- (6) Offline transaction signing: This feature refers to the practice of keeping the private keys in a cold wallet, which is a wallet installed in an offline ("cold") device. Since the offline wallet never gets connected to the internet, its stored private keys remain secure. The cold wallet is only used to sign individual transactions, which are later sent to the Monero network using a view-only wallet. Click on the question mark icon to see step-by-step instructions.
- (7) Sweep unmixable: This allows you to get rid of outputs which have strange amounts like 0.000006839355 and can't be spent without combining them with another output.

Most users will never need to use this feature.

Address Book

The Address book tab lets you save the name and Monero address of contacts that you frequently transactions.

22

Receive Monero

Figure 23: receive

The Receive tab provides tools for generating subaddresses.

- (1) Addresses: Thislistincludesyourwallet'sprimaryaddress(startingwith4...)andallitssubaddresses (starting with 8...).
- (2) Create new address: Thisbuttonallowsyoutocreateasmanynewsubaddressesasyouwish. Since Monero is private, you don't need to create a new subaddress every time you receive a transaction. 33

However, to avoid off-chain linking, it's recommended that you create a new subaddress for every

person, company or exchange you will receive Monero from. Learn more about subaddresses.

- (3) Set Label: Click on this button to set this subaddress label. You can use this label to store the person, company or exchange you gave this subaddress.
- (4) QR code: This is a QR code that has your selected address embedded into it. It can be used as a way to give others your Monero address by scanning the code.

(5) Save: Click here to save the QR code as a png image.

(6) Copy: Click here to copy the QR code corresponding URL formated as *monero:

Merchant mode

Figure 24: merchant

The Merchant mode offers vendors a simple Point of Sale (PoS) to receive Monero (XMR). It allows you to manually generate payment requests, and to monitor incoming transactions (unconfirmed and confirmed 34

transactions).

- (1) QR code: This is a QR code that contains your currently selected address, and, optionally, the amount to receive. Display this QR code to your customers, so they can scan it and pay using their mobile wallets.
- (2) Amount to receive (XMR):Thisisusedtocreateapaymentrequest. EntertheamountofMonero (XMR) you would like to receive, and the QR code will be updated.
- (3) Payment URL: This is the URL corresponding to the address and amounty ou have chosen. It could be copied by clicking on it and sent to a customer.
- (4) Enable sales tracker: If you tick this box, you'll see a list of incoming transactions. By enabling sales tracker, the merchant page will automatically scan the blockchain and the tx pool for incoming transactions using the QR code. It's up to you whether to accept unconfirmed transactions or not. It is likely they'll be confirmed in short order, but there is still a possibility they might not, so for larger values you may want to wait for one or more confirmation(s).
- (5) Sales: Those are the transactions currently seen on the blockchain and the transaction pool, with associated confirmations.

35

Transactions History

Figure 25: transactions

The Transactions tab let you walk through the transactions sent and received on the currently selected account of your Monero wallet.

- (1) Search: Quickly filter out transactions from the list searching by transaction ID, destination address, description, amount or blockheight (number of the block in which the transaction was mined).
- (2) Sort & Filter: Here you can filter out transactions between specific dates, or sort them by blockheight, date or amount.
- (3) Transaction list: This area displays the sent and received transactions of the currently selected account.

For incoming transactions you will see: Transaction type (Received), Amount, In (your wallet's address which received this transaction and its label), and Date. Because of Monero's privacy-preserving technology, it's not possible to know the sender's address. Therefore, in order to know from who you are receiving each transaction, you should always remember to create and give a new subaddress for every person you will receive Monero from.

Foroutgoingtransactionsyouwillsee: Transaction type(Sent), Amount, To(thedestinationaddress or its Address Book name), and Date.

By clicking on a transaction, you will see the following additional information: Fee (outgoing transactions), Confirmations, Description (optional), Transaction ID, Transaction key, and 36

Blockheight. The transaction ID, the transaction key and the destination address can be used to prove that a payment was done in case of a dispute. The transaction keys and the descriptions (notes) are stored in the cache of your local wallet, therefore they cannot be recovered from the blockchain.

- (4) Details: Clicking here will show you the following transaction details, when available: Transaction ID, Date, Amount, Address, Payment ID, Integrated address, Transaction key, Description (note), Destinations and Rings.
- (5) Prove payment (P): Clicking here will generate a payment proof, which you can use, in case of a dispute, to prove that you made a payment. More details on proving payments can be found here(6) Set description: Click on this icon to set a new description or edit an existing one.

(7) Advanced options: Lets you choose in which format the date should be displayed.

Advanced Features

Solo mining

Figure 26: mining

The Mining tab provides a one click CPU miner that is embedded into the GUI.

CPU threads: Number of CPU threads to use for mining.

- (2) threads auto-configuration: Set automatically the number of threads either to the recommended number, or to the max number.
- (3) Background mining: Check this box to enable experimental background mining. This should allow you to use your computer normally while mining.

(4) Start mining: Start the miner.

(5) Stop mining: Stop the miner.

(6) Status: Indicates the mining state and hashrate.

Prove - Check

TheProve/checktabprovidestoolsforprovingapaymentorvalidatingproofofapayment. Thisisnecessary with Monero because these details are not available on the blockchain.

Prove Transaction

This will generate a proof that you made a payment to a certain address. You need to put the following information:

(1) Transaction ID: This is the ID of the payment you are creating proof for. You can find the transaction details by selecting the History tab from the left menu.

(2) Address: This is the address you are proving payment to.

(3) Message (optional): This an optional message that will be signed with the transaction details. If you choose to include a message then the other party must also include the exact same message in order to verify your proof.

(4) Generate: Click here once you've entered all the details to generate your proof.

A detailed guide is available on getmonero.org: 'How to prove payment'

Check Transaction

This will verify that a payment was made. You need to put the following information:

Transaction ID: This is the ID of the payment you are attempting to verify.

(2) Address: This is the receiving address of the payment you are attempting to verify.

(3) Message (optional): This is the optional message that may have been included with the proof.

(4) Signature: This is the signature generated to prove payment.

(5) Check: Click here once you've entered all the details to check that the transaction proof is valid. Shared RingDB

This is an advanced tool that can be used to improve the privacy of ring signatures. The outputs used in ringsignaturescanbeadaptedtomitigatetheprivacylosswhenusingakey-reusingforkortoavoidoutputs

Figure 27: Prove payment

Figure 28: Check payment

Figure 29: shared ringdb 1/2

that could not be spent in this transaction.

- (1) Mark as spent filename: This tool will mark outputs that are known to be spent. After running monero-blockchain-mark-spent-outputs, import the resulting file to avoid using these outputs as decoys in constructed ring signatures. This file is stored in the .shared-ringdb folder by default.
- (2) Mark as spent output: This will mark or unmark as spent a chosen single output. Outputs are represented by 64-character strings. The outputs added in this field will not be used as decoys in constructed ring signatures. Unmarked outputs may (but will not necessarily) by used as decoys. Figure 30: shared ringdb 2/2

(3) Key image input: Add the key image that was used on the key-reusing fork.

- (4) Get ring: Press the "Get Ring" button to get the ring members for the given key image in 3. (5) Set ring: Press the "Set Ring" button to set the ring members for a transaction. Copy the ring
- members from 4 to get those for the key image, or manually type in your own.

43

(6) Intent to spend: Select this if you are certain that you will spend Monero on a key-reusing fork. This will aggressively modify the input selection algorithm to give you the greatest plausible deniability.

(7) Possibility to spend: Select this if you may spend Monero on a key-reusing fork. This will modifytheinputselectionalgorithm. Uncheckthisonlyifyouarecertainyouwillnotuseakey-reusingfork.

(8) Relative: When selected, the offsets are encoded relative to the previous, as opposed to absolute (transactions use relative offsets).

(9) Segregation height: The block height at which the key-reusing fork splits.

Sign - verify Message

The Sign/verify tab provides tools for signing a message or file with your private key or verifying the authenticity of a singed message or file.

Sign

(1) Message: This is where you can enter a message to be signed.

(2) Signature: This is where your unique signature will appear once you click the Sign button. This is linked to your private key and the message you entered. It will be given as proof along with the message which was signed.

Verify

(3) Verify message: This is where you will put a message that has been signed.

(4) Address: This is where you will enter the public Monero address of the signer.

(5) Signature: This is where you will enter the signature you are verifying. Once all the required information has been entered click the Verify button. A pop-up will tell you if the signature is valid. Sign - verify File

The Sign/verify tab provides tools for signing a message or file with your private key or verifying the authenticity of a singed message or file.

Sign

(1) File: This is where you can choose a file to be signed. Click Browse to navigate the file system.

(2) Signature: This is where your unique signature will appear once you click the Sign button. This is linked to your private key and the file you entered. It will be given as proof along with the file which was signed.

Verify

(3) File: This is where you enter the path to a file that has been signed. Click Browse to navigate the file system.

(4) Address: This is where you will enter the public Monero address of the signer.

ÀΔ

Figure 31: sign/verify

45

Figure 32: sign/verify

46

(5) Signature: This is where you will enter the signature you are verifying. Once all the required information has been entered click the Verify button. A pop-up will tell you if the signature is valid.

Settings

The Settings tab provides tools for customizing configuration options.

Wallet

Figure 33: settings-wallet

(1) Close this wallet: Click here to safely close the current wallet and open the main menu.

(2) Create a view-only wallet: Click here to generate a view-only (or audit) wallet file, which is capable to see all incoming transactions. In order to display the real balance, you must also import the key images from your normal wallet into your view-only wallet. The view-only wallet will be created with the same password as the current wallet. See this user-guide for more information.

(3) Show seed & keys: This button will redirect you to the Seed and keys tab.

(4) Rescan wallet balance: Click here to rescan all spent outputs from your wallet, updating your wallet balance. If your balance is still incorrect, you probably will have to resync your wallet after changing the wallet restore height to a restore height before the height of the first transaction to your wallet. Todothis,gototheSettings>Infopage,Walletrestoreheight,andclickonthe(Change)link.

(5) Change wallet password: Click here to change the password of your wallet file.

(6) Enter merchant mode: Click here to open Monero GUI's business-friendly mode.

48

Interface

Figure 34: settings_interface

TheInterfacetabiswhereyoucanadjustappearanceandsecuritysettingsoftheGUIwallet. Theoptions are:

- (1) Custom decorations: Switch custom window decorations.
- (2) Check for updates periodically: Enable this option if you want your wallet to periodically check if a new version is available.
- (3) Hide balance: Will display your balance as ?.?? in the balance card. It is a useful privacy feature if you are running your wallet in a public place, as a point of sales system, or if you have to take a screenshot or record your screen to someone.

(4) Light theme: Switch between light and dark themes.

- (5) Ask for password before sending a transaction: Disable this option if you don't want to type your password every time a transaction is sent. This option is enabled by default.
- (6) Autosave: When enabled, your wallet file will be saved automatically, every 10 minutes (default) or at an interval of your choice. This option is enabled by default.
- (7) Lock wallet on inactivity: Set this to automatically lock your wallet after N minutes of inactivity. This ensures no one is able to use your wallet while you are away from keyboard.
- (8) Enable displaying balance in other currencies: Gives you the possibility to also display your balance, the transaction amount and transaction fee inother currencies. You can select the price source and the currency you prefer (currently only USD and EUR are supported). Local Node
- (1) Start/Stop Local Node: Depending on its current state, either start or stop the local node.
- (2) Blockchain location: Manually enter a non-default path to the blockchain, or click change to choose a new path.

49

Figure 35: settings_local-node

50

- (3) Startupflags: Whenusingalocalnode, this will be where you enter additional command line options.
- (4) Bootstrap Address: Enter the hostname or IP address of the bootstrap remote node. See section Bootstrap nodes for a brief explanation of what a bootstrap node is.
- (5) Bootstrap Port: Enter the port of the bootstrap remote node.

Remote Node

Use a remote node, do not download the blockchain. Check the 'About remote nodes' section of this guide Figure 36: settings_remote-node

- (1) Address: Enter the hostname or IP address of the remote node.
- (2) Port: Enter the port of the remote node.
- (3) Daemon Username: Enter a username in case authentication to the remote node is required.
- (4) Daemon Password: Enter a password in case authentication to the remote node is required.
- (5) TrustedDaemon: Bydefault,datarequeststoremotenodesareobfuscated,andthisprocessrequires more resources. If your remote node is under your control (i.e. a dedicated server of your own) you can mark it trusted so that data requests will not be obfuscated anymore (just like a local node). Log

Figure 37: settings-log

- (1) Log level: Change the verbosity of the debug logs.
- (2) Log categories: Add specific categories to the debug logs.
- (3) Daemon log: Real time output of the log.
- (4) Command line: Interact with the daemon.

Info

GUI Version: Version of the GUI wallet installed.

らク

Figure 38: settings-info

53

- (2) Embedded Monero Version: Version of the embedded daemon in use.
- (3) Wallet path: Where the wallet is located on your computer.
- (4) Wallet restore height: Your wallet synchronization starts at the block defined in wallet restore height. Therefore, you must set the restore height before the height of the first incoming transaction of your wallet. If you click on the (Change) link, you can set a blockheight or a date. After changing

- it, your wallet will rescan the blockchain starting from the blockheight you set. Note: when you change your wallet's restore height, you will lose all information that is stored in the wallet software and cannot be recovered from the blockchain, which includes destination addresses, transaction keys, and descriptions (notes).
- (5) Wallet log path: Where the logs for this wallet will be saved.
- (6) Wallet mode: Display the wallet mode chosen in the wizard.

(7) Graphics mode: Display the graphics mode.

(8) Copy to clipboard: Copy all information to clipboard.

Seed and keys

Figure 39: seed-keys

The Seeds & Keys tabdisplaysyourwalletsmnemonic seed aswellas yoursecret view key, public viewkey, secret spend key, and public spend key.

(1) Mnemonic seed: DO NOT share your mnemonic seed with anyone. Store a copy securely. The mnemonic seed is a 25 word phrase that contains all the information needed to view and spend funds. Learn more about mnemonic seeds.

- (2) Wallet restore height. This is the blockheight of the first incoming transaction of your wallet. This information is useful when you restore your wallet, because you will only have to synchronize the blockchain for the period that is needed.
- (3) Primary address: This is the main address of your wallet and starts with 4. All other addresses from your wallet are subaddresses, and start with 8.
- (4) Secret view key: Secret (private) view keys allows the holder to view your wallets incoming transactions, but not outgoing. It is sometimes useful for auditing purposes to give your secret view key to a third party.

Figure 40: seed-keys-2

- (5) Publicviewkey: Thepublicviewkeyisusedforstealthaddresscreation. Learnmoreaboutviewkeys.
- (6) Secret spend key: DO NOT share your secret spend key with anyone. The secret (private) spend key is used to sign transactions and should be regarded with the same security as your mnemonic seed.
- (7) Public spend key: The public spend key is used by the network to verify the signature of the key image you generate when you make a transaction. This is what prevents double-spends asthenetworkenforcestherulethatakeyimagecanbespentonlyonce. Learnmoreaboutspendkeys.
- (8) Export Spendable Wallet: DO NOT share your spendable wallet QR code with anyone. This can be used like a mnemonic seed for recovering your wallet. This creates a qrcode that contains all of your keys.
- (9) Export View Only Wallet: This creates a QR code that contains only the keys for viewing the transactions that this wallet sends or receives, but cannot create transactions.

Binaries Verification

Verifythatthefilesyoudownloadedmatchtheo∎icialones. Youcanusethisstep-by-stepguidewithpictures (easy, for Windows user).

20

About remote nodes

Remote nodes are useful if you are not able/don't want to download the whole blockchain, but be advised that malicious remote nodes could compromise some privacy. They may track your IP address, track your "restoreheight" and associated block request data, and sendyouin accurate information to learn more about transactions you make. Please make sure to use a node you trust (hopefully your own) and remain aware of these limitations. Users who prioritize privacy should use the wallet in advanced mode and start a local node without setting a bootstrap node. A number of public remode nodes are listed at moneroworld.com and node-o-matic

Bootstrap nodes

RemotenodescanalsobeusefulifyouarerunningalocalnodeandwanttouseMonerobeforetheblockchain download has finished. In this situation, the remote node is known as a bootstrap node. Your local node will temporarily connect to it while the blockchain is still being downloaded. When the blockchain is synced locally, your local node will disconnect from the bootstrap node. It is a reasonable trade-off for most people who care about privacy but also want the convenience of an automatic fallback option. Be aware that when using remote nodes (including a local node with a bootstrap node), nodes may track your IP address, your "restoreheight", and associated block request data, as well as sendy ouin accurate information

to learn more about transactions you make. Please make sure to use a remote node you trust (hopefully your own) and remain aware of these limitations. Keep the Monero full node software operating on your computer even when you are not using the wallet to reduce the amount of leaked data. More information a https://getmonero.org/resources/moneropedia/bootstrap-node.html

Common issues and solutions

The following are only some of the most common issues. For a more extensive list visit the FAQ page on getmonero.org.

- How to change Wallet restore height / Wrong or zero balance after synchronizing?
- How do I generate a Ledger Monero wallet with the GUI?
- I am missing (not seeing) a transaction to (in) the GUI (zero balance)
- I am using the GUI and my daemon doesn't start anymore
- Transaction stuck as "pending" in the GUI
- My GUI feels buggy / freezes all the time
- My name contains a special (non-ASCII) character (e.g. é, ø, â, Ö) and I can't create a wallet with the GUI
- The GUI uses all my bandwidth and I can't browse anymore or use another application that requires internet connection
- How do I move the blockchain (data.mdb) to a different directory during (or after) the initial sync without losing the progress?
- How do I change the language of the 25 word mnemonic seed in the GUI or CLI?