# Code Optimization II: Machine-dependent Optimizations


COMP400727: Introduction to Computer Systems

Hao Li Xi'an Jiaotong University


# **Today**

- Machine-Dependent Optimizations
- Instruction-Level Parallelism
- **■** Branch Predictions

### Multiple Levels of Optimizations



### **Modern CPU Design**



# **Today**

- **■** Machine-Dependent Optimizations
- Instruction-Level Parallelism
- **■** Branch Predictions

# **Exploiting Instruction-Level Parallelism**

- Need general understanding of modern processor design
  - Hardware can execute multiple instructions in parallel
- Performance limited by data dependencies
- Simple transformations can cause big speedups
  - Compilers often cannot make these transformations
  - Lack of associativity and distributivity in floating-point arithmetic

# **Benchmark Example: Data Type for Vectors**

```
/* data structure for vectors */
typedef struct{
    size_t len;
    data_t *data;
} vec;
```

```
        len
        0
        1
        len-1

        data
        ......
```

### Data Types

- Use different declarations for data t
- int
- long
- float
- double

```
/* retrieve vector element
   and store at val */
int get_vec_element
   (*vec v, size_t idx, data_t *val)
{
   if (idx >= v->len)
      return 0;
   *val = v->data[idx];
   return 1;
}
```

### **Benchmark Computation**

```
void combine1(vec_ptr v, data_t *dest)
{
    long int i;
    *dest = IDENT;
    for (i = 0; i < vec_length(v); i++) {
        data_t val;
        get_vec_element(v, i, &val);
        *dest = *dest OP val;
    }
}</pre>
```

Compute sum or product of vector elements

#### Data Types


- Use different declarations for data\_t
- int
- long
- float
- double

### Operations

- Use different definitions of
   OP and IDENT
- **+** / 0
- **\*** / 1

# **Cycles Per Element (CPE)**

- Convenient way to express performance of program that operates on vectors or lists
- Length = n
- In our case: CPE = cycles per OP
- Cycles = CPE\*n + Overhead
  - CPE is slope of line



### **Benchmark Performance**

```
void combine1(vec_ptr v, data_t *dest)
{
    long int i;
    *dest = IDENT;
    for (i = 0; i < vec_length(v); i++) {
        data_t val;
        get_vec_element(v, i, &val);
        *dest = *dest OP val;
    }
}</pre>
```

Compute sum or product of vector elements

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Combine1 unoptimized	22.68	20.02	19.98	20.18
Combine1 -O1	10.12	10.12	10.17	11.14
Combine1 –O3	4.5	4.5	6	7.8

Results in CPE (cycles per element)

### **Basic Optimizations**

```
void combine4(vec_ptr v, data_t *dest)
{
  long i;
  long length = vec_length(v);
  data_t *d = get_vec_start(v);
  data_t t = IDENT;
  for (i = 0; i < length; i++)
     t = t OP d[i];
  *dest = t;
}</pre>
```

- Move vec\_length out of loop
- Avoid bounds check on each cycle
- Accumulate in temporary

# **Effect of Basic Optimizations**

```
void combine4(vec_ptr v, data_t *dest)
{
  long i;
  long length = vec_length(v);
  data_t *d = get_vec_start(v);
  data_t t = IDENT;
  for (i = 0; i < length; i++)
     t = t OP d[i];
  *dest = t;
}</pre>
```

Method	Integer		Doub	le FP
Operation	Add Mult		Add	Mult
Combine1 -O1	10.12	10.12	10.17	11.14
Combine4	1.27	3.01	3.01	5.01

Eliminates sources of overhead in loop

# **Loop Unrolling (2x1)**

```
void unroll2a combine(vec ptr v, data_t *dest)
{
    long length = vec length(v);
    long limit = length-1;
    data t *d = get vec start(v);
    data t x = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
       x = (x OP d[i]) OP d[i+1];
    /* Finish any remaining elements */
    for (; i < length; i++) {
       x = x OP d[i];
    *dest = x;
```

Perform 2x more useful work per iteration

# **Effect of Loop Unrolling**

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Combine4	1.27	3.01	3.01	5.01
Unroll 2x1	1.01	3.01	3.01	5.01
Latency Bound	1.00	3.00	3.00	5.00


### Helps integer add

Achieves latency bound

$$x = (x OP d[i]) OP d[i+1];$$

- Others don't improve. Why?
  - Sequential dependency


# **Combine4 = Serial Computation (OP = \*)**




Computation (length=8)

```
(((((((((((1 * d[0]) * d[1]) * d[2]) * d[3])
* d[4]) * d[5]) * d[6]) * d[7])
```

- Sequential dependence
  - Performance: determined by latency of OP



### **Modern CPU Design**




### **Superscalar Processor**

- Definition: A superscalar processor can issue and execute multiple instructions in one cycle. The instructions are retrieved from a sequential instruction stream and are usually scheduled dynamically.
- Benefit: without programming effort, superscalar processor can take advantage of the instruction level parallelism that most programs have
- Most modern CPUs are superscalar.
- Intel: since Pentium (1993)

### **Pipelined Functional Units**

```
long mult_eg(long a, long b, long c) {
   long p1 = a*b;
   long p2 = a*c;
   long p3 = p1 * p2;
   return p3;
}
```



	Time						
	1	2	3	4	5	6	7
Stage 1	a*b	a*c			p1*p2		
Stage 2		a*b	a*c			p1*p2	
Stage 3			a*b	a*c			p1*p2

- Divide computation into stages
- Pass partial computations from stage to stage
- Stage i can start on new computation once values passed to i+1
- E.g., complete 3 multiplications in 7 cycles, even though each requires 3 cycles

### **Haswell CPU**

- 8 Total Functional Units
- Multiple instructions can execute in parallel
  - 2 load, with address computation
  - 1 store, with address computation
  - 4 integer
  - 2 FP multiply
  - 1 FP add
  - 1 FP divide

### Some instructions take > 1 cycle, but can be pipelined

Instruction	Latency	Cycles/Issue
Load / Store	4	1
Integer Multiply	3	1
Integer/Long Divide	3-30	3-30
Single/Double FP Multiply	5	1
Single/Double FP Add	3	1
Single/Double FP Divide	3-15	3-15

# x86-64 Compilation of Combine4

Inner Loop (Case: Integer Multiply)

Method	Integer		Double FP	
Operation	Add Mult		Add	Mult
Combine4	1.27	3.01	3.01	5.01
Latency Bound	1.00	3.00	3.00	5.00

# Loop Unrolling with Reassociation (2x1a)

```
void unroll2aa combine(vec ptr v, data t *dest)
{
    long length = vec length(v);
    long limit = length-1;
    data t *d = get vec start(v);
    data t x = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
       x = x OP (d[i] OP d[i+1]);
    /* Finish any remaining elements */
    for (; i < length; i++) {
       x = x OP d[i];
                                 Compare to before
                                 x = (x OP d[i]) OP d[i+1];
    *dest = x;
```

- Can this change the result of the computation?
- Yes, for FP. Why?

### **Effect of Reassociation**

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Combine4	1.27	3.01	3.01	5.01
Unroll 2x1	1.01	3.01	3.01	5.01
Unroll 2x1a	1.01	1.51	1.51	2.51
Latency Bound	1.00	3.00	3.00	5.00
Throughput Bound	0.50	1.00	1.00	0.50

4 func. units for int +, 2 func. units for load / Why Not .25?

1 func. unit for FP + 3-stage pipelined FP +

Nearly 2x speedup for Int \*, FP +, FP \*

Reason: Breaks sequential dependency


$$x = x OP (d[i] OP d[i+1]);$$

Why is that? (next slide)

2 func. units for FP \*, 2 func. units for load 5-stage pipelined FP \*

### **Reassociated Computation**

$$x = x OP (d[i] OP d[i+1]);$$



### ■ What changed:

 Ops in the next iteration can be started early (no dependency)

#### Overall Performance

- N elements, D cycles latency/op
- (N/2+1)\*D cycles:CPE = D/2

### Loop Unrolling with Separate Accumulators (2x2)

```
void unroll2a combine(vec ptr v, data t *dest)
    long length = vec length(v);
    long limit = length-1;
    data t *d = get vec start(v);
    data t x0 = IDENT;
    data t x1 = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
       x0 = x0 \text{ OP d[i]};
       x1 = x1 \text{ OP } d[i+1];
    /* Finish any remaining elements */
    for (; i < length; i++) {
        x0 = x0 \text{ OP d[i]};
    *dest = x0 OP x1;
```

Different form of reassociation

# **Effect of Separate Accumulators**

Method	Integer		Double FP		
Operation	Add	Mult	Add	Mult	
Combine4	1.27	3.01	3.01	5.01	
Unroll 2x1	1.01	3.01	3.01	5.01	
Unroll 2x1a	1.01	1.51	1.51	2.51	
Unroll 2x2	0.81	1.51	1.51	2.51	
Latency Bound	1.00	3.00	3.00	5.00	
Throughput Bound	0.50	1.00	1.00	0.50	

Int + makes use of two load units


```
x0 = x0 OP d[i];
x1 = x1 OP d[i+1];
```

2x speedup (over unroll2) for Int \*, FP +, FP \*

### **Separate Accumulators**

```
x0 = x0 \text{ OP d[i]};

x1 = x1 \text{ OP d[i+1]};
```



### What changed:

Two independent "streams" of operations

#### Overall Performance

- N elements, D cycles latency/op
- Should be (N/2+1)\*D cycles:
  CPE = D/2
- CPE matches prediction!

What Now?

# **Unrolling & Accumulating**

#### Idea

- Can unroll to any degree L
- Can accumulate K results in parallel
- L must be multiple of K

#### Limitations

- Diminishing returns
  - Cannot go beyond throughput limitations of execution units
- Large overhead for short lengths
  - Finish off iterations sequentially

# **Unrolling & Accumulating: Double \***

#### Case

- Intel Haswell
- Double FP Multiplication
- Latency bound: 5.00. Throughput bound: 0.50

FP *	Unrolling Factor L								
K	1	2	3	4	6	8	10	12	
1	5.01	5.01	5.01	5.01	5.01	5.01	5.01		
2		2.51		2.51		2.51			
3			1.67						
4				1.25		1.26			
6					0.84			0.88	
8						0.63			
10							0.51		
12								0.52	

### **Achievable Performance**

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Best	0.54	1.01	1.01	0.52
Latency Bound	1.00	3.00	3.00	5.00
Throughput Bound	0.50	1.00	1.00	0.50


- Limited only by throughput of functional units
- Up to 42X improvement over original, unoptimized code

Can we do even better?

### **Programming with AVX2**

### **YMM Registers**

- 16 total, each 32 bytes
- 32 single-byte integers



- 16 16-bit integers
- - 8 32-bit integers
- - 8 single-precision floats
- - 4 double-precision floats
- - 1 single-precision float
- - 1 double-precision float

### **SIMD Operations**

■ SIMD Operations: Single Precision

■ SIMD Operations: Double Precision

# **Using Vector Instructions**

Method	Integer		Double FP	
Operation	Add	Mult	Add	Mult
Scalar Best	0.54	1.01	1.01	0.52
Vector Best	0.06	0.24	0.25	0.16
Latency Bound	0.50	3.00	3.00	5.00
Throughput Bound	0.50	1.00	1.00	0.50
Vec Throughput Bound	0.06	0.12	0.25	0.12

#### Make use of AVX Instructions


- Parallel operations on multiple data elements
- See Web Aside OPT:SIMD on CS:APP web page

# **Today**

- Machine-Dependent Optimizations
- Instruction-Level Parallelism
- Branch Predictions

### **Branches Are A Challenge**


Instruction Control Unit must work well ahead of Execution Unit to generate enough operations to keep EU busy



If the CPU has to wait for the result of the cmp before continuing to fetch instructions, may waste tens of cycles doing nothing!

### **Branch Prediction**

- Guess which way branch will go
  - Begin executing instructions at predicted position
  - But don't actually modify register or memory data



# **Branch Prediction Through Loop**

```
Assume
401029:
         mulsd
                  (%rdx), %xmm0, %xmm0
40102d:
          add
                 $0x8,%rdx
                                           array length = 100
401031:
                 %rax,%rdx
          cmp
                              i = 98
401034:
                 401029
          ine
                                           Predict Taken (OK)
401029:
         mulsd
                  (%rdx),%xmm0,%xmm0
40102d:
                 $0x8,%rdx
          add
401031:
                 %rax,%rdx
          cmp
                              i = 99
                 401029
401034:
          jne
                                           Predict Taken
                                           (Oops)
401029:
         mulsd
                  (%rdx),%xmm0,%xmm0
40102d:
                 $0x8,%rdx
         add
                                                           Executed
                                           Read
401031:
                 %rax,%rdx
          cmp
                                           invalid
                              i = 100
401034:
          jne
                 401029
                                           location
401029:
         mulsd
                  (%rdx),%xmm0,%xmm0
                                                            Fetched
40102d:
          add
                 $0x8,%rdx
401031:
                 %rax,%rdx
          cmp
                              i = 101
401034:
                 401029
          jne
```

### **Branch Misprediction Invalidation**

```
Assume
401029:
           mulsd
                    (%rdx),%xmm0,%xmm0
40102d:
           add
                    $0x8,%rdx
                                                  array length = 100
401031:
                    %rax,%rdx
           cmp
                                   i = 98
401034:
                    401029
           ine
                                                  Predict Taken (OK)
401029:
           mulsd
                    (%rdx),%xmm0,%xmm0
40102d:
                    $0x8,%rdx
           add
401031:
                    %rax,%rdx
           cmp
                                   i = 99
                    401029
401034:
           jne
                                                  Predict Taken
                                                  (Oops)
<del>401029:</del>
           mulsd
                    (%rdx), %xmm0, %xmm0
40102d:
                    $0x8, %rdx
           <del>-add-</del>
<del>401031:</del>
           <del>cmp</del>
                    %rax,%rdx
                                   i = 100
401034: ine
                    401029
                                                      Invalidate
           mulsd
                    (%rdx), %xmm0, %xmm0
<del>401029:</del>
40102d:
                    $0x8, %rdx
           add
<del>401031:</del>
                    %rax,%rdx
           <del>cmp</del>
                                   i = 101
401034:
                    401029
           ine
```

### **Branch Misprediction Recovery**

```
401029:
         mulsd
                 (%rdx), %xmm0, %xmm0
40102d:
                 $0x8,%rdx
         add
                                  i = 99
                                             Definitely not taken
401031:
         cmp
                 %rax,%rdx
401034:
         jne
                 401029
401036:
                 401040
         jmp
                                                Reload
401040:
                 %xmm0,(%r12)
         movsd
```

#### Performance Cost

- Multiple clock cycles on modern processor
- Can be a major performance limiter

### **Branch Prediction Numbers**

### A simple heuristic:

- Backwards branches are often loops, so predict taken
- Forwards branches are often ifs, so predict not taken
- >95% prediction accuracy just with this!

### **■** Fancier algorithms track behavior of each branch

- Subject of ongoing research
- 2011 record (<a href="https://www.jilp.org/jwac-2/program/JWAC-2-program.htm">https://www.jilp.org/jwac-2/program/JWAC-2-program/JWAC-2-program.htm</a>): 34.1 mispredictions per 1000 instructions
- Current research focuses on the remaining handful of "impossible to predict" branches (strongly data-dependent, no correlation with history)
  - e.g. <a href="https://hps.ece.utexas.edu/pub/PruettPatt">https://hps.ece.utexas.edu/pub/PruettPatt</a> BranchRunahead.pdf

### Loop Unrolling

```
void unroll2a combine(vec ptr v, data t *dest)
{
    long length = vec length(v);
    long limit = length-1;
    data t *d = get vec start(v);
    data t x = IDENT;
    long i;
    /* Combine 2 elements at a time */
    for (i = 0; i < limit; i+=2) {
       x = (x OP d[i]) OP d[i+1];
    /* Finish any remaining elements */
    for (; i < length; i++) {
       x = x OP d[i];
    *dest = x;
```

#### Transform Branches

```
for (int c=0; c < size; ++c)
{
    if (data[c] >= 128)
       sum += data[c];
}
```

```
.L4:

mov rdx, QWORD PTR [rax]

cmp rdx, 127

jbe .L3

add rcx, rdx

mov edi, 1

.L3:

next loop
```

```
int t = (data[c] - 128) >> 31;
sum += ~t & data[c];
```

```
.L3:
   mov rcx, QWORD PTR [rdx]
        rax, [rcx-128]
   lea
   shr
        rax, 31
   not eax
   cdge
   and rax, rcx
        rsi, rax
   add
   add
        rdx, 8
   cmp
        rdx, rdi
   jne .L3
```

Conditional Moves

```
int absdiff(int x, int y) {
   int result;
   if (x > y) result = x - y;
   else result = y - x;
   return result;
}
```

```
absdiff:
         eax, DWORD PTR [rbp-20]
   mov
         eax, DWORD PTR [rbp-24]
   cmp
   ile .L2
   mov eax, DWORD PTR [rbp-20]
    sub eax, DWORD PTR [rbp-24]
        DWORD PTR [rbp-4], eax
   mov
         .L3
    qmr
.L2:
        eax, DWORD PTR [rbp-24]
   mov
   sub
         eax, DWORD PTR [rbp-20]
         DWORD PTR [rbp-4], eax
   mov
.L3:
         eax, DWORD PTR [rbp-4]
   mov
```

```
absdiff:

mov edx, edi
sub edx, esi
mov eax, esi
sub eax, edi
cmp edi, esi
cmovg eax, edx
```



#### Make Branch More Predictable

```
for (int c=0; c < size; ++c) {
   if (data[c] >= 128)
      sum += data[c];
}
```

T = branch taken
N = branch not taken

### **Going Further**

- Compiler optimizations are an easy gain
  - 20 CPE down to 3-5 CPE
- With careful hand tuning and computer architecture knowledge
  - 4-16 elements per cycle
  - Newest compilers are closing this gap

### **Summary: Getting High Performance**

- Good compiler and flags
- Don't do anything sub-optimal
  - Watch out for hidden algorithmic inefficiencies
  - Write compiler-friendly code
    - Watch out for optimization blockers: procedure calls & memory references
  - Look carefully at innermost loops (where most work is done)

#### Tune code for machine

- Exploit instruction-level parallelism
- Avoid unpredictable branches
- Make code cache friendly