# pwny Documentation

Release 0.7.0

**Author** 

# Contents

1	pwny package	3		
2 pwnypack package				
	2.1 pwnypack.asm-(Dis)assembler	4		
	2.2 pwnypack.codec - Data transformation	6		
	2.3 pwnypack.elf-ELF file parsing			
	2.4 pwnypack.flow-Communication	13		
	2.5 pwnypack.fmtstring-Format strings	18		
	2.6 pwnypack.packing - Data (un)packing	19		
	2.7 pwnypack.rop-ROP gadgets	21		
	2.8 pwnypack.target - Target definition	22		
	2.9 pwnypack.util - Utility functions			
3	Indices and tables	25		
Ρv	vthon Module Index	25		

*pwnypack* is the official CTF toolkit of Certified Edible Dinosaurs. It aims to provide a set of command line utilities and a python library that are useful when playing hacking CTFs.

The core functionality of *pwnypack* is defined in the modules of the pwnypack package. The pwny package imports all that functionality into a single namespace for convenience.

Some of the functionality of the pwnypack package is also exported through a set of commandline utilities. Run pwny help after installing *pwnypack* to get a list of available utilities. You can create convenience symlinks for all the included apps by running pwny symlink. Each app has a help function that is accessible using the -h parameter.

For some example of how to use *pwnypack*, check the write-ups on the official Certified Edible Dinosaurs website.

Package contents:

Contents 1

2 Contents

# pwny package

The pwny package provides a convence metapackage that imports the entire public API of *pwnypack* into a single namespace:

```
>>> from pwny import *
>>> enhex(asm('mov rax, 0xced', target=Target(arch=Architecture.x86_64)))
u'b8ed0c0000'
```

For details about what exactly is made available, please consult the documentation of the individual pwnypack modules.

# pwnypack package

All the functionality of *pwnypack* is implemented in the modules of this package.

# 2.1 pwnypack.asm - (Dis)assembler

This module contains functions to assemble and disassemble code for a given target platform.

Currently, the only supported architecture is x86 (both 32 and 64 bits variants). Assembly is performed by the *nasm* assembler (only supports nasm syntax). Disassembly is performed by *ndisasm* (nasm syntax) or *capstone* (intel & att syntax).

class pwnypack.asm.AsmSyntax

Bases: enum. IntEnum

This enumeration is used to specify the assembler syntax.

pwnypack.asm.asm(code, addr=0, syntax=AsmSyntax.nasm, target=None)

Assemble statements into machine readable code.

#### **Parameters**

- **code** (*str*) The statements to assemble.
- **addr** (*int*) The memory address where the code will run.
- **syntax** (AsmSyntax) The input assembler syntax.
- target (Target) The target architecture. The global target is used if this argument is None.

Returns The assembled machine code.

# Return type bytes

# Raises

- $\bullet$  SyntaxError If the assembler statements are invalid.
- NotImplementedError In an unsupported target platform is specified.

#### **Example**

```
>>> from pwny import *
>>> asm('''
... pop rdi
... ret
... ''', target=Target(arch=Target.Arch.x86, bits=64))
b'_\xc3'
```

pwnypack.asm.disasm(code, addr=0, syntax=AsmSyntax.nasm, target=None)

Disassemble machine readable code into human readable statements.

#### **Parameters**

- **code** (*bytes*) The machine code that is to be disassembled.
- addr (int) The memory address of the code (used for relative references).
- **syntax** (AsmSyntax) The output assembler syntax.
- target (Target) The architecture for which the code was written. The global target is used if this argument is None.

**Returns** The disassembled machine code.

**Return type** list of str

#### Raises

- NotImplementedError In an unsupported target platform is specified.
- RuntimeError If ndisasm encounters an error.

#### **Example**

```
>>> from pwny import *
>>> disasm(b'_\xc3', target=Target(arch=Target.Arch.x86, bits=64))
['pop rdi', 'ret']
```

# 2.2 pwnypack.codec - Data transformation

This module contains functions that allow you to manipulate, encode or decode strings and byte sequences.

```
pwnypack.codec.xor(key, data)
```

Perform cyclical exclusive or operations on data.

The key can be a an integer ( $0 \le key \le 256$ ) or a byte sequence. If the key is smaller than the provided data, the key will be repeated.

### **Parameters**

- **key** (*int or bytes*) The key to xor data with.
- data (*bytes*) The data to perform the xor operation on.

**Returns** The result of the exclusive or operation.

Return type bytes

# **Examples**

```
>>> from pwny import *
>>> xor(5, b'ABCD')
b'DGFA'
>>> xor(5, b'DGFA')
b'ABCD'
>>> xor(b'pwny', b'ABCDEFGHIJKLMNOPQRSTUVWXYZ')
b'15-=51)19=%5=9!)!%=-%!9!)-'
>>> xor(b'pwny', b'15-=51)19=%5=9!)!%=-%!9!)-')
b'ABCDEFGHIJKLMNOPQRSTUVWXYZ'
```

```
pwnypack.codec.rot13(d)
```

Rotate all characters in the alphabets A-Z and a-z by 13 positions in the alphabet. This is a caesar() shift of 13 along the fixed alphabets A-Z and a-z.

**Parameters** d(str) – The string to the apply the cipher to.

**Returns** The string with the rot13 cipher applied.

Return type str

# **Examples**

```
>>> rot13('whax')
'junk'
>>> rot13('junk')
'whax'
```

```
pwnypack.codec.caesar(shift, data, shift_ranges=('az', 'AZ'))
```

Apply a caesar cipher to a string.

The caesar cipher is a substition cipher where each letter in the given alphabet is replaced by a letter some fixed number down the alphabet.

If shift is 1, A will become B, B will become C, etc...

You can define the alphabets that will be shift by specifying one or more shift ranges. The characters will than be shifted within the given ranges.

# **Parameters**

- **shift** (*int*) The shift to apply.
- data (str) The string to apply the cipher to.
- **shift\_ranges** (*list of str*) Which alphabets to shift.

**Returns** The string with the caesar cipher applied.

Return type str

# **Examples**

```
>>> caesar(16, 'Pwnypack')
'Fmdofqsa'
>>> caesar(-16, 'Fmdofqsa')
'Pwnypack'
>>> caesar(16, 'PWNYpack', shift_ranges=('AZ',))
```

```
'FMDOpack'
>>> caesar(16, 'PWNYpack', shift_ranges=('Az',))
'`g^iFqsA'
```

```
pwnypack.codec.enhex (d, separator='')
```

Convert bytes to their hexadecimal representation, optionally joined by a given separator.

#### **Parameters**

- **d** (*bytes*) The data to convert to hexadecimal representation.
- **separator** (*str*) The separator to insert between hexadecimal tuples.

Returns The hexadecimal representation of d.

Return type str

# **Examples**

```
>>> from pwny import *
>>> enhex(b'pwnypack')
'70776e797061636b'
>>> enhex(b'pwnypack', separator=' ')
'70 77 6e 79 70 61 63 6b'
```

```
pwnypack.codec.dehex (d)
```

Convert a hexadecimal representation of a byte sequence to bytes. All non-hexadecimal characters will be removed from the input.

**Parameters** d(str) – The string of hexadecimal tuples.

**Returns** The byte sequence represented by d.

Return type bytes

# **Examples**

```
>>> from pwny import *
>>> dehex('70776e797061636b')
b'pwnypack'
>>> dhex('70 77 6e 79 70 61 63 6b')
b'pwnypack'
```

```
pwnypack.codec.enb64(d)
```

Convert bytes to their base64 representation.

**Parameters** d (*bytes*) – The data to convert to its base64 representation.

**Returns** The base64 representation of d.

Return type str

#### **Example**

```
>>> from pwny import *
>>> enb64(b'pwnypack')
'cHdueXBhY2s='
```

```
pwnypack.codec.deb64(d)
```

Convert a base64 representation back to its original bytes.

**Parameters** d (*str*) – The base64 representation to decode.

Returns The bytes represented by d.

Return type bytes

# **Example**

```
>>> from pwny import *
>>> deb64('cHdueXBhY2s=')
b'pwnypack'
```

```
pwnypack.codec.frequency(v)
```

Perform a frequency analysis on a byte sequence or string.

**Parameters** d (*bytes or str*) – The sequence to analyse.

Returns A dictionary of unique elements in d and how often the occur.

Return type dict

# **Example**

```
>>> frequency('pwnypack')
{'a': 1, 'c': 1, 'k': 1, 'n': 1, 'p': 2, 'w': 1, 'y': 1}
```

# 2.3 pwnypack.elf - ELF file parsing

This module contains a parser for, and methods to extract information from ELF files.

```
class pwnypack.elf.ELF (f=None)
    Bases: pwnypack.target.Target
```

A parser for ELF files. Upon parsing the ELF headers, it will not only fill the ELF specific fields but will also populate the inherited arch, bits and endian properties based on the values it encounters.

**Parameters** f (str, file or None) – The (path to) the ELF file to parse.

# **Example**

```
>>> from pwny import *
>>> e = ELF('my-executable')
>>> print(e.machine)
>>> print(e.program_headers)
>>> print(e.section_headers)
>>> print(e.symbols)
```

### class Machine

Bases: enum.IntEnum

The target machine architecture.

```
class ELF.OSABI
    Bases: enum. IntEnum
    Describes the OS- or ABI-specific ELF extensions used by this file.
class ELF. ProgramHeader (elf, data)
    Bases: object
    Describes how the loader will load a part of a file. Called by the ELF class.
        Parameters
            • elf (ELF) – The ELF instance owning this program header.
            • data – The content of the program header entry.
    class Flags
        Bases: enum. IntEnum
        The individual flags that make up ELF.ProgramHeader.flags.
    class ELF. ProgramHeader. Type
        Bases: enum. IntEnum
        The segment type.
    ELF.ProgramHeader.align = None
    ELF.ProgramHeader.filesz = None
    ELF.ProgramHeader.flags = None
    ELF.ProgramHeader.memsz = None
    ELF.ProgramHeader.offset = None
    ELF.ProgramHeader.paddr = None
    ELF.ProgramHeader.type = None
    ELF.ProgramHeader.type_id = None
    ELF.ProgramHeader.vaddr = None
class ELF.SectionHeader (elf, data)
    Bases: object
    Describes a section of an ELF file. Called by the ELF class.
        Parameters
            • elf (ELF) – The ELF instance owning this section header.
            • data – The content of the section header entry.
    class Flags
        Bases: enum. IntEnum
    class ELF. SectionHeader. Type
        Bases: enum. IntEnum
        Describes the section's type
    ELF.SectionHeader.addr = None
    ELF.SectionHeader.addralign = None
    ELF.SectionHeader.content
```

The contents of this section.

```
ELF.SectionHeader.elf = None
    ELF.SectionHeader.entsize = None
    ELF.SectionHeader.flags = None
    ELF.SectionHeader.info = None
    ELF.SectionHeader.link = None
    ELF.SectionHeader.name = None
    ELF.SectionHeader.name_index = None
    ELF.SectionHeader.offset = None
    ELF.SectionHeader.size = None
    ELF.SectionHeader.type = None
    ELF.SectionHeader.type_id = None
class ELF . Symbol (elf, data, strs)
    Bases: object
    Contains information about symbols. Called by the ELF class.
        Parameters
            • elf (ELF) – The ELF instance owning this symbol.
            • data – The content of the symbol definition.
            • strs – The content of the string section associated with the symbol table.
    class Binding
        Bases: enum.IntEnum
        Describes a symbol's binding.
    class ELF. Symbol. Special Section
        Bases: enum.IntEnum
        Special section types.
    class ELF. Symbol. Type
        Bases: enum. IntEnum
        Describes the symbol's type.
    class ELF. Symbol. Visibility
        Bases: enum. IntEnum
        Describes the symbol's visibility.
    ELF.Symbol.content
        The contents of a symbol.
           Raises TypeError – If the symbol isn't defined until runtime.
    ELF.Symbol.elf = None
    ELF.Symbol.info = None
    ELF.Symbol.name = None
    ELF.Symbol.name_index = None
    ELF.Symbol.other = None
```

```
ELF.Symbol.shndx = None
    ELF.Symbol.size = None
    ELF.Symbol.type = None
    ELF.Symbol.type_id = None
    ELF.Symbol.value = None
    ELF.Symbol.visibility = None
class ELF. Type
    Bases: enum.IntEnum
    Describes the object type.
ELF.abi_version = None
ELF . entry = None
ELF.f = None
ELF.flags = None
ELF.get_program_header(index)
    Return a specific program header by its index.
        Parameters index (int) – The program header index.
        Returns ~ ELF.ProgramHeader: The program header.
        Return type :class
        Raises KeyError - The specified index does not exist.
ELF.get_section_header(section)
    Get a specific section header by index or name.
        Parameters section (int or str) – The index or name of the section header to return.
        Returns ~ ELF. Section Header: The section header.
        Return type :class
        Raises KeyError – The requested section header does not exist.
ELF.get symbol(symbol)
    Get a specific symbol by index or name.
        Parameters symbol (int or str) – The index or name of the symbol to return.
        Returns The symbol.
        Return type ELF.Symbol
        Raises KeyError - The requested symbol does not exist.
ELF.hsize = None
ELF.machine = None
ELF.osabi = None
ELF.parse_file(f)
    Parse an ELF file and fill the class' properties.
        Parameters f (file or str) – The (path to) the ELF file to read.
ELF.phentsize = None
```

```
ELF.phnum = None
ELF.phoff = None
ELF.program_headers
    A list of all program headers.
ELF.section_headers
    Return the list of section headers.
ELF.shentsize = None
ELF.shnum = None
ELF.shoff = None
ELF.shstrndx = None
ELF.symbols
    Return a list of all symbols.
ELF.type = None
```

# 2.4 pwnypack.flow - Communication

The Flow module lets you connect to processes or network services using a unified API. It is primarily designed for synchronous communication flows.

It is based around the central Flow class which uses a Channel to connect to a process. The Flow class then uses the primitives exposed by the Channel to provide a high level API for reading/receiving and writing/sending data.

# **Examples**

```
>>> from pwny import *
>>> f = Flow.connect_tcp('ced.pwned.systems', 80)
>>> f.writelines([
... b'GET / HTTP/1.0',
... b'Host: ced.pwned.systems',
... b'',
... ])
>>> line = f.readline().strip()
>>> print(line == b'HTTP/1.0 200 OK')
True
>>> f.until(b'\r\n\r\n')
>>> f.read_eof(echo=True)
... lots of html ...
```

```
>>> from pwny import *
>>> f = Flow.execute('cat')
>>> f.writeline(b'hello')
>>> f.readline(echo=True)
```

class pwnypack.flow.ProcessChannel (executable, argument..., redirect\_stderr=False)
 Bases: object

This channel type allows controlling processes. It uses python's subprocess. Popen class to execute a process and allows you to communicate with it.

#### **Parameters**

```
• executable (str) – The executable to start.
                 • argument . . . (list of str) – The arguments to pass to the executable.
                 • redirect_stderr (bool) - Whether to also capture the output of stderr.
     close()
           Wait for the subprocess to exit.
     fileno()
           Return the file descriptor number for the stdout channel of this process.
     kill()
           Terminate the subprocess.
     read(n)
           Read n bytes from the subprocess' output channel.
               Parameters n (int) – The number of bytes to read.
               Returns n bytes of output.
               Return type bytes
               Raises EOFError – If the process exited.
     write(data)
           Write n bytes to the subprocess' input channel.
               Parameters data (bytes) – The data to write.
               Raises EOFError – If the process exited.
class pwnypack.flow.SocketChannel(sock)
     Bases: object
     This channel type allows controlling sockets.
           Parameters socket (socket.socket) – The (already connected) socket to control.
     close()
           Close the socket gracefully.
           Return the file descriptor number for the socket.
     kill()
           Shut down the socket immediately.
     read(n)
           Receive n bytes from the socket.
               Parameters n (int) – The number of bytes to read.
               Returns n bytes read from the socket.
               Return type bytes
               Raises EOFError – If the socket was closed.
     write (data)
           Send n bytes to socket.
               Parameters data (bytes) – The data to send.
               Raises EOFError – If the socket was closed.
```

# class pwnypack.flow.TCPClientSocketChannel(host, port)

Bases: pwnypack.flow.SocketChannel

Convenience subclass of SocketChannel that allows you to connect to a TCP hostname / port pair easily.

#### **Parameters**

- host (*str*) The hostname or IP address to connect to.
- **port** (*int*) The port number to connect to.

# class pwnypack.flow.Flow(channel, echo=False)

Bases: object

The core class of Flow. Takes a channel and exposes synchronous utility functions for communications.

Usually, you'll use the convenience classmethods <code>connect\_tcp()</code> or <code>execute()</code> instead of manually creating the constructor directly.

#### **Parameters**

- channel (Channel) A channel.
- echo (bool) Whether or not to echo all input / output.

#### close()

Gracefully close the channel.

# static connect\_ssh (\*args, \*\*kwargs)

Create a new connected SSHClient instance. All arguments are passed to SSHClient.connect().

### classmethod connect\_tcp (host, port, echo=False)

Set up a TCPClientSocketChannel and create a Flow instance for it.

# **Parameters**

- **host** (*str*) The hostname or IP address to connect to.
- **port** (*int*) The port number to connect to.
- echo (bool) Whether to echo read/written data to stdout by default.

**Returns** Flow: A Flow instance initialised with the TCP socket channel.

Return type :class

# classmethod execute (executable, \*arguments, \*\*kwargs)

execute(executable, argument..., redirect\_stderr=False, echo=False):

Set up a ProcessChannel and create a Flow instance for it.

### **Parameters**

- **executable** (*str*) The executable to start.
- **argument** . . . (*list of str*) The arguments to pass to the executable.
- redirect\_stderr (bool) Whether to also capture the output of stderr.
- echo (bool) Whether to echo read/written data to stdout by default.

**Returns** *Flow*: A Flow instance initialised with the process channel.

Return type :class

# classmethod execute\_ssh (command, arguments..., pty=False, echo=False)

Execute command on a remote server. It first calls  $Flow.connect\_ssh()$  using all positional and keyword arguments, then calls SSHClient.execute() with the command and pty / echo options.

#### **Parameters**

- **command** (*str*) The command to execute on the remote server.
- arguments... The options for the SSH connection.
- **pty** (*bool*) Request a pseudo-terminal from the server.
- echo (bool) Whether to echo read/written data to stdout by default.

**Returns** Flow: A Flow instance initialised with the SSH channel.

Return type :class

#### interact()

Interact with the socket. This will send all keyboard input to the socket and input from the socket to the console until an EOF occurs.

# classmethod invoke\_ssh\_shell(\*args, \*\*kwargs)

invoke\_ssh(arguments..., pty=False, echo=False)

Star a new shell on a remote server. It first calls Flow.connect\_ssh() using all positional and keyword arguments, then calls SSHClient.invoke\_shell() with the pty/echo options.

#### **Parameters**

- arguments... The options for the SSH connection.
- **pty** (*bool*) Request a pseudo-terminal from the server.
- echo (bool) Whether to echo read/written data to stdout by default.

**Returns** Flow: A Flow instance initialised with the SSH channel.

Return type :class

# **kill**()

Terminate the channel immediately.

# classmethod listen\_tcp (host='', port=0, echo=False)

Set up a TCPServerSocketChannel and create a Flow instance for it.

### **Parameters**

- **host** (*str*) The hostname or IP address to bind to.
- **port** (*int*) The port number to listen on.
- echo (bool) Whether to echo read/written data to stdout by default.

**Returns** Flow: A Flow instance initialised with the TCP socket channel.

**Return type** :class

# read(n, echo=None)

Read *n* bytes from the channel.

#### **Parameters**

- **n** (*int*) The number of bytes to read from the channel.
- echo (bool) Whether to write the read data to stdout.

**Returns** *n* bytes of data.

# Return type bytes

**Raises** EOFError – If the channel was closed.

### read eof(echo=None)

Read until the channel is closed.

**Parameters** echo (*bool*) – Whether to write the read data to stdout.

Returns The read data.

**Return type** bytes

# read\_until (s, echo=None)

Read until a certain string is encountered..

#### **Parameters**

- **s** (*bytes*) The string to wait for.
- echo (bool) Whether to write the read data to stdout.

**Returns** The data up to and including s.

Return type bytes

**Raises** EOFError – If the channel was closed.

### readline(echo=None)

Read 1 line from channel.

Parameters echo (bool) – Whether to write the read data to stdout.

**Returns** The read line which includes new line character.

Return type bytes

Raises EOFError – If the channel was closed before a line was read.

# readlines (n, echo=None)

Read n lines from channel.

#### **Parameters**

- **n** (*int*) The number of lines to read.
- echo (bool) Whether to write the read data to stdout.

**Returns** *n* lines which include new line characters.

Return type list of bytes

**Raises** EOFError – If the channel was closed before *n* lines were read.

# until (s, echo=None)

Read until a certain string is encountered..

### **Parameters**

- **s** (*bytes*) The string to wait for.
- echo (bool) Whether to write the read data to stdout.

**Returns** The data up to and including s.

Return type bytes

**Raises** EOFError – If the channel was closed.

# write(data, echo=None)

Write data to channel.

#### **Parameters**

- data (*bytes*) The data to write to the channel.
- echo (bool) Whether to echo the written data to stdout.

Raises EOFError – If the channel was closed before all data was sent.

writeline (line=b'', sep=b'\n', echo=None)

Write a byte sequences to the channel and terminate it with carriage return and line feed.

#### **Parameters**

- line (bytes) The line to send.
- **sep** (*bytes*) The separator to use after each line.
- echo (bool) Whether to echo the written data to stdout.

**Raises** EOFError – If the channel was closed before all data was sent.

writelines (lines, sep=b'\n', echo=None)

Write a list of byte sequences to the channel and terminate them with a separator (line feed).

#### **Parameters**

- **lines** (*list of bytes*) The lines to send.
- **sep** (*bytes*) The separator to use after each line.
- echo (bool) Whether to echo the written data to stdout.

**Raises** EOFError – If the channel was closed before all data was sent.

# 2.5 pwnypack.fmtstring - Format strings

The fmtstring module allows you to build format strings that can be used to exploit format string bugs (printf(buf);).

pwnypack.fmtstring.fmtstring(offset, writes, written=0, max\_width=2, target=None)

Build a format string that writes given data to given locations. Can be used easily create format strings to exploit format string bugs.

writes is a list of 2- or 3-item tuples. Each tuple represents a memory write starting with an absolute address, then the data to write as an integer and finally the width (1, 2, 4 or 8) of the write.

*fmtstring()* will break up the writes and try to optimise the order to minimise the amount of dummy output generated.

### **Parameters**

- **offset** (*int*) The parameter offset where the format string start.
- writes (*list*) A list of 2 or 3 item tuples.
- written (int) How many bytes have already been written before the built format string starts.
- max\_width (int) The maximum width of the writes (1, 2 or 4).
- target (pwnypack.target.Target) The target architecture.

**Returns** The format string that will execute the specified memory writes.

Return type bytes

### **Example**

The following example will (on a 32bit architecture) build a format string that write 0xc0debabe to the address 0xdeadbeef and the byte 0x90 to 0xdeadbeef + 4 assuming that the input buffer is located at offset 3 on the stack.

```
>>> from pwny import *
>>> fmtstring(3, [(0xdeadbeef, 0xc0debabe), (0xdeadbeef + 4, 0x90, 1)])
```

# 2.6 pwnypack.packing - Data (un)packing

```
pwnypack.packing.pack (fmt, v1, v2, ..., endian=None, target=None)
```

Return a string containing the values v1, v2, ... packed according to the given format. The actual packing is performed by struct.pack but the byte order will be set according to the given *endian*, *target* or byte order of the global target.

#### **Parameters**

- **fmt** (*str*) The format string.
- **v1**, **v2**, . . . The values to pack.
- **endian** (*Endian*) Override the default byte order. If None, it will look at the byte order of the target argument.
- target (*Target*) Override the default byte order. If None, it will look at the byte order of the global target.

**Returns** The provided values packed according to the format.

# Return type bytes

```
pwnypack.packing.unpack (fmt, data, endian=None, target=None)
```

Unpack the string (presumably packed by pack(fmt, ...)) according to the given format. The actual unpacking is performed by struct.unpack but the byte order will be set according to the given *endian*, *target* or byte order of the global target.

#### **Parameters**

- **fmt** (*str*) The format string.
- data (*bytes*) The data to unpack.
- **endian** (*Endian*) Override the default byte order. If None, it will look at the byte order of the target argument.
- target (Target) Override the default byte order. If None, it will look at the byte order of the global target.

**Returns** The unpacked values according to the format.

### Return type list

```
pwnypack.packing.pack_size (fmt, endian=None, target=None)
pwnypack.packing.P (value, bits=None, endian=None, target=None)
Pack an unsigned pointer for a given target.
```

#### **Parameters**

• **value** (*int*) – The value to pack.

- bits (Bits) Override the default word size. If None it will look at the word size of target.
- endian (Endian) Override the default byte order. If None, it will look at the byte order of the target argument.
- target (Target) Override the default byte order. If None, it will look at the byte order of the global target.

pwnypack.packing.**p**(*value*, *bits=None*, *endian=None*, *target=None*)

Pack a signed pointer for a given target.

#### **Parameters**

- **value** (*int*) The value to pack.
- **bits** (*pwnypack.target.Target.Bits*) Override the default word size. If None it will look at the word size of target.
- endian (Endian) Override the default byte order. If None, it will look at the byte order of the target argument.
- target (Target) Override the default byte order. If None, it will look at the byte order of the global target.

pwnypack.packing.**U** (*data*, *bits=None*, *endian=None*, *target=None*)
Unpack an unsigned pointer for a given target.

#### **Parameters**

- data (*bytes*) The data to unpack.
- **bits** (pwnypack.target.Target.Bits) Override the default word size. If None it will look at the word size of target.
- **endian** (*Endian*) Override the default byte order. If None, it will look at the byte order of the target argument.
- target (*Target*) Override the default byte order. If None, it will look at the byte order of the global target.

**Returns** The pointer value.

# Return type int

pwnypack.packing.u (*data*, *bits=None*, *endian=None*, *target=None*)
Unpack a signed pointer for a given target.

#### **Parameters**

- data (*bytes*) The data to unpack.
- **bits** (pwnypack.target.Target.Bits) Override the default word size. If None it will look at the word size of target.
- endian (Endian) Override the default byte order. If None, it will look at the byte order of the target argument.
- target (*Target*) Override the default byte order. If None, it will look at the byte order of the global target.

Returns The pointer value.

Return type int

```
pwnypack.packing.p8 (value, endian=None, target=None)
     Pack signed 8 bit integer. Alias for pack ('b', ...).
pwnypack.packing.P8 (value, endian=None, target=None)
     Pack unsigned 8 bit integer. Alias for pack ('B', ...).
pwnypack.packing.u8 (data, endian=None, target=None)
     Unpack signed 8 bit integer. Alias for unpack ('b', ...).
pwnypack.packing.U8 (data, endian=None, target=None)
     Unpack unsigned 8 bit integer. Alias for unpack ('B', ...).
pwnypack.packing.p16 (value, endian=None, target=None)
     Pack signed 16 bit integer. Alias for pack ('h', ...).
pwnypack.packing.P16 (value, endian=None, target=None)
     Pack unsigned 16 bit integer. Alias for pack ('H', ...).
pwnypack.packing.u16 (data, endian=None, target=None)
     Unpack signed 16 bit integer. Alias for unpack ('h', ...).
pwnypack.packing.U16 (data, endian=None, target=None)
     Unpack unsigned 16 bit integer. Alias for unpack ('H', ...).
pwnypack.packing.p32 (value, endian=None, target=None)
     Pack signed 32 bit integer. Alias for pack ('l', ...).
pwnypack.packing.P32 (value, endian=None, target=None)
     Pack unsigned 32 bit integer. Alias for pack ('L', ...).
pwnypack.packing.u32 (data, endian=None, target=None)
     Unpack signed 32 bit integer. Alias for unpack ('1', ...).
pwnypack.packing.U32 (data, endian=None, target=None)
     Unpack unsigned 32 bit integer. Alias for unpack ('L', ...).
pwnypack.packing.p64 (value, endian=None, target=None)
     Pack signed 64 bit integer. Alias for pack ('q', ...).
pwnypack.packing.P64 (value, endian=None, target=None)
     Pack unsigned 64 bit integer. Alias for pack ('Q', ...).
pwnypack.packing.u64 (data, endian=None, target=None)
     Unpack signed 64 bit integer. Alias for unpack ('g', ...).
pwnypack.packing.U64 (data, endian=None, target=None)
     Unpack unsigned 64 bit integer. Alias for unpack ('Q', ...).
```

# 2.7 pwnypack.rop - ROP gadgets

The ROP module contains a function to find gadgets in ELF binaries that can be used to create ROP chains.

```
pwnypack.rop.find_gadget (elf, gadget, align=1, unique=True)
```

Find a ROP gadget in a the executable sections of an ELF executable or library. The ROP gadget can be either a set of bytes for an exact match or a (bytes) regular expression. Once it finds gadgets, it uses the capstone engine to verify if the gadget consists of valid instructions and doesn't contain any call or jump instructions.

#### **Parameters**

- **elf** (*ELF*) The ELF instance to find a gadget in.
- gadget (bytes or regexp) The gadget to find.

- align (int) Make sure the gadget starts at a multiple of this number
- unique (bool) If true, only unique gadgets are returned.

### Returns

A dictionary containing a description of the found gadget. Contains the following fields:

- section: The section the gadget was found in.
- offset: The offset inside the segment the gadget was found at.
- addr: The virtual memory address the gadget will be located at.
- gadget: The machine code of the found gadget.
- asm: A list of disassembled instructions.

Return type dict

# 2.8 pwnypack.target - Target definition

The *Target* class describes the architecture of a targeted machine, executable or environment. It encodes the generic architecture, the word size, the byte order and an architecture dependant mode.

It is used throughout *pwnypack* to determine how data should be interpreted or emitted.

```
class pwnypack.target .Target (arch=None, bits=None, endian=None, mode=0)
    Bases: object
```

# class Arch

Bases: enum. Enum

Describes the general architecture of a target.

# class Target.Bits

Bases: enum. IntEnum

The target architecture's word size.

# class Target. Endian

Bases: enum.IntEnum

The target architecture's byte order.

#### class Target. Mode

Bases: enum.IntEnum

Architecture dependant mode flags.

# Target.arch

The target's architecture. One of Target.Arch.

#### Target.assume(other)

Assume the identity of another target. This can be useful to make the global target assume the identity of an ELF executable.

**Parameters** other (*Target*) – The target whose identity to assume.

### **Example**

```
>>> from pwny import *
>>> target.assume(ELF('my-executable'))
```

#### Target.bits

The target architecture word size. One of Target.Bits.

#### Target.endian

The target architecture byte order. One of Target. Endian.

### Target.mode

The target architecture dependant flags. OR'ed values of Target. Mode.

# 2.9 pwnypack.util - Utility functions

The util module contains various utility functions.

```
pwnypack.util.cycle(length, width=4)
```

Generate a de Bruijn sequence of a given length (and width). A de Bruijn sequence is a set of varying repetitions where each sequence of *n* characters is unique within the sequence. This type of sequence can be used to easily find the offset to the return pointer when exploiting a buffer overflow.

#### **Parameters**

- **length** (*int*) The length of the sequence to generate.
- width (int) The width of each element in the sequence.

**Returns** The sequence.

Return type str

#### **Example**

```
>>> from pwny import *
>>> cycle(80)
AAAABAAACAAADAAAEAAAFAAAGAAAHAAAIAAAJAAAKAAALAAAMAAANAAAOAAAPAAAQAAARAAASAAATAAA
```

```
pwnypack.util.cycle_find(key, width=4)
```

Given an element of a de Bruijn sequence, find its index in that sequence.

### **Parameters**

- **key** (*str*) The piece of the de Bruijn sequence to find.
- width (int) The width of each element in the sequence.

**Returns** The index of key in the de Bruijn sequence.

# Return type int

```
pwnypack.util.reghex(pattern)
```

Compile a regular hexpression (a short form regular expression subset specifically designed for searching for binary strings).

A regular hexpression consists of hex tuples interspaced with control characters. The available control characters are:

- •?: Any byte (optional).
- .: Any byte (required).
- •?  $\{n\}$ : A set of 0 up to n bytes.
- •.  $\{n\}$ : A set of exactly n bytes.
- •\*: Any number of bytes (or no bytes at all).
- •+: Any number of bytes (at least one byte).

**Parameters** pattern (*str*) – The reghex pattern.

**Returns** A regular expression as returned by re.compile().

Return type regexp

```
pwnypack.util.pickle_call (func, *args)
```

Create a byte sequence which when unpickled calls a callable with given arguments.

#### **Parameters**

- **func** (*callable*) The function to call or class to instantiate.
- **args** (*tuple*) The arguments to call the callable with.

Returns The data that when unpickled calls func (\*args).

Return type bytes

# **Example**

```
>>> from pwny import *
>>> import pickle
>>> def hello(arg):
... print('Hello, %s!' % arg)
...
>>> pickle.loads(pickle_call(hello, 'world'))
Hello, world!
```

# CHAPTER 3

# Indices and tables

- genindex
- modindex

# p

pwnypack.asm, 5 pwnypack.codec, 6 pwnypack.elf, 9 pwnypack.flow, 13 pwnypack.fmtstring, 18 pwnypack.packing, 19 pwnypack.rop, 21 pwnypack.target, 22 pwnypack.util, 23

28 Python Module Index

A	ELF.SectionHeader (class in pwnypack.elf), 10	
abi_version (pwnypack.elf.ELF attribute), 12 addr (pwnypack.elf.ELF.SectionHeader attribute), 10 addralign (pwnypack.elf.ELF.SectionHeader attribute), 10 align (pwnypack.elf.ELF.ProgramHeader attribute), 10 arch (pwnypack.target.Target attribute), 22 asm() (in module pwnypack.asm), 5 AsmSyntax (class in pwnypack.asm), 5	ELF.SectionHeader.Flags (class in pwnypack.elf), 10 ELF.SectionHeader.Type (class in pwnypack.elf), 10 ELF.Symbol (class in pwnypack.elf), 11 ELF.Symbol.Binding (class in pwnypack.elf), 11 ELF.Symbol.SpecialSection (class in pwnypack.elf), 11 ELF.Symbol.Type (class in pwnypack.elf), 11 ELF.Symbol.Visibility (class in pwnypack.elf), 11 ELF.Type (class in pwnypack.elf), 12	
assume() (pwnypack.target.Target method), 22	enb64() (in module pwnypack.codec), 8 endian (pwnypack.target.Target attribute), 23	
B bits (pwnypack.target.Target attribute), 23	enhex() (in module pwnypack.codec), 8 entry (pwnypack.elf.ELF attribute), 12 entsize (pwnypack.elf.ELF.SectionHeader attribute), 11 execute() (pwnypack.flow.Flow class method), 15 execute_ssh() (pwnypack.flow.Flow class method), 15	
С		
caesar() (in module pwnypack.codec), 7 close() (pwnypack.flow.Flow method), 15 close() (pwnypack.flow.ProcessChannel method), 14 close() (pwnypack.flow.SocketChannel method), 14 connect_ssh() (pwnypack.flow.Flow static method), 15 connect_tcp() (pwnypack.flow.Flow class method), 15 content (pwnypack.elf.ELF.SectionHeader attribute), 10 content (pwnypack.elf.ELF.Symbol attribute), 11 cycle() (in module pwnypack.util), 23 cycle_find() (in module pwnypack.util), 23  D deb64() (in module pwnypack.codec), 8 dehex() (in module pwnypack.codec), 8	f (pwnypack.elf.ELF attribute), 12 fileno() (pwnypack.flow.ProcessChannel method), 14 fileno() (pwnypack.flow.SocketChannel method), 14 filesz (pwnypack.elf.ELF.ProgramHeader attribute), 10 find_gadget() (in module pwnypack.rop), 21 flags (pwnypack.elf.ELF attribute), 12 flags (pwnypack.elf.ELF.ProgramHeader attribute), 10 flags (pwnypack.elf.ELF.SectionHeader attribute), 11 Flow (class in pwnypack.flow), 15 fmtstring() (in module pwnypack.fmtstring), 18 frequency() (in module pwnypack.codec), 9	
disasm() (in module pwnypack.asm), 6	G	
ELF (class in pwnypack.elf), 9 elf (pwnypack.elf.ELF.SectionHeader attribute), 10	get_program_header() (pwnypack.elf.ELF method), 12 get_section_header() (pwnypack.elf.ELF method), 12 get_symbol() (pwnypack.elf.ELF method), 12	
elf (pwnypack.elf.ELF.Symbol attribute), 11 ELF.Machine (class in pwnypack.elf), 9 ELF.OSABI (class in pwnypack.elf), 9	H hsize (pwnypack.elf.ELF attribute), 12	
ELF.ProgramHeader (class in pwnypack.elf), 10 ELF.ProgramHeader.Flags (class in pwnypack.elf), 10 ELF.ProgramHeader.Type (class in pwnypack.elf), 10	info (pwnypack.elf.ELF.SectionHeader attribute), 11	

info (pwnypack.elf.ELF.Symbol attribute), 11 interact() (pwnypack.flow.Flow method), 16 invoke_ssh_shell() (pwnypack.flow.Flow class method), 16  K kill() (pwnypack.flow.Flow method), 16 kill() (pwnypack.flow.ProcessChannel method), 14 kill() (pwnypack.flow.SocketChannel method), 14	pwnypack.asm (module), 5 pwnypack.codec (module), 6 pwnypack.elf (module), 9 pwnypack.flow (module), 13 pwnypack.fmtstring (module), 18 pwnypack.packing (module), 19 pwnypack.rop (module), 21 pwnypack.target (module), 22 pwnypack.util (module), 23	
L	R	
link (pwnypack.elf.ELF.SectionHeader attribute), 11 listen_tcp() (pwnypack.flow.Flow class method), 16	read() (pwnypack.flow.Flow method), 16 read() (pwnypack.flow.ProcessChannel method), 14 read() (pwnypack.flow.SocketChannel method), 14	
M	read_eof() (pwnypack.flow.Flow method), 16	
machine (pwnypack.elf.ELF attribute), 12 memsz (pwnypack.elf.ELF.ProgramHeader attribute), 10 mode (pwnypack.target.Target attribute), 23	read_until() (pwnypack.flow.Flow method), 17 readline() (pwnypack.flow.Flow method), 17 readlines() (pwnypack.flow.Flow method), 17 reghex() (in module pwnypack.util), 23 rot13() (in module pwnypack.codec), 7	
N		
name (pwnypack.elf.ELF.SectionHeader attribute), 11 name (pwnypack.elf.ELF.Symbol attribute), 11	S	
name_index (pwnypack.elf.ELF.SectionHeader attribute), 11 name_index (pwnypack.elf.ELF.Symbol attribute), 11	section_headers (pwnypack.elf.ELF attribute), 13 shentsize (pwnypack.elf.ELF attribute), 13 shndx (pwnypack.elf.ELF.Symbol attribute), 11 shnum (pwnypack.elf.ELF attribute), 13	
O	shoff (pwnypack.elf.ELF attribute), 13 shstrndx (pwnypack.elf.ELF attribute), 13	
offset (pwnypack.elf.ELF.ProgramHeader attribute), 10 offset (pwnypack.elf.ELF.SectionHeader attribute), 11 osabi (pwnypack.elf.ELF attribute), 12 other (pwnypack.elf.ELF.Symbol attribute), 11	size (pwnypack.elf.ELF. attribute), 11 size (pwnypack.elf.ELF. Symbol attribute), 12 SocketChannel (class in pwnypack.flow), 14 symbols (pwnypack.elf.ELF attribute), 13	
P	T	
P() (in module pwnypack.packing), 19 p() (in module pwnypack.packing), 20 P16() (in module pwnypack.packing), 21 p16() (in module pwnypack.packing), 21 P32() (in module pwnypack.packing), 21 p32() (in module pwnypack.packing), 21 P64() (in module pwnypack.packing), 21 P64() (in module pwnypack.packing), 21 p8() (in module pwnypack.packing), 21 p8() (in module pwnypack.packing), 20 pack() (in module pwnypack.packing), 19 pack_size() (in module pwnypack.packing), 19 paddr (pwnypack.elf.ELF.ProgramHeader attribute), 10 parse_file() (pwnypack.elf.ELF method), 12 phentsize (pwnypack.elf.ELF attribute), 12	Target (class in pwnypack.target), 22 Target.Arch (class in pwnypack.target), 22 Target.Bits (class in pwnypack.target), 22 Target.Endian (class in pwnypack.target), 22 Target.Mode (class in pwnypack.target), 22 TCPClientSocketChannel (class in pwnypack.flow), 14 type (pwnypack.elf.ELF attribute), 13 type (pwnypack.elf.ELF.ProgramHeader attribute), 10 type (pwnypack.elf.ELF.SectionHeader attribute), 11 type_id (pwnypack.elf.ELF.ProgramHeader attribute), 12 type_id (pwnypack.elf.ELF.SectionHeader attribute), 11 type_id (pwnypack.elf.ELF.SectionHeader attribute), 11 type_id (pwnypack.elf.ELF.Symbol attribute), 12	
phonum (pwnypack.elf.ELF attribute), 12 phoff (pwnypack.elf.ELF attribute), 13 pickle_call() (in module pwnypack.util), 24 ProcessChannel (class in pwnypack.flow), 13 program, headers (pwnypack, elf ELF attribute), 13	U  U() (in module pwnypack.packing), 20 u() (in module pwnypack.packing), 20 U16() (in module pwnypack.packing), 21 u16() (in module pwnypack.packing), 21	

30 Index

```
U32() (in module pwnypack.packing), 21
u32() (in module pwnypack.packing), 21
U64() (in module pwnypack.packing), 21
u64() (in module pwnypack.packing), 21
U8() (in module pwnypack.packing), 21
u8() (in module pwnypack.packing), 21
unpack() (in module pwnypack.packing), 19
until() (pwnypack.flow.Flow method), 17

V
vaddr (pwnypack.elf.ELF.ProgramHeader attribute), 10
value (pwnypack.elf.ELF.Symbol attribute), 12
visibility (pwnypack.elf.ELF.Symbol attribute), 12
```

# W

write() (pwnypack.flow.Flow method), 17 write() (pwnypack.flow.ProcessChannel method), 14 write() (pwnypack.flow.SocketChannel method), 14 writeline() (pwnypack.flow.Flow method), 18 writelines() (pwnypack.flow.Flow method), 18

# Χ

xor() (in module pwnypack.codec), 6

Index 31