# The **irace** Package: User Guide

## Manuel López-Ibáñez, Leslie Pérez Cáceres, Jérémie Dubois-Lacoste, Thomas Stützle and Mauro Birattari IRIDIA, CoDE, Université Libre de Bruxelles, Brussels, Belgium

## Version 3.3, April 26, 2019

## Contents

1	Ger	neral information					
	1.1	Background					
	1.2	Version					
	1.3	License					
2	Bef	ore starting					
3	Inst	tallation					
	3.1	System requirements					
	3.2	irace installation					
		3.2.1 Install automatically within R					
		3.2.2 Manual download and installation					
		3.2.3 Local installation					
		3.2.4 Testing the installation and invoking irace					
4	Running irace						
	4.1	Step-by-step setup guide					
	4.2	Setup example for ACOTSP					
5	Defining a configuration scenario						
	5.1	Target algorithm parameters					
		5.1.1 Parameter types					
		5.1.2 Parameter domains					
		5.1.3 Conditional parameters					
		5.1.4 Parameter file format					
		5.1.5 Parameters R format					
	5.2	Target algorithm runner					
		5.2.1 Target runner executable program					
		5.2.2 Target runner R function					
	5.3	Target evaluator					
		5.3.1 Target evaluator executable program					
		5.3.2 Target evaluator R function					
	5.4	Training instances					

	5.5 5.6 5.7	Initial configurations	21 22 22
6	Paral	lelization	23
7	Testi	ng (Validation) of configurations	<b>25</b>
8	Recov	vering irace runs	<b>25</b>
9	Outp	ut and results	26
	9.1	Text output	26
	9.2	R data file (logFile)	29
	9.3	Analysis of results	34
10	Adva	nced topics	39
	10.1	Tuning budget	39
	10.2	Multi-objective tuning	39
	10.3	Tuning for minimizing computation time	40
	10.4	Hyper-pararameter optimization of machine learning methods	41
	10.5	Heterogeneous scenarios	41
	10.6	Choosing the statistical test	42
	10.7	Complex parameter space constraints	42
	10.8	Unreliable target algorithms and immediate rejection	43
	10.9	Ablation Analysis	44
	10.10	Postselection race	45
11	List o	of command-line and scenario options	46
	11.1	General options	46
	11.2	Elitist irace	47
	11.3	Internal irace options	48
	11.4	Target algorithm parameters	49
	11.5	Target algorithm execution	49
	11.6	Initial configurations	50
	11.7	Training instances	50
	11.8	Tuning budget	50
	11.9	Statistical test	51
	11.10	Adaptive capping	51
	11.11	Recovery	52
	11.12	Testing	52
f 12	FAQ	(Frequently Asked Questions)	53
	12.1	Is <b>irace</b> minimizing or maximizing the output of my algorithm?	53
	12.2	Is it possible to configure a MATLAB algorithm with irace?	53
	12.3	My program works perfectly on its own, but not when running under <b>irace</b> . Is	
		irace broken?	53
	12.4	My program may be buggy and run into an infinite loop. Is it possible to set a maximum timeout?	
	12.5	When using the mpi option, <b>irace</b> is aborted with an error message indicating	54
	12.0	that a function is not defined. How to fix this?	5/

<ul> <li>Error: 4 arguments passed to .Internal(nchar) which requires 3</li> <li>How are relative filesystem paths interpreted by irace?</li> <li>My parameter space is small enough that irace could generate all possible configurations; however, irace generates repeated configurations and/or does not generate some of them. Is this a bug?</li></ul>	54 55 55			
3 Resources and contact information				
14 Acknowledgements Bibliography				
Appendix B targetRunner troubleshooting checklist	57			
Appendix C targetEvaluator troubleshooting checklist	60			
Appendix D Glossary				
Appendix E NEWS	61			

## 1 General information

## 1.1 Background

The **irace** package implements an *iterated racing* procedure, which is an extension of Iterated F-race (I/F-Race) [2]. The main use of **irace** is the automatic configuration of optimization and decision algorithms, that is, finding the most appropriate settings of an algorithm given a set of instances of a problem. However, it may also be useful for configuring other types of algorithms when performance depends on the used parameter settings. It builds upon the **race** package by Birattari and it is implemented in R. The **irace** package is available from CRAN:

https://cran.r-project.org/package=irace

More information about irace is available at http://iridia.ulb.ac.be/irace.

### 1.2 Version

The current version of the **irace** package is 3.3. Previous versions of the package can also be found in the CRAN website.

The algorithm underlying the current version of **irace** and its motivation are described by López-Ibáñez et al. [8]. The **adaptive capping mechanism** available from version 3.0 is described by Pérez Cáceres et al. [10]. Details of the implementation before version 2.0 can be found in a previous technical report [7].



Versions of irace before 2.0 are not compatible with the file formats detailed in this document.

#### 1.3 License

The **irace** package is Copyright © 2019 and distributed under the GNU General Public License version 3.0 (http://www.gnu.org/licenses/gpl-3.0.en.html). The **irace** package is free software (software libre): You can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

The **irace** package is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

Please be aware that the fact that this program is released as Free Software does not excuse you from scientific propriety, which obligates you to give appropriate credit! If you write a scientific paper describing research that made substantive use of this program, it is your obligation as a scientist to (a) mention the fashion in which this software was used in the Methods section; (b) mention the algorithm in the References section. The appropriate citation is:

Manuel López-Ibáñez, Jérémie Dubois-Lacoste, Leslie Pérez Cáceres, Thomas Stützle, and Mauro Birattari. The **irace** package: Iterated Racing for Automatic Algorithm Configuration. *Operations Research Perspectives*, 3:43–58, 2016. doi: 10.1016/j.orp.2016.09.002




Figure 1: Scheme of irace flow of information.

## 2 Before starting

The **irace** package provides an automatic configuration tool for tuning optimization algorithms, that is, automatically finding good configurations for the parameters values of a (target) algorithm saving the effort that normally requires manual tuning.

Figure 1 gives a general scheme of how **irace** works. **Irace** receives as input a parameter space definition corresponding to the parameters of the target algorithm that will be tuned, a set of instances for which the parameters must be tuned for and a set of options for **irace** that define the configuration scenario. Then, **irace** searches in the parameter search space for good performing algorithm configurations by executing the target algorithm on different instances and with different parameter configurations. A **targetRunner** must be provided to execute the target algorithm with a specific parameter configuration ( $\theta$ ) and instance (i). The **targetRunner** function (or program) acts as an interface between the execution of the target algorithm and **irace**: It receives the instance and configuration as arguments and must return the evaluation of the execution of the target algorithm.

The following user guide contains guidelines for installing **irace**, defining configuration scenarios, and using **irace** to automatically configure your algorithms.

## 3 Installation

## 3.1 System requirements

- R (version ≥ 3.2.0) is required for running irace, but you don't need to know the R language to use it. R is freely available and you can download it from the R project website (https://www.r-project.org). See Appendix A for a quick installation guide of R.
- For GNU/Linux and OS X, the command-line executables irace and parallel-irace require GNU Bash. There is also an irace.bat for Windows. Individual examples may require additional software.

#### 3.2 irace installation

The **irace** package can be installed automatically within R or by manual download and installation. We advise to use the automatic installation unless particular circumstances do not allow it. The instructions to install **irace** with the two mentioned methods are the following:

#### 3.2.1 Install automatically within R

Execute the following line in the R console to install the package:

```
install.packages("irace")
```

Select a mirror close to your location, and test the installation in the R console with:

```
library("irace")
q() # To exit R
```

Alternatively, within the R graphical interface, you may use the Packages and data->Package installer menu on OS X or the Packages menu on Windows.

#### 3.2.2 Manual download and installation

From the **irace** package CRAN website (https://cran.r-project.org/package=irace), download one of the three versions available depending on your operating system:

- irace\_3.3.tar.gz (Unix/BSD/GNU/Linux)
- irace\_3.3.tgz (OS X)
- irace\_3.3.zip (Windows)

To install the package on GNU/Linux and OS X, you must execute the following command at the shell (replace <package> with the path to the downloaded file, either irace\_3.3.tar.gz or irace\_3.3.zip):

```
R CMD INSTALL <package>
```

To install the package on Windows, open R and execute the following line on the R console (replace <package> with the path to the downloaded file irace\_3.3.zip):

```
install.packages("<package>", repos = NULL)
```

If the previous installation instructions fail because of insufficient permissions and you do not have sufficient admin rights to install **irace** system-wide, then you need to force a local installation.

#### 3.2.3 Local installation

Let's assume you wish to install **irace** on a path denoted by <R\_LIBS\_USER>, which is a filesystem path for which you have sufficient rights. This directory **must** exist before attempting the installation. Moreover, you must provide to R the path to this library when loading the package.

However, the latter can be avoided by adding the path to the system variable R\_LIBS or to the R internal variable .libPaths, as we will see below.<sup>1</sup>

On  $\mathrm{GNU}/\mathrm{Linux}$  or OS X, execute the following commands to install the package on a local directory:

```
export R_LIBS_USER="<R_LIBS_USER>"
# Create R_LIBS_USER if it doesn't exist
mkdir $R_LIBS_USER
# Replace <package> with the path to the downloaded file.
R CMD INSTALL --library=$R_LIBS_USER <package>
# Tell R where to find R_LIBS_USER
export R_LIBS=${R_LIBS_USER}:${R_LIBS}
```

On Windows, you can install the package on a local directory by executing the following lines in the R console:

```
# Replace <package> with the path to the downloaded file.
# Replace <R_LIBS_USER> with the path used for installation.
install.packages("<package>", repos = NULL, lib = "<R_LIBS_USER>")
# Tell R where to find R_LIBS_USER.
# This must be executed for every new session.
.libPaths(c("<R_LIBS_USER>", .libPaths()))
```

### 3.2.4 Testing the installation and invoking irace

Once **irace** has been installed, load the package and test that the installation was successful by opening an R console and executing:

```
# Load the package
library("irace")
# Obtain the installation path
system.file(package = "irace")
```

The last command must print out the filesystem path where **irace** is installed. In the remainder of this guide, the variable \$IRACE\_HOME is used to denote this path. When executing any provided command that includes the \$IRACE\_HOME variable do not forget to replace this variable with the installation path of **irace**.

On GNU/Linux or OS X, you can let the operating system know where to find **irace** by defining the \$IRACE\_HOME variable and adding it to the system PATH. Append the following commands to ~/.bash\_profile, ~/.bashrc or ~/.profile:

```
# Replace <IRACE_HOME> with the irace installation path
export IRACE_HOME=<IRACE_HOME>
export PATH=${IRACE_HOME}/bin/:$PATH
# Tell R where to find R_LIBS_USER
# Use the following line only if local installation was forced
export R_LIBS=${R_LIBS_USER}:${R_LIBS}
```

<sup>&</sup>lt;sup>1</sup>On Windows, see also https://cran.r-project.org/bin/windows/base/rw-FAQ.html#I-don\_0027t-have-permission-to-write-to-the-R\_002d3\_002e3\_002e1\_005clibrary-directory.

Then, open a new terminal and launch **irace** as follows:

```
irace --help
```

On Windows, you need to add both R and the installation path of **irace** to the environment variable PATH. To edit the PATH, search for "Environment variables" in the control panel, edit PATH and add a string similar to C:\R\_PATH\bin;C:\IRACE\_HOME\bin where R\_PATH is the installation path of R and IRACE\_HOME is the installation path of **irace**. If **irace** was installed locally, you also need to edit the environment variable R\_LIBS to add R\_LIBS\_USER. Then, open a new terminal (run program cmd.exe) and launch **irace** as:

```
irace.bat --help
```

Alternatively, you may directly invoke irace from within the R console by executing:

```
library("irace")
irace.cmdline("--help")
```

## 4 Running irace

Before performing the tuning of your algorithm, it is necessary to define a tuning scenario that will give **irace** all the necessary information to optimize the parameters of the algorithm. The tuning scenario is composed of the following elements:

- 1. Target algorithm parameter description (see Section 5.1).
- 2. Target algorithm runner (see Section 5.2).
- 3. Training instances list (see Section 5.4)
- 4. **irace** options (see Section 11).
- 5. Optional: Initial configurations (see Section 5.5).
- 6. Optional: Forbidden configurations (see Section 5.6).
- 7. Optional: Target algorithm evaluator (see Section 5.3).

These scenario elements can be provided as plain text files or as R objects. This user guide provides examples of both types, but we advise the use of plain text files, which we consider the simpler option.

For a step-by-step guide to create the scenario elements for your target algorithm continue to Section 4.1. For an example execution of **irace** using the **ACOTSP** scenario go to Section 4.2.

### 4.1 Step-by-step setup guide

This section provides a guide to setup a basic execution of **irace**. The template files provided in the package (**\$IRACE\_HOME/templates**) will be used as basis for creating your new scenario. Please follow carefully the indications provided in each step and in the template files used; if you have doubts check the the sections that describe each option in detail.

1. Create a directory (e.g., ~/tuning/) for the scenario setup. This directory will contain all the files that describe the scenario. On GNU/Linux or OS X, you can do this as follows:

```
mkdir ~/tuning
cd ~/tuning
```

2. Copy all the template files from the **\$IRACE\_HOME/templates/** directory to the scenario directory.

```
# $IRACE_HOME is the installation directory of irace.
cp $IRACE_HOME/templates/*.tmpl ~/tuning/
```

- 3. For each template in your tuning directory, remove the .tmpl suffix, and modify them following the next steps.
- 4. Define the target algorithm parameters to be tuned by following the instructions in parameters.txt. Available parameter types and other guidelines can be found in Section 5.1.
- 5. Optional: Define the initial parameter configuration(s) of your algorithm, which allows you to provide good starting configurations (if you know some) for the tuning. Follow the instructions in configurations.txt and set configurationsFile="configurations.txt" in scenario.txt. More information in Section 5.5. If you do not need to define initial configurations remove this file from the directory.
- 6. Optional: Define forbidden parameter value combinations, that is, configurations that irace must not consider in the tuning. Follow the instructions in forbidden.txt and update scenario.txt with forbiddenFile = "forbidden.txt". More information about forbidden configurations in Section 5.6. If you do not need to define forbidden configurations remove this file from the directory.
- 7. Place the instances you would like to use for the tuning of your algorithm in the folder ~/tuning/Instances/. In addition, you can create a file (e.g., instances-list.txt) that specifies which instances from that directory should be run and which instance-specific parameters to use. To use such an instance file, set the appropriate option in scenario.txt, e.g., trainInstancesFile = "instances-list.txt". See Section 5.4 for guidelines.
- 8. Uncomment and assign in scenario.txt only the options for which you need a value different from the default. Some common parameters that you might want to adjust are:
  - execDir (--exec-dir): the directory in which irace will execute the target algorithm; the
    default value is the current directory.
  - maxExperiments (--max-experiments): the maximum number of executions of the target algorithm that **irace** will perform.
  - maxTime (--max-time): maximum total execution time in seconds for the executions of
    targetRunner. In this case, targetRunner must return two values: cost and time.
    Note that you must provide either maxTime or maxExperiments.

For setting the tuning budget see Section 10.1. For more information on **irace** options and their default values, see Section 11.

- 9. Modify the target-runner script to run your algorithm. This script must execute your algorithm with the parameters and instance specified by irace and return the evaluation of the execution and optionally the execution time (cost [time]). When the maxTime option is used, returning time is mandatory. The target-runner template is written in GNU Bash scripting language, which can be executed easily in GNU/Linux and OS X systems. However, you may use any other programming language. As an example, we provide a Python example in the directory \$IRACE\_HOME/examples/python. Follow these instructions to adjust the given target-runner template to your algorithm:
  - (a) Set the EXE variable with the path to the executable of the target algorithm.
  - (b) Set the FIXED\_PARAMS if you need extra arguments in the execution line of your algorithm. An example could be the time that your algorithm is required to run (FIXED\_PARAMS ="--time 60") or the number of evaluations required (FIXED\_PARAMS="--evaluations 10000").
  - (c) The line provided in the template executes the executable described in the EXE variable.

```
$EXE ${FIXED_PARAMS} -i ${INSTANCE} --seed ${SEED} ${CONFIG_PARAMS}
```

You must change this line according to the way your algorithm is executed. In this example, the algorithm receives the instance to solve with the flag -i and the seed of the random number generator with the flag --seed. The variable CONFIG\_PARAMS adds to the command line the parameters that **irace** has given for the execution. You must set the command line execution as needed. For example, the instance might not need a flag and might need to be the first argument:

```
$EXE ${INSTANCE} ${FIXED_PARAMS} --seed ${SEED} ${CONFIG_PARAMS}
```

The output of your algorithm is saved to the file defined in the \$STDOUT variable, and error output is saved in the file given by \$STDERR. The line:

```
if [ -s "$STDOUT" ]; then
```

checks if the file containing the output of your algorithm is not empty. The example provided in the template assumes that your algorithm prints in the last output line the best result found (only a number). The line:

```
COST=$(cat ${STDOUT} | grep -e '^[[:space:]]*[+-]\?[0-9]' | cut -f1)
```

parses the output of your algorithm to obtain the result from the last line. The target-runner script must return only one number. In the template example, the result is returned with echo "\$COST" (assuming maxExperiments is used) and the used files are deleted.



The target-runner script must be executable.

You can test the target runner from the R console by checking the scenario as explained earlier in Section 4.

If you have problems related to the target-runner script when executing irace, see Appendix B for a check list to help diagnose common problems. For more information about the targetRunner, please see Section 5.2,

10. Optional: Modify the target-evaluator file. This is rarely needed and the target-runner template does not use it. Section 5.3 explains when a targetEvaluator is needed and how to define it.

- 11. The **irace** executable provides an option (--check) to check that the scenario is correctly defined. We recommend to perform a check every time you create a new scenario. When performing the check, **irace** will verify that the scenario and parameter definitions are correct and will test the execution of the target algorithm. To check your scenario execute the following commands:
  - From the command-line (on Windows, execute irace.bat):

```
# $IRACE_HOME is the installation directory of irace.
$IRACE_HOME/bin/irace --scenario scenario.txt --check
```

• Or from the R console:

- 12. Once all the scenario elements are prepared you can execute **irace**, either using the command-line wrappers provided by the package or directly from the R console:
  - From the command-line console, call the command (on Windows, you should execute irace.bat):

```
cd ~/tuning/
# $IRACE_HOME is the installation directory of irace
# By default, irace reads scenario.txt, you can specify a different file
# with --scenario.
$IRACE_HOME/bin/irace
```

For this example we assume that the needed scenario files have been set properly in the scenario.txt file using the options described in Section 11. Most irace options can be specified in the command line or directly in the scenario.txt file.

• From the R console, evaluate:

This will perform one run of **irace**. See the output of **irace** --help in the command-line or **irace.usage()** in R for quick information on additional **irace** parameters. For more information about **irace** options, see Section 11.



Command-line options override the same options specified in the scenario.txt file.

## 4.2 Setup example for ACOTSP

The ACOTSP tuning example can be found in the package installation at \$IRACE\_HOME/examples/acotsp. Additionally, a number of example scenarios can be found in the examples folder. More examples of tuning scenarios can be found in the Algorithm Configuration Library (AClib, http://www.aclib.net/).

In this section, we describe how to execute the **ACOTSP** scenario. If you wish to start setting up your own scenario, continue to the next section. For this example, we assume a GNU/Linux system but making the necessary changes in the commands and <code>targetRunner</code>, it can be executed in any system that has a C compiler. To execute this scenario follow these steps:

1. Create a directory for the tuning (e.g., ~/tuning/) and copy the example scenario files located in the examples folder to the created directory:

```
mkdir ~/tuning
cd ~/tuning
# $IRACE_HOME is the installation directory of irace.
cp $IRACE_HOME/examples/acotsp/* ~/tuning/
```

- 2. Download the training instances from http://iridia.ulb.ac.be/irace/ to the ~/tuning/directory.
- 3. Create the instance directory (e.g., ~/tuning/Instances) and decompress the instance files on it.

```
mkdir ~/tuning/Instances/
cd ~/tuning/
tar -xvf tsp-instances-training.tar.bz2 Instances/
```

4. Download the **ACOTSP** software from http://www.aco-metaheuristic.org/aco-code/ to the ~/tuning/ directory and compile it.

```
cd ~/tuning/
tar -xvf ACOTSP-1.03.tgz
cd ~/tuning/ACOTSP-1.03
make
```

5. Create a directory for the executable and copy it:

```
mkdir ~/bin/
cp ~/tuning/ACOTSP-1.03/acotsp ~/bin/
```

6. Create a directory for executing the experiments and execute **irace**:

```
mkdir ~/tuning/acotsp-arena/
cd ~/tuning/
# $IRACE_HOME is the installation directory of irace.
$IRACE_HOME/bin/irace
```

7. Or you can also execute **irace** from the R console using:

```
library("irace")
setwd("~/tuning/")
irace.cmdline()
```

## 5 Defining a configuration scenario

## 5.1 Target algorithm parameters

The parameters of the target algorithm are defined by a parameter file as described in Section 5.1.4. Optionally, when executing **irace** from the R console, the parameters can be specified directly as an R object (see Section 5.1.5). For defining your parameters follow the guidelines provided in the following sections.

### 5.1.1 Parameter types

Each target parameter has an associated type that defines its domain and the way **irace** handles them internally. Understanding the nature of the domains of the target parameters is important to select appropriate types. The four basic types supported by **irace** are the following:

- Real parameters are numerical parameters that can take floating-point values within a given range. The range is specified as an interval '(<lower bound>, <upper bound>)'. This interval is closed, that is, the parameter value may eventually be one of the bounds. The possible values are rounded to a number of decimal places specified by option digits. For example, given the default number of digits of 4, the values 0.12345 and 0.12341 are both rounded to 0.1234. Selected real-valued parameters can be optionally sampled on a logarithmic scale (base e).
- *Integer* parameters are numerical parameters that can take only integer values within the given range. Their range is specified as the range of real parameters and they can also be optionally sampled on a logarithmic scale (base *e*).
- Categorical parameters are defined by a set of possible values specified as '(<value 1>, ..., <value n>)'. The values are quoted or unquoted character strings. Empty strings and strings containing commas or spaces must be quoted.
- Ordinal parameters are defined by an ordered set of possible values in the same format as for categorical parameters. They are handled internally as integer parameters, where the integers correspond to the indexes of the values.

### 5.1.2 Parameter domains

For each target parameter, an interval or a set of values must be defined according to its type, as described above. There is no limit for the size of the set or the length of the interval, but keep in mind that larger domains could increase the difficulty of the tuning task. Choose always values that you consider relevant for the tuning. In case of doubt, we recommend to choose larger intervals, as occasionally best parameter settings may be not intuitive a priori. All intervals are considered as closed intervals.

It is possible to define parameters that will have always the same value. Such "fixed" parameters will not be tuned but their values are used when executing the target algorithm and they are affected by constraints defined on them. All fixed parameters must be defined as categorical parameters and have a domain of one element.

#### 5.1.3 Conditional parameters

Conditional parameters are active only when others have certain values. These dependencies define a hierarchical relation between parameters. For example, the target algorithm may have a parameter localsearch that takes values (sa,ts) and another parameter ts-length that only needs to be set if the first parameter takes precisely the value ts. Thus, parameter ts-length is conditional on localsearch == "ts".

#### 5.1.4 Parameter file format

For simplicity, the description of the parameters space is given as a table. Each line of the table defines a configurable parameter

```
<name> <label> <type> <range> [ | <condition> ]
```

where each field is defined as follows:

<name> The name of the parameter as an unquoted alphanumeric string, e.g., 'ants'.

<label> A label for this parameter. This is a string that will be passed together with the parameter to targetRunner. In the default targetRunner provided with the package (Section 5.2), this is the command-line switch used to pass the value of this parameter, for instance '"--ants "'.

The value of the parameter is concatenated without separator to the label when invoking targetRunner, thus any whitespace in the label is significant. Following the same example, when parameter ants takes value 5, the default targetRunner will pass the parameter as "--ants 5".

<type> The type of the parameter, either integer, real, ordinal or categorical, given as a single letter: 'i', 'r', 'o' or 'c'. Numerical parameters can be sampled using a natural logarithmic scale with 'i,log' and 'r,log' (without spaces) for integer and real parameters, respectively.

<range> The range or set of values of the parameter delimited by parentheses.
e.g., (0,1) or (a,b,c,d).

<condition> An optional condition that determines whether the parameter is enabled or disabled, thus making the parameter conditional. If the condition evaluates to false, then no value is assigned to this parameter, and neither the parameter value nor the corresponding label are passed to targetRunner. The condition must follow the same syntax as those for specifying forbidden configurations (Section 5.6), that is, it must be a valid R logical expression². The condition may contain the name of other parameters as long as the dependency graph does not contain any cycle. Otherwise, irace will detect the cycle and stop with an error.

As an example, Figure 2 shows the parameters file of the ACOTSP scenario.

#### 5.1.5 Parameters R format

The target parameters are stored in an R list that you can obtain from the R console using the following command:

<sup>&</sup>lt;sup>2</sup>For a list of R operators see: https://stat.ethz.ch/R-manual/R-devel/library/base/html/Syntax.html

```
# name
            switch
                              type
                                       values
                                                            [conditions (using R syntax)]
algorithm
                                       (as,mmas,eas,ras,acs)
localsearch "--localsearch "
                             С
                                       (0, 1, 2, 3)
            "--alpha "
                                       (0.00, 5.00)
alpha
                             r
            "--beta "
                                       (0.00, 10.00)
beta
                             r
            "--rho "
rho
                                       (0.01, 1.00)
                             r
            "--ants "
ants
                             i
                                       (5, 100)
            "--nnls "
                                       (5, 50)
                                                            | localsearch %in% c(1, 2, 3)
nnls
                             i
q0
            "--q0 "
                                       (0.0, 1.0)
                                                            | algorithm == "acs"
                             r
            "--dlb "
                                       (0, 1)
dlb
                                                            | localsearch %in% c(1,2,3)
                              С
rasrank
            "--rasranks "
                                       (1, 100)
                                                            | algorithm == "ras"
                             i
elitistants "--elitistants "
                                       (1, 750)
                                                            | algorithm == "eas"
```

Figure 2: Parameter file (parameters.txt) for tuning ACOTSP.

```
parameters <- readParameters(file = "parameters.txt")</pre>
```

See the help of the readParameters function (?readParameters) for more information. The structure of the parameter list that is created is as follows:

```
structure of the parameter list that is created is as follows:
         names
                 Vector that contains the names of the parameters.
         types
                 Vector that contains the type of each parameter 'i', 'c', 'r', 'o'.
                 Vector that contains the labels of the parameters. e.g., switches to be used
     switches
                 for the parameters on the command line.
                 List of vectors, where each vector may contain two values (minimum, maxi-
        domain
                 mum) for real and integer parameters, or a set of values for categorical and
                 ordinal parameters.
   conditions
                 List of R logical expressions, with variables corresponding to parameter
                 names.
                 Logical vector that specifies which parameter is fixed and, thus, it does not
      isFixed
                 need to be tuned.
    transform
                 Vector that contains the transformation of each parameter. Currently, it can
                 take values "" (no transformation, default) of "log" (natural logarithmic
                 transformation).
 nbParameters
                 An integer, the total number of parameters.
      nbFixed
                 An integer, the number of parameters with a fixed value.
                 Number of variable (i.e., to be tuned) parameters.
   nbVariable
```

The following example shows the structure of the parameters R object for the algorithm, ants and q0 parameters of the ACOTSP scenario:

```
..- attr(*, "names")= chr [1:3] "algorithm" "ants" "q0"
            :List of 3
$ domain
..$ algorithm: chr [1:5] "as" "mmas" "eas" "ras" "acs"
..$ ants : num [1:2] 5 100
 ..$ q0
           : num [1:2] 0 1
$ conditions :List of 3
 ..$ algorithm: logi TRUE
 ..$ ants : logi TRUE
             : expression(algorithm %in% c("acs"))
..$ q0
$ isFixed
            : Named logi [1:3] FALSE FALSE FALSE
..- attr(*, "names")= chr [1:3] "algorithm" "ants" "q0"
$ transform :List of 3
..$ algorithm: chr ""
..$ ants : chr ""
            : chr ""
 ..$ q0
$ hierarchy : Named num [1:3] 1 1 2
..- attr(*, "names")= chr [1:3] "algorithm" "ants" "q0"
$ nbParameters: int 3
$ nbFixed : int 0
$ nbVariable : int 3
```

## 5.2 Target algorithm runner

The evaluation of a candidate configuration on a single instance is done by means of a user-given auxiliary program or, alternatively, a user-given R function. The function (or program name) is specified by the option targetRunner. The targetRunner must return the cost value (e.g., cost of the best solution found) of the evaluation; unless computing the cost requires information from all the configurations evaluated on an instance, e.g., when evaluating multi-objective algorithms with unknown normalisation bounds (see Section 5.3 for details).



The objective of **irace** is to minimize the cost value returned by the target algorithm. If you wish to maximize, you can multiply the cost by -1 before returning it to **irace**.

### 5.2.1 Target runner executable program

When targetRunner is an auxiliary executable program, it is invoked for each candidate configuration, passing as arguments:

<id.configuration> <id.instance> <seed> <instance> [bound] <configuration>

id.configuration an alphanumeric string that uniquely identifies a configuration;

id.instance an alphanumeric string that uniquely identifies an instance;

seed seed for the random number generator to be used for this evaluation,

ignore the seed for deterministic algorithms;

instance string giving the instance to be used for this evaluation;

bound optional execution time bound. Only provided when the maxBound option

is set in the scenario, see Section 10.3;

configuration the pairs parameter label-value that describe this candidate configuration.

Typically given as command-line switches to be passed to the executable

program.

The experiment list shown in Section 5.2.2, would result in the following execution line:

```
target-runner 1 113 734718556 /home/user/instances/tsp/2000-533.tsp \
--eas --localsearch 0 --alpha 2.92 --beta 3.06 --rho 0.6 --ants 80
```

The command line switches that describe the candidate configuration are constructed by appending to each parameter label (switch), without separator, the value of the parameter, following the order given in the parameter table. The program targetRunner must print a real number, which corresponds to the cost measure of the candidate configuration for the given instance and optionally its execution time (mandatory when maxTime is used and/or when the capping option is enabled). The working directory of targetRunner is set to the execution directory specified by the option execDir. This allows the user to execute independent runs of irace in parallel using different values for execDir, without the runs interfering with each other.

#### 5.2.2 Target runner R function

When targetRunner is an R function, it is invoked for each candidate configuration as:

```
targetRunner(experiment, scenario)
```

where experiment is a list that contains information about configuration and instance to execute one experiment, and scenario is the scenario list. The structure of the experiment list is as follows:

id.configuration an alphanumeric string that uniquely identifies a configuration;

id.instance an alphanumeric string that uniquely identifies an instance;

seed seed to be used for this evaluation;

instance string giving the instance to be used for this evaluation;

bound optional execution time bound;

configuration 1-row data frame with a column per parameter name;

switches vector of parameter switches (labels) in the order of parameters used in

configuration.

The following is an example of an experiment list for the **ACOTSP** scenario:

```
> print(experiment)
```

```
$id.configuration
[1] 1
$id.instance
[1] 4
$seed
[1] 1220261452
$configuration
 algorithm localsearch alpha beta rho ants nnls q0 dlb rasrank
             0 1 1 0.95 10 NA NA <NA>
 elitistants
1
        NA
$instance
[1] "./instances/1000-4.tsp"
$switches
     algorithm
                 localsearch
                                     alpha
          "--" "--localsearch "
                                  "--alpha "
                                                  "--beta "
          rho ants
                                   nnls
                                                   q0
      "--rho "
                                  "--nnls "
                    "--ants "
                                                    "--q0 "
                     rasrank
         dlb
                                 elitistants
       "--dlb " "--rasranks " "--elitistants "
```

If targetEvaluator is NULL, then the targetRunner function must return a list with at least one element "cost", the numerical value corresponding to the evaluation of the given configuration on the given instance. A cost of Inf is accepted and results in the immediate rejection of the configuration (see Section 10.8).

If the scenario option maxTime is non-zero or if the capping option is enabled, then the list must contain at least another element "time" that reports the execution time for this call to targetRunner.

The return list may also contain the following optional elements that are used by **irace** for reporting errors in targetRunner:

```
    error is a string used to report an error;
    outputRaw is a string used to report the raw output of calls to an external program or function;
    call is a string used to report how targetRunner called an external program or function;
```

## 5.3 Target evaluator

Normally, targetRunner returns the cost of the execution of a candidate configuration (see Section 5.2). However, there are cases when the cost evaluation must be delayed until all candidate configurations in a race have been executed on a instance.

The targetEvaluator option defines an auxiliary program (or an R function) that allows postponing the evaluations of the candidate configurations. For each instance seen, the program

targetEvaluator is only invoked after all the calls to targetRunner for all alive candidate configurations on the same instance have already finished.



When using targetEvaluator, targetRunner must not return the evaluation of the configuration. If maxTime is used, targetRunner must return only execution time.

As an example, targetEvaluator may be used to dynamically find normalization bounds for the output returned by an algorithm for each individual instance. In this case, targetRunner will save the output of the algorithm, then the first call to targetEvaluator will examine the output produced by all calls to targetRunner for the same instance, update the normalization bounds and return the normalized output. Subsequent calls to targetEvaluator for the same instance will simply return the normalized output.

A similar need arises when using quality measures for multi-objective optimization algorithms, such as the hypervolume, which typically require specifying reference points or sets. By using targetEvaluator, it is possible to dynamically compute the reference points or sets while irace is running. Examples are provided at examples/hypervolume. See also Section 10.2 for more information on how to tune multi-objective algorithms.

### 5.3.1 Target evaluator executable program

When targetEvaluator is an auxiliary executable program, it is invoked for each candidate with the following arguments:

```
<id.configuration> <id.instance> <seed> <instance> <num.configs> <all.conf.id>
id.configuration an alphanumeric string that uniquely identifies a configuration;
id.instance an alphanumeric string that uniquely identifies an instance;
seed seed to be used for this evaluation;
instance string giving the instance to be used for this evaluation;
num.configs number of alive candidate configurations;
all.conf.id list of IDs of the alive configurations separated by whitespace.
```

The targetEvaluator executable must print a numerical value corresponding to the cost measure of the candidate configuration on the given instance.

#### 5.3.2 Target evaluator R function

When targetEvaluator is an R function, it is invoked for each candidate configuration as:

where experiment is a list that contains information about one experiment (see Section 5.2.2), num.configurations is the number of configurations alive in the race, all.conf.id is the vector of IDs of the alive configurations, scenario is the scenario list and target.tunner.call is the string of the targetRunner execution line.

The function targetEvaluator must return a list with one element "cost", the numerical value corresponding to the cost measure of the given configuration on the given instance.

The return list may also contain the following optional elements that are used by **irace** for reporting errors in targetEvaluator:

```
error is a string used to report an error;
```

outputRaw is a string used to report the raw output of calls to an external program or

call is a string used to report how targetEvaluator called an external program or function:

### 5.4 Training instances

The irace options trainInstancesDir and trainInstancesFile specify where to find the training instances. By default, the value of trainInstancesFile is empty. This means that irace will consider all files within the directory given by trainInstancesDir (by default ./Instances) as training instances.

Otherwise, the value of trainInstancesFile may specify a text file. The format of this file is one instance per line. Within each line, elements separated by white-space will be parsed as separate arguments to be supplied to targetRunner. This allows defining instance-specific parameter settings. Quoted strings will be parsed as a single argument. The following example shows a training instance file for the ACOTSP scenario:

```
# Example training instances file
100/100-1_100-2.tsp --time 1
100/100-1_100-3.tsp --time 2
100/100-1_100-4.tsp --time 3
```

Figure 3: Training instances file for tuning ACOTSP.

The value of trainInstancesDir is always prefixed to the instance name, that is, the instances names are treated as relative to this directory. For example, given the above file as trainInstancesFile and the default value of trainInstancesDir (./Instances), then a possible invocation of targetRunner would be:

```
target-runner 1 113 734718 ./Instances/100/100-1_100-2.tsp --time 1 \
--alpha 2.92 ...
```

Training instances do not need to be files, **irace** just passes the elements of each line as arguments to **targetRunner**, thus each line may denote the name of a benchmark function or a label, plus instance-specific settings, that the target algorithm understands. Each line may even be the command-line parameters required to call an instance generator within **targetRunner**. When the instances do not represent actual files, then **trainInstancesDir** is usually set to the empty string (--train-instances-dir=""). For example,

```
# Example training instances file
rosenbrock_20 --function=12 --nvar 20
rosenbrock_30 --function=12 --nvar 30
rastrigin_20 --function=15 --nvar 20
rastrigin_30 --function=15 --nvar 30
```

Optionally, when executing **irace** from the R console, the list of instances might be provided explicitly by means of the variable **scenario\$instances**. Thus, the previous example would be equivalent to:

By default, **irace** assumes that the target algorithm is stochastic (the value of the option **deterministic** is 0), thus, the same configuration can be executed more than once on the same instance and obtain different results. In this case, **irace** generates pairs (**instance,seed**) by generating a random seed for each instance. In other words, configurations evaluated on the same instance use the same random seed. This is a well-known variance reduction technique called *common random numbers* [9]. If all available pairs are used within a run of **irace**, new pairs are generated with different seeds, that is, a configuration evaluated more than once per instance will use different random seeds.

If deterministic is set to 1, then each instance will be used at most once per race. This setting should only be used for target algorithms that do not have a stochastic behavior and, therefore, executing the target algorithm on the same instance several times with different seeds does not make sense.



If deterministic is active and the number of training instances provided to **irace** is less than firstTest (default: 5), no statistical test will be performed on the race.

Finally, **irace** randomly re-orders the sequence of instances provided. This random sampling may be disabled by using the option **sampleInstances** (--sample-instances 0) if keeping the order provided in the instance file is important.



We advise to always sample instances to prevent biasing the tuning due to the instance order. See also Section 10.5

## 5.5 Initial configurations

The scenario option **configurationsFile** allows specifying a text file that contains an initial set of configurations to start the execution of **irace**. If the number of initial configurations supplied in the file is less than the number of configurations required by **irace** in the first iteration, additional configurations will be sampled uniformly at random.

The format of the configurations file is one configuration per line, and one parameter value per column. The first line must give the parameter name corresponding to each column (names must match those given in the parameters file). Each configuration must satisfy the parameter conditions (NA should be used for those parameters that are not enabled for a given configuration) and not be forbidden by the constraints that define forbidden configurations (Section 5.6), if any.

Figure 4 gives an example file that corresponds to the **ACOTSP** scenario.

```
## Initial candidate configuration for irace algorithm localsearch alpha beta rho ants nnls dlb q0 rasrank elitistants as 0 1.0 1.0 0.95 10 NA NA 0 NA NA
```

Figure 4: Initial configuration file (default.txt) for tuning ACOTSP.

We advise to use this feature when a default configuration of the target algorithm exists or when different sets of good parameter values are known. This will allow **irace** to start the search from those parameter values and attempt to improve their performance.

## 5.6 Forbidden configurations

The scenario option **forbiddenFile** specifies a text file containing logical expressions of parameter values that valid configurations should not satisfy, that is, no configuration that satisfies any of these logical expressions will be evaluated by **irace**. This is useful when some combination of parameter values could cause the target algorithm to crash, consume excessive CPU time or memory, or when it is known that they do no produce satisfactory results.

The format of the forbidden configurations file is one constraint per line, where each constraint is a logical expression (in R syntax) containing parameter names as defined by the parameterFile (Section 5.1), values and logical operators. For a list of R logical operators see:

```
https://stat.ethz.ch/R-manual/R-devel/library/base/html/Syntax.html
```

If a parameter configuration is generated that makes any of the logical expressions evaluate to TRUE, then the configuration is considered forbidden and it is discarded. Figure 5 shows an example file that corresponds to the **ACOTSP** scenario.

```
## Examples of valid logical operators are:
## == != >= <= > < & | ! %in%
(alpha == 0.0) & (beta == 0.0)</pre>
```

Figure 5: Forbidden configurations file (forbidden.txt) for tuning ACOTSP.



If initial configuration are provided (Section 5.5), they must also comply with the constraints defined in forbiddenFile.



Categorical and ordinal parameters are always treated as strings. Given a parameter like: a "" c (0, 5, 10, 20)

then, a condition like a > 10 will be true when a is 5, because comparisons between strings are lexicographic and "10" is sorted before "5". As a work-around, you can convert the string to numeric in the condition with as.numeric(a).

## 5.7 Repairing configurations

In some problems, the parameter values require complex constraints that cannot be implemented by constraints defined in forbiddenFile (Section 5.6). The scenario option repairConfiguration can be set to a user-defined R function that takes a single configuration generated by irace and returns a "repaired" configuration, thus allowing the implementation of any rules necessary to satisfy arbitrary constraints on parameter values. The repairConfiguration function is called after generating a configuration and before checking for forbidden configurations. The first argument is a 1-row data.frame with parameter names as the column names, the second argument is the parameters list (Section 5.1.5), and the third argument is the scenario variable digits. An example that makes all real-valued parameters sum up to one would be:

```
repairConfiguration = function (configuration, parameters, digits)
{
  isreal <- parameters$type[colnames(configuration)] %in% "r"
  configuration[isreal] <- configuration[isreal] / sum(configuration[isreal])
  return(configuration)
}</pre>
```

The following example forces three specific parameters to be in increasing order:

```
repairConfiguration = function (configuration, parameters, digits)
{
  columns <- c("p1","p2","p3")
  # cat("Before"); print(configuration)
  configuration[columns] <- sort(configuration[columns])
  # cat("After"); print(configuration)
  return(configuration)
}</pre>
```

The above code can be specified directly in the scenarioFile, by default scenario.txt.

## 6 Parallelization

A single run of **irace** can be done much faster by executing the calls to **targetRunner** (the runs of the target algorithm) in parallel. There are four ways to parallelize a single run of **irace**:

- 1. Parallel processes: The option parallel allows executing in parallel, within a single computer, the calls to targetRunner, by means of the parallel R package. For example, adding --parallel N to the command line of irace will launch in parallel up to N calls of the target algorithm.
- 2. MPI: By enabling the option mpi, calls to targetRunner will be executed in parallel by using the message passing interface (MPI) protocol (requires the Rmpi R package). In this case, the option parallel controls the number of slave nodes used by irace. For example, adding --mpi 1 --parallel N to the command-line will create N slaves + 1 master, and execute up to N calls of targetRunner in parallel.

The user is responsible for setting up the required MPI environment. MPI is commonly available in computing clusters and requires launching **irace** in some particular way. An example script for using MPI mode in a SGE cluster is given at **\$IRACE\_HOME/bin/parallel-irace-mpi**.

By default, **irace** dynamically balances the load among nodes, however, this may significantly increase communication overhead in some parallel environments, where disabling <code>loadBalancing</code> may be faster.

3. Batch jobs clusters: Some computing clusters work by submitting jobs to a batch queue and waiting for the jobs to finish. With the option batchmode (--batchmode [sge|pbs|torque|slurm]), irace will launch in parallel as many calls of targetRunner as possible (parallel can be used to set a limit) and use a cluster-specific method to wait for jobs to finish. If your cluster type is not supported or not working as expected, please contact us and we will gladly add support for it.



In this mode, **irace** must run in the submission node of the cluster, and hence, **irace** should not be submitted to the cluster as a job (that is, neither **qsub** nor **squeue** should be used to invoke **irace** itself). The user must call the appropriate job submission command (e.g., **qsub**) from within **targetRunner** with the appropriate settings for their cluster, otherwise **targetRunner** will not submit jobs to the cluster. The script must return a single string: The job ID that allows **irace** to determine the status of the running job. Moreover, the use of a separate **targetEvaluator** script is required to evaluate the results of **targetRunner** and return them to **irace**.

See the examples in **\$IRACE\_HOME**/examples/batchmode-cluster/.

4. targetRunnerParallel: This option allows users to fully control the parallelization of the execution of targetRunner. Its value must be an R function that will be invoked by irace as follows:

```
targetRunnerParallel(experiments, exec.target.runner, scenario, target.runner)
```

where scenario is the list describing the configuration scenario (Section 5); experiments is a list that describes the configurations and instances to be executed (see Section 5.2 for a description); target.runner is the function that calls the target algorithm and it is the same as targetRunner, if the latter is a function, or it is a call to target.runner.default, if targetRunner is the path to an executable; and exec.target.runner is an internal function within irace that takes care of executing target.runner, check its output and, possibly, retry in case of error (see targetRunnerRetries). The targetRunnerParallel function should call the given target.runner function for each element in the experiments list, possibly using exec.target.runner as a wrapper. A trivial example would be:

However, the user is free to set up the calls in any way, perhaps implementing its own replacement for target.runner and/or exec.target.runner.

The only requirement is that the targetRunnerParallel function must return a list of the same length as experiments, where each element is the output expected from the corresponding call to targetRunner (see Section 5.2). The following is an example of the output of a call to targetRunnerParallel with 2 experiments, in which the execution time is not reported:

```
print(output)

## [[1]]
## [[1]]$cost
## [1] 28319606
##
## [[1]]$time
## [1] NA
##
##
## [[2]]
## [[2]]$cost
## [1] 23684332
##
## [[2]]$time
## [1] NA
```

## 7 Testing (Validation) of configurations

Once the tuning process is finished, **irace** returns a set of configurations corresponding to the elite configurations at the end of the run, ordered from best to worst. In order to evaluate the generality of these configurations without looking at their performance on the training set, **irace** offers the possibility of evaluating these configurations on a test instance set, typically different from the training set used during the tuning phase. These evaluations will use the same settings for parallel execution, **targetRunner** and **targetEvaluator**.

The test instance set can be specified by the options testInstancesDir and testInstancesFile, or by setting directly the variable scenario\$testInstances, which behave the same as their counterparts for the training instances (Section 5.4). In particular, each test instance is assigned a different seed in the same way as done for the training instances. In principle, irace evaluates each configuration on each testing instance just once, because evaluating one run on n instances is always better than evaluating n' runs on n/n' instances [1]. However, if the number of instances is limited, one can always duplicate instances as needed in the testInstancesFile, and irace will assign a different random seed to each instance.

The options testNbElites and testIterationElites control which configurations are evaluated during the testing phase. In particular, setting testIterationElites = 1 will test not only the final set of elite configurations (those returned at the end of the training phase), but also the set of elites at the end of each race (iteration). The option testNbElites limits the maximum number of configurations considered within each set. Some examples:

- testIterationElites = 0; testNbElites = 1 means that only the best configuration found during the run of irace, the final best, will be used in the testing phase.
- testIterationElites = 1; testNbElites = 1 will test, in addition to the final best, the best configuration found at each iteration.
- testIterationElites = 1; testNbElites = 2 will test the two best configurations found at each iteration, in addition to the final best and second-best configurations.

The testing can be also (re-)executed at a later time by using the following R command:

```
testing.main(logFile = "./irace.Rdata")
```

The above line will load the scenario setup from logFile to perform the testing. The testing results will be stored in the R object iraceResults\$testing, which is saved in the file specified by scenario\$logFile. The structure of the object is described in Section 9.2. For examples on how to analyse the results see Section 9.3.

Another alternative is to test a specific set of configurations using the command-line option --only-test as follows:

```
irace --only-test configurations.txt
```

where configurations.txt has the same format as the set of initial configurations (Section 5.5).

## 8 Recovering irace runs

Problems like power cuts, hardware malfunction or the need to use computational power for other tasks may occur during the execution of **irace**, terminating a run before completion. At the end of each iteration, **irace** saves an R data file (logFile, by default "./irace.Rdata") that not

only contains information about the tuning progress (Section 9.2), but also internal information that allows recovering an incomplete execution.

To recover an incomplete **irace** run, set the option **recoveryFile** to the log file previously produced, and **irace** will continue the execution from the last saved iteration. The state of the random generator is saved and loaded, therefore, as long as the execution is continued in the same machine, the obtained results will be exactly the same as executing **irace** in one step (external factors, such as CPU load and disk caches, may affect the target algorithm and that may affect the results). You can specify the **recoveryFile** from the command-line or from the scenario file, and execute **irace** as described in Section 4. For example, from the command-line use:

irace --recovery-file "./irace-backup.Rdata"



When recovering a previous run, **irace** will try to save data on the file specified by the <code>logFile</code> option. Thus, you must specify different files for <code>logFile</code> and <code>recoveryFile</code>. Before recovering, we strongly advise to rename the saved R data file as in the example above, which uses <code>"irace-backup.Rdata"</code>.



Do not change anything in the log file or the scenario file before recovering, as it may have unexpected effects on the recovered run of **irace**. In case of doubt, please contact us first (Section 13). In particular, it is not possible to continue a run of **irace** by recovering with a larger budget. Results will **not** be the same as running **irace** from the start with the largest budget. An alternative is to use the final configurations from one run as the initial configurations of a new run.



If your scenario uses targetEvaluator (Section 5.3) and targetEvaluator requires files created by targetRunner, then recovery will fail if those files are not present in the execDir directory. This can happen, for example, if you recover from a different directory than the one from which irace was initially executed, or when execDir is set to a temporary directory for every irace run. Thus, you need to copy the contents of the previous execDir into the new one.

## 9 Output and results

During its execution, **irace** prints information about the progress of the tuning in the standard output. Additionally, after each iteration, an R data file is saved (logFile option) containing the state of **irace**.

#### 9.1 Text output

Figure 6 shows the output, up to the end of the first iteration, of a run of elitist **irace** applied to the **ACOTSP** scenario with 1000 evaluations as budget.

First, **irace** gives the user a warning informing that it has found a file with the default scenario filename and it will use it. Then, general information about the selected **irace** options is printed:

- nbIterations indicates the minimum number of iterations irace has calculated for the scenario. Depending on the development of the tuning the final iterations that are executed can be more.
- minNbSurvival indicates the minimum number of alive configurations that are required to continue a race. When less configurations are alive the race is stopped and a new iteration begins.

- nbParameters is the number of parameters of the scenario.
- seed is the number that was used to initialize the random number generator in irace.
- confidence level is the confidence level of the statistical test.
- budget is the total number of evaluations available for the tuning.
- time budget is the maximum execution time available for the tuning.
- mu is a value used for calculating the minimum number of iterations.
- deterministic indicates if the target algorithm is assumed to be deterministic.

At each iteration, information about the progress of the execution is printed as follows:

- experimentsUsedSoFar is the number of experiments from the total budget that have been used up to the current iteration.
- timeUsed is the execution time used so far in the experiments. Only available when reported in the targetRunner (activate it with the maxTime option).
- remainingBudget is the number of experiments that have not been used yet.
- timeEstimate estimation of the mean execution time. This is used to calculate the remaining budget when maxTime is used.
- currentBudget is the number of evaluations irace has allocated to the current iteration.
- nbConfigurations is the number of configurations irace will use in the current iteration. In the first iteration, this number of configurations include the initial configurations provided; in later iterations, it includes the elite configurations from the previous iterations.

After the iteration information, a table shows the progress of the iteration execution. Each row of the table gives information about the execution of an instance in the race. The first column contains a symbol that describes the results of the statistical test:

- |x| No statistical test was performed for this instance. The options firstTest and eachTest control on which instances the statistical test is performed.
- |-| Statistical test performed and configurations have been discarded. The column Alive gives an indication of how many configurations have been discarded.
- |=| Statistical test performed and no configurations have been discarded. This means **irace** needs to evaluate more instances to identify the best configurations.
- !! This indicator exists only for the elitist version of **irace**. It indicates that the statistical test was performed and some elite configurations appear to show bad performance and could be discarded but they are kept because of the elitist rules. See option **elitist** in Section 11 for more information.

Other columns have the following meaning:

Instance: Index of (instance, seed) pair executed. This number corresponds to the index of the list found in state\$.irace\$instancesList. See Section 9.2 for more information. This is different from the instance ID passed to targetRunner.

```
# irace: An implementation in R of (Elitist) Iterated Racing
# Version: 3.2.2215
# Copyright (C) 2010-2019
# Manuel Lopez-Ibanez
                              <manuel.lopez-ibanez@manchester.ac.uk>
# Jeremie Dubois-Lacoste
# Leslie Perez Caceres
                               <leslie.perez.caceres@ulb.ac.be>
# This is free software, and you are welcome to redistribute it under certain
  conditions. See the GNU General Public License for details. There is NO
# WARRANTY; not even for MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.
# irace builds upon previous code from the race package:
       race: Racing methods for the selection of the best
       Copyright (C) 2003 Mauro Birattari
# installed at: /home/manu/R/x86_64-pc-linux-gnu-library/3.4/irace
# called with: --parallel 2
Warning: A default scenario file './scenario.txt' has been found and will be read
# Adding 1 initial configuration(s) from file '/home/manu/work/irace/trunk/examples/vignette-example/default.txt' # 2019-04-04 11:52:51 BST: Initialization
# Elitist race
# Elitist new instances: 1
# Elitist limit: 2
# nbIterations: 5
# minNbSurvival: 5
# nbParameters: 11
# seed: 340101640
# confidence level: 0.95
# budget: 1000
# mu: 5
# deterministic: FALSE
# 2019-04-04 11:52:51 BST: Iteration 1 of 5
# experimentsUsedSoFar: 0
# remainingBudget: 1000
# currentBudget: 200
# nbConfigurations: 33
  Markers:
     x No test is performed.
      - The test is performed and some configurations are discarded.
      = The test is performed but no configuration is discarded.
      ! The test is performed and configurations could be discarded but elite configurations are preserved.
      . All alive configurations are elite and nothing is discarded
| | Instance | Alive | Best | Mean best | Exp so far | W time | rho | Ken W | Qvar |

        33|
        6|
        23254140.00|
        33|00:02:53|
        NA|
        NA|

        33|
        21|
        23206384.50|
        66|00:02:52|+0.96|0.98|0.0

        33|
        21|
        23237162.67|
        99|00:02:52|+0.95|0.97|0.0

        33|
        32|
        23266553.50|
        132|00:02:52|+0.97|0.97|0.0

        3|
        32|
        23246622.20|
        165|00:02:52|-0.05|0.16|0.6

               11
                                                                       66|00:02:52|+0.96|0.98|0.0069|
99|00:02:52|+0.95|0.97|0.0069|
132|00:02:52|+0.97|0.97|0.0069|
165|00:02:52| 0.05|0.45|
| x |
                21
IxI
               31
lx1
                41
                                                                            165|00:02:52|-0.05|0.16|0.6111|
1-1
               5|
                                            ---+--
Best-so-far configuration:
                                          32
                                                    mean value: 23246622.20
Description of the best-so-far configuration:
   .ID. algorithm localsearch alpha beta rho ants nnls q0 dlb n 32 acs 3 3.4899 9.9275 0.2071 42 10 0.0868 0
                                                                                  {\tt q0} dlb rasrank elitistants .PARENT.
                                                                                              NA
                                                                                                               NΑ
# 2019-04-04 12:07:15 BST: Elite configurations (first number is the configuration ID; listed from best to worst according to the sum of
   algorithm localsearch alpha beta rho ants nnls q0 dlb
acs 3 3.4899 9.9275 0.2071 42 10 0.0868 0
acs 3 4.2535 2.5375 0.6954 6 15 0.7730 1
acs 3 2.0533 2.1353 0.7127 25 20 0.7251 0
                                                                         q0 dlb rasrank elitistants
32
                                                                                          NΑ
                                                                                                         NΑ
21
                                                                                          NA
                                                                                                          NA
6
                                                                                          NA
                                                                                                          NA
# 2019-04-04 12:07:15 BST: Iteration 2 of 5
# experimentsUsedSoFar: 165
# remainingBudget: 835
# currentBudget: 208
```

Figure 6: Sample text output of **irace**.

Bound: Only when **capping** is enabled. Execution time used as bound for the execution of new candidate configurations.

Alive: Number of configurations that have not been discarded after the statistical test was performed.

Best: ID of the best configuration according to the instances seen so far in this race (i.e., not including previous iterations).

Mean best: Mean of the best configuration across the instances seen so far in this race.

Exp so far: Number of experiments performed so far.

W time: Wall-clock time spent on this instance.

rho, KenW, and Qvar: Spearman's rank correlation coefficient rho, Kendall's concordance coefficient W, and a variance measure described in [11], respectively, of the configurations across the instances evaluated so far in this iteration. These measures evaluate how consistent is the performance of the configurations across the instances. Values close to 1 for rho and KenW and values close to 0 for Qvar indicate that the scenario is highly homogeneous. For heterogeneous scenarios, we provide advice in Section 10.5.

Finally, **irace** outputs the best configuration found and a list of the elite configurations. The elite configurations are configurations that did not show statistically significant difference during the race; they are ordered according to their mean performance on the executed instances.

## 9.2 R data file (logFile)

The R data file created by **irace** (by default as **irace.Rdata**, see option **logFile**) contains an object called **iraceResults**. You can load this file in the R console with:

```
load("irace-acotsp.Rdata")
```

The iraceResults object is a list, and the elements of a list can be accessed in R by using the \$ or [[]] operators:

```
> iraceResults$irace.version
[1] "3.2.2215"
> iraceResults[["irace.version"]]
[1] "3.2.2215"
```

The iraceResults list contains the following elements:

- scenario: The scenario R object containing the **irace** options used for the execution. See Section 11 and the help of the **irace** package; open an R console and type: ?defaultScenario. See Section 11 for more information.
- parameters: The parameters R object containing the description of the target algorithm parameters. See Section 5.1.

• allConfigurations: The target algorithm configurations generated by irace. This object is a data frame, each row is a candidate configuration; the first column (.ID.) indicates the internal identifier of the configuration; the final column (.PARENT.) is the identifier of the configuration from which the current configuration was sampled; and the remaining columns correspond to the parameter values; each column is named as the parameter name specified in the parameter object.

```
> head(iraceResults$allConfigurations)
  .ID. algorithm localsearch alpha
                                      beta
                                              rho ants nnls
                                                                 q0
1
    1
             as
                          0 1.0000 1.0000 0.9500
                                                   10
                                                          NA
                                                                 NA
2
     2
                           1 3.0035 3.9421 0.3787
                                                    14
                                                          14
                                                                 NA
              as
3
     3
                           1 2.4189 2.7543 0.7737
                                                    10
                                                          6 0.0664
             acs
4
     4
                          1 4.6970 9.3580 0.0976
                                                    49
                                                          34
                                                                 NA
             ras
5
     5
             as
                          3 2.7316 6.7535 0.8776
                                                    26
                                                         41
                                                                 NA
                           3 2.0533 2.1353 0.7127
                                                    25
6
     6
                                                          20 0.7251
             acs
   dlb rasrank elitistants .PARENT.
1 <NA>
                                 NA
           NA
                       NA
2
                                 NA
    1
            NA
                        NA
3
    1
            NA
                        NA
                                 NA
4
            29
                        NA
                                 NA
     1
5
     0
            NA
                        NA
                                 NA
     0
                                 NA
```

• allElites: A list that contains one element per iteration. Each element contains the internal identifier of the elite candidate configurations of the corresponding iteration (identifiers correspond to allConfigurations\$.ID.).

```
> print(iraceResults$allElites)

[[1]]
[1] 32 21 6

[[2]]
[1] 32 21 6 35 43

[[3]]
[1] 32 78 64 21 35

[[4]]
[1] 110 95 64 112 32

[[5]]
[1] 129 133 110 95 135

[[6]]
[1] 140 133 129 110 142
```

The configurations are ordered by mean performance, that is, the ID of the best configuration corresponds to the first ID. To obtain the values of the parameters of all elite configurations found by **irace** use:

```
> getFinalElites(logFile = "irace-acotsp.Rdata", n = 0)
   .ID. algorithm localsearch alpha
                                                      q0
                                beta
                                       rho ants nnls
110 110 acs 3 1.6928 0.2335 0.4496 11 10 0.5141
129 129
                      3 1.4332 0.7319 0.3364 16 16 0.5681
          acs
                      3 1.6209 0.9782 0.7217 9 13 0.4398
133 133
          acs
140 140
           acs
                      3 1.2462 2.1628 0.2982 16 20 0.4988
142 142 acs 3 1.3394 0.8031 0.5894 7 15 0.4967
   dlb rasrank elitistants .PARENT.
   1 NA NA
110
                           64
                          110
129
   1
          NA
                   NA
133
   1
          NA
                   NA
                          110
                          129
140
   1
          NA
                    NA
                          133
142
          NA
                    NA
```

• iterationElites: A vector containing the best candidate configuration ID of each iteration. The best configuration found corresponds to the last one of this vector.

```
> print(iraceResults$iterationElites)
[1] 32 32 32 110 129 140
```

One can obtain the full configuration with:

```
> last <- length(iraceResults$iterationElites)
> id <- iraceResults$iterationElites[last]
> getConfigurationById(logFile = "irace-acotsp.Rdata", ids = id)

.ID. algorithm localsearch alpha beta rho ants nnls q0
140 140 acs 3 1.2462 2.1628 0.2982 16 20 0.4988
   dlb rasrank elitistants .PARENT.
140 1 NA NA 129
```

- rejectedConfigurations: A vector containing the rejected configurations IDs. These correspond to configurations that produced failed executions and were ignored by **irace** during the configuration process. See Section 10.8 to enable the detection of such configurations.
- experiments: A matrix with configurations as columns and instances as rows. Column names correspond to the internal identifier of the configuration (allConfigurations\$.ID.). The results of a particular configuration can be obtained using:

```
> # As an example, we use the best configuration found
> best.config <- getFinalElites(iraceResults = iraceResults, n = 1)
> id <- best.config$.ID.</pre>
```

```
> # Obtain the configurations using the identifier
> # of the best configuration
> all.exp <- iraceResults$experiments[,as.character(id)]</pre>
> all.exp[!is.na(all.exp)]
               2
                       3
                                4
                                         5
                                                  6
23231857 23115332 23271045 23382063 23162539 23217677 22838729
               9 10
                              11
                                        12
                                                 13
23136107 23018909 23357141 22904830 23228906 23231390 23104760
     15
23032760
```

When a configuration was not executed on an instance, its value is NA. A configuration may not be executed on an instance because: 1) it was not created yet when the instance was used, or 2) it was discarded by the statistical test and not executed on subsequent instances, or 3) the race terminated before this instance was considered.

Row names correspond to the identifier of the (instance, seed) pairs defined in state\$.irace\$instancesList. The instance and seed used for a particular experiment can be obtained with:

```
> # As an example, we get seed and instance of the experiments
> # of the best candidate.
> # Get index of the instances
> pair.id <- names(all.exp[!is.na(all.exp)])</pre>
> index <- iraceResults$state$.irace$instancesList[pair.id,"instance"]</pre>
> # Obtain the instance names
> iraceResults$scenario$instances[index]
 [1] "./instances/1000-4.tsp" "./instances/1000-3.tsp"
 [3] "./instances/1000-5.tsp" "./instances/1000-1.tsp"
 [5] "./instances/1000-2.tsp" "./instances/1000-9.tsp"
 [7] "./instances/1000-8.tsp" "./instances/1000-7.tsp"
 [9] "./instances/1000-6.tsp" "./instances/1000-10.tsp"
[11] "./instances/1000-8.tsp" "./instances/1000-4.tsp"
[13] "./instances/1000-9.tsp" "./instances/1000-3.tsp"
[15] "./instances/1000-6.tsp"
> # Get the seeds
> iraceResults$state$.irace$instancesList[index,"seed"]
 [1] 409467946 289477271 1676224743 1220261452 1659906086 1687160934
 [7] 1305346323 1827115271 216547899 1063134936 1305346323 409467946
[13] 1687160934 289477271 216547899
```

• experimentLog: A matrix with columns iteration, instance, configuration. This matrix contains the log of all the experiments that irace performs during its execution. The instance column refers to the index of the state\$.irace\$instancesList data frame. When capping is enabled a column bound is added to log the execution bound applied for each execution.

- softRestart: A logical vector that indicates if a soft restart was performed on each iteration. If FALSE, then no soft restart was performed. See option softRestart in Section 11.
- state: A list that contains the state of **irace**, the recovery (Section 8) is done using the information contained in this object. The probabilistic model of the last elite configurations can be found here by doing:

```
> # As an example, we get the model probabilities for the
> # localsearch parameter.
> iraceResults$state$model["localsearch"]
$localsearch
$localsearch$`129`
[1] 0.002061904 0.002061904 0.002061904 0.993814288
$localsearch$`133`
[1] 0.002061904 0.002061904 0.002061904 0.993814288
$localsearch$`110`
[1] 0.002061904 0.002061904 0.002061904 0.993814288
$localsearch$`95`
[1] 0.002061904 0.002061904 0.002061904 0.993814288
$localsearch$`135`
[1] 0.002061904 0.002061904 0.002061904 0.993814288
> # The order of the probabilities corresponds to:
> iraceResults$parameters$domain$localsearch
[1] "0" "1" "2" "3"
```

The example shows a list that has one element per elite configuration (ID as element name). In this case, localsearch is a categorical parameter and it has a probability for each of its values.

- testing: A list that contains the testing results. The list contains the following elements:
  - experiments: Matrix of experiments in the same format as the iraceResults\$experiments matrix. The column names indicate the candidate configuration identifier and the row names contain the name of the instances.

```
5t 23209025 23188063 23215787 23241732 23249566 23186894
6t 23405205 23442994 23374269 23446188 23375515 23380036
7t 23335011 23324526 23351169 23359563 23351186 23375381
8t 23262829 23263361 23228639 23234191 23281635 23213823
9t 23339334 23300092 23295216 23278792 23303729 23293629
10t 23061345 23032704 23094304 23095169 23024431 23032993
```

 seeds: The seeds used for the experiments, each seed corresponds to each instance in the rows of the test experiments matrix.

In the example, instance 1000-1.tsp is executed with seed 1391381798.

## 9.3 Analysis of results

The final configurations returned by **irace** are the elites of the final race. They are reported in decreasing order of performance, that is, the best configuration is reported first.

If testing is performed, you can further analyze the resulting best configurations by performing statistical tests in R or just plotting the results:

```
> results <- iraceResults$testing$experiments
> # Wilcoxon paired test
> conf <- gl(ncol(results), # number of configurations
            nrow(results), # number of instances
            labels = colnames(results))
> pairwise.wilcox.test (as.vector(results), conf, paired = TRUE, p.adj = "bonf")
Pairwise comparisons using Wilcoxon signed rank test
data: as.vector(results) and conf
   32 110 129 140 133
110 1 -
129 1 1
140 1 1
          1
133 1 1
         1 1
142 1 1
P value adjustment method: bonferroni
> # Plot the results
> configurationsBoxplot (results, ylab = "Solution cost")
```




Figure 7: Boxplot of the testing results of the best configurations.

During the tuning, **irace** iteratively updates the sampling models of the parameters to focus on the best regions of the parameter search space. The frequency of the sampled configurations can provide insights on the parameter search space. We provide a function for plotting the frequency of the sampling of a set of configurations. For more information on this function, please see the R help, type in the R console: <code>?parameterFrequency</code>. The following example plots the frequency of the parameters sampled during one **irace** run:

```
> parameterFrequency(iraceResults$allConfigurations, iraceResults$parameters)

Plotting: algorithm
Plotting: localsearch
Plotting: alpha
Plotting: beta
Plotting: rho
Plotting: ants
Plotting: nnls
Plotting: q0
Plotting: dlb
Plotting: rasrank
Plotting: elitistants
```

By using parallel coordinates plots, it is possible to analyze how the parameters interact with each other. For more information on this function, please see the R help, type in the R console: (?parallelCoordinatesPlot). The following example shows how to create a parallel coordinate plot of the configurations in the last two iterations of **irace**.




Figure 8: Parameters sampling frequency.

### Parameters parallel coordinates




Figure 9: Parallel coordinate plots of the parameters of the configurations in the last two iterations of a run of **irace**.

It is also possible to plot the performance on the test set of the best-so-far configuration over the number of experiments as follows:




Figure 10: Testing set performance of the best-so-far configuration over number of experiments. Label of each point is the configuration ID.

The **irace** package also provides an implementation of the ablation method [4]. See Section 10.9.

# 10 Advanced topics

### 10.1 Tuning budget

Before setting the budget for a run of **irace**, please consider the number of parameters that need to be tuned, available processing power and available time. The optimal budget depends on the difficulty of the tuning scenario, the size of the parameter space and the heterogeneity of the instances. Typical values range from 1 000 to 100 000 runs of the target algorithm, although smaller and larger values are also possible. Currently, **irace** does not detect whether the given budget allows generating all possible configurations. In such a case, the use of *iterated* racing is unnecessary: One can simply perform a single race of all configurations (see FAQ in Section 12.8).

Irace provides two options for setting the total tuning budget (maxExperiments and maxTime). The option maxExperiments limits the number of executions of targetRunner performed by irace. The option maxTime limits the total time of the targetRunner executions. When this latter option is used, targetRunner must return the evaluation cost together with the execution time ("cost time").



When the goal is to minimize the computation time of an algorithm, and you wish to use maxTime as the tuning budget, targetRunner must return the time also as the evaluation cost, that is, return the time two times as "time time".



When using targetEvaluator and using maxTime as tuning budget, targetRunner just returns the time ("time") and targetEvaluator returns the cost.

When using maxTime, irace estimates the execution time of each targetRunner execution before the configuration. The amount of budget used for the estimation is set with the option budgetEstimation (default is 2%). The obtained estimation is adjusted after each iteration using the obtained results and it is used to estimate the number of experiments that can be executed. Internally, irace uses the number of remaining experiments to adjust the number of configurations tested in each race.

### 10.2 Multi-objective tuning

Currently, **irace** only optimizes one cost value at a time, which can be solution cost, computation time or any other objective that is returned to **irace** by the **targetRunner**. If the target algorithm is multi-objective, it will typically return not a single cost value, but a set of objective vectors (typically, a Pareto front). For tuning such a target algorithm with **irace**, there are two alternatives. If the algorithm returns a single vector of objective values, they can be aggregated into one single number by using, for example, a weighted sum. Otherwise, if the target algorithm returns a set of objective vectors, a unary quality metric (e.g., the hypervolume) may be used to evaluate the quality of the set.<sup>3</sup>

The use of aggregation or quality metrics often requires normalizing the different objectives. If normalization bounds are known a priori for each instance, normalized values can be computed by targetRunner. Otherwise, the bounds may be dynamically computed while running irace, by using targetEvaluator. In this case, targetRunner will save the output of the algorithm, then

<sup>&</sup>lt;sup>3</sup>An implementation is publicly available at http://lopez-ibanez.eu/hypervolume [5]

the first call to targetEvaluator will examine the output produced by all calls to targetRunner for the same instance, update the normalization bounds and return the normalized output. Subsequent calls to targetEvaluator for the same instance will simply return the normalized output. A similar approach can be used to dynamically compute the reference points or sets often required by unary quality metrics.

For more information about defining a targetEvaluator, see Section 5.3. Examples of tuning a multi-objective target algorithm using the hypervolume can be found in the examples at \$IRACE\_HOME/examples/hypervolume and \$IRACE\_HOME/examples/moaco.

### 10.3 Tuning for minimizing computation time

When using **irace** for tuning algorithms that report computation time to reach a target, **targetRunner** should return the execution time of a configuration instead of solution cost.

Starting from version 3.0, **irace** includes an elitist racing procedure that implements an **adaptive capping mechanism** [10]. Adaptive capping [6] is a configuration technique that avoids the execution of long runs of the target algorithm, focusing the configuration budget in the evaluation of the best configurations found. This is done by bounding the execution time of each configuration based on the best performing candidate configurations.

To use adaptive capping, the capping option must be enabled and the elitist irace option must be selected. When evaluating candidate configurations on an instance, irace calculates an execution bound based on the execution times of the elite configurations. The boundType option defines how the performance of the elite configurations is defined to obtain the execution bound. The default value of boundType calculates the performance  $(p_i^s)$  of each elite configuration (s) as the mean execution time of the instances already executed in the race and the currently executed instance (i). The cappingType option specifies the measure used to obtain the elite configurations bound. By default, the execution bound is calculated as the median of the execution times of the elite configurations:

$$b_i = \mathrm{Median}_{\theta_s \in \Theta^{\mathrm{elite}}} \{ p_i^s \} \tag{1}$$

The execution bound for new configurations (j) is calculated by multiplying the elite configurations bound by the number of instances (i) in the execution list and subtracting the mean execution time of the instances executed by the candidate:

$$k_i^{'j} = b_i \cdot i + b^{\min} - p_{i-1}^j \cdot (i-1)$$
 (2)

A small constant  $b^{\min}$  is added to account for time measurements errors. These settings are also used to apply a dominance elimination criterion together with the statistical test elimination. The domination criterion is defined as:

$$b_i + b^{\min} < p_i^j \tag{3}$$

When elite configurations dominate new configurations, these are eliminated from the race.



The default statistical test when capping is enabled is t-test. This test is more appropriate to configure algorithms for optimizing runtime (see Section 10.6).

The execution bound is constantly adjusted by **irace** based on the best configurations times, nevertheless, a maximum execution time  $(b^{\text{max}})$  is never exceeded. This maximum execution time must be defined in the configuration scenario when **capping** is enabled. To specify the

maximum execution bound for the target runner executions use the **boundMax** option. The final execution bound  $(k_i^j)$  is calculated by:

$$k_{i}^{j} = \begin{cases} b^{\max} & \text{if } k_{i}^{'j} > b^{\max}, \\ \min\{b_{i}, b^{\max}\} & \text{if } k_{i}^{'j} \leq 0, \\ k_{i}^{'j} & \text{otherwise;} \end{cases}$$
(4)

Additionally, the **boundDigits** option defines the precision of the time bound provided by **irace**, the default setting is 0.

Timed out executions occur when the maximum execution bound (boundMax) is reached and the algorithm has not achieved successful termination or a defined quality goal. In this case, it is a common practice to apply a penalty known as PARX, in which timeouts are penalized by multiplying boundMax by a constant X. The constant X may be set using the boundPar option. Bounded executions are executions that do not achieve successful termination or a defined quality goal in the execution bound  $(k_i^j)$  set by irace, which is smaller than boundMax. The boundAsTimeout option replaces the evaluation of bounded executions by the boundMax value. More details about the implementation of adaptive capping can be found in Pérez Cáceres et al. [10].



Note that bounded executions are not timed out executions and thus, they will not be penalized by PARX.



Penalized evaluations of timed out and bounded executions are only used for the elimination tests and the comparison between the quality of configurations. To calculate execution bounds and computation budget consumed, **irace** uses only unpenalized execution times. The unpenalized execution time must be provided by the target runner or target evaluator as described in Section 5.2 and Section 5.3.

### 10.4 Hyper-parameter optimization of machine learning methods

The **irace** package can also be used for model selection and hyper-parameter optimization of machine learning methods. For such a task, we recommend the **mlr** package [3]. The following webpage documents how to use **irace** for this purpose: https://mlr-org.github.io/mlr-tutorial/devel/html/advanced\_tune/index.html

### 10.5 Heterogeneous scenarios

We classify a scenario as homogeneous when the target algorithm has a consistent performance regarding the instances; roughly speaking, good configurations tend to perform well and bad configurations tend to perform poorly on all instances of the problem. By contrast, in heterogeneous scenarios, the target algorithm has an inconsistent performance on different instances, that is, some configurations perform well for a subset of the instances, while they perform poorly for a different subset.

When facing a heterogeneous scenario, the first question should be whether the objective of tuning is to find configurations that perform reasonably well over all instances, even if they are not the best ones in any of them. If this is not the case, then it would be better to partition instances into more similar subsets and execute **irace** separately on each subset. This will lead to a portfolio of algorithm configurations, one for each subset, and algorithm selection techniques can be used to select the best configuration from the portfolio when facing a new instance.

If finding an overall good configuration for all the instances is the objective, then we recommend that instances are randomly sampled (option sampleInstances), unless one can provide the instances in a particular order that does not bias the tuning towards any subset. For example, let's assume a heterogeneous scenario with two classes of instances. If training instances are not sampled and the first ten instances belong to only one class, the tuning will be biased towards configurations that perform good for those instances. An optimal order would not ever present consecutively two instances of the same type.

In addition, it may be useful to increase the number of instances executed before doing a statistical test in order to see more instance classes before discarding configurations. The option elitistNewInstances in elitist irace (option elitist) can be used to increase the number of new instances executed in each iteration, e.g., --elitist-new-instances 5 (default value is 1). For the non-elitist irace, the option firstTest may be used for the same purpose, e.g., --first-test 10 (default value is 5).

While executing **irace**, the homogeneity of the scenario can be observed by examining the values of Spearman's rank correlation coefficient and Kendall's concordance coefficient in the text output of **irace**. See Section 9.1 for more information.

### 10.6 Choosing the statistical test

The statistical test used in **irace** identifies statistically bad performing configurations that can be discarded from the race in order to save budget. Different statistical tests use different criteria to compare the cost of the configurations, which has an effect on the tuning results.

**Irace** provides two types of statistical tests (option **testType**). Each test has different characteristics that are beneficial for different goals:

- Friedman test (F-test): This test uses the ranking of the configurations to analyze the differences between their performance. This makes the test suitable for scenarios where the numerical results and their scale are not significant to assess the cost of the configurations. For example, if the results for different instances have high numerical differences and evaluating the performance of the configurations using the mean could be deceiving. We recommend to use the F-test (default when capping is not enabled) when tuning for solution cost and whenever the best performing algorithm should be among the best in as many instances as possible.
- Student's t-test (t-test): This test uses the mean performance of the configurations to analyze the differences between the configurations. This makes the test suitable for scenarios where the differences between values obtained for different instances are relevant to assess good configurations. We recommend using t-test, in particular, when the target algorithm is minimizing computation time and, in general, whenever the best configurations should obtain the best average solution cost.

The confidence level of the tests may be adjusted by using the option **confidence**. Increasing the value of **confidence** leads to a more strict statistical test. Keep in mind that a stricter test will require more budget to identify which configurations perform worse. A less strict test discards configurations faster by requiring less evidence against them and, therefore, it is more likely to discard good configurations.

### 10.7 Complex parameter space constraints

Some parameters may have complex dependencies. Ideally, parameters should be defined in the way that is more likely to help the search performed by **irace**. For example, when tuning a branch

and bound algorithm, one may have the following parameters:

- branching (b) that takes values in {0,1,2,3}, where 0 indicates no branching will be used and the rest are different types of branching.
- stabilization (s) that takes values in  $\{0,1,2,3,4,5,6,7,8,9,10\}$ , of which for b=0 only  $\{0,1,2,3,4,5\}$  are relevant.

In this case, it is not possible to describe the parameter space by defining only two parameters for **irace**. An extra parameter must be introduced as follows:

# name	label	type	range	condition
b	"-b "	С	(0,1,2,3)	
s1	"-s "	С	(0,1,2,3,4,5)	b == "0"
s2	"-s "	С	(0,1,2,3,4,5,6,7,8,9,10)	b != "0"

Parameters whose values depend on the value of other parameters may also require using extra parameters or changing the parameters and processing them in **targetRunner**. For example, given the following parameters:

- Population size (p) takes the integer values [1, 100].
- Selection size (s) takes the same values but no more than the population size, that is [1,p].

In this case, it is possible to describe the parameters p and s using surrogate parameters for **irace** that represent a ratio of the original interval as follows:

```
# name label type range
p "-p" i (1,100)
s_f "-s" r (0.0,1.0)
```

and targetRunner must calculate the actual value of s as min(max(round( $s_f \cdot p, 1$ )), 100). For example, if the parameter p has value 50 and the surrogate parameter  $s_f$  has value 0.3, then s will have value 15.

The processing within targetRunner can also split and join parameters. For example, assume the following parameters:

```
# name label type range
m "-m" i (1,250)
e "-e" r (0.0,2.0)
```

These parameters could be used to define a value  $m \cdot 10^e$  for another parameter (--strength) not known by **irace**. Then, **targetRunner** takes care of parsing -m and -e, computing the strength value and passing the parameter --strength together with its value to the target algorithm.

More complex parameter space constraints may be implemented by means of the repairConfiguration function (Section 5.7).

# 10.8 Unreliable target algorithms and immediate rejection

There are some situations in which the target algorithm may fail to execute correctly. By default, **irace** stops as soon as a call to **targetRunner** or **targetEvaluator** fails, which helps to detect bugs in the target algorithm. Sometimes the failure cannot be fixed because it is due to system problems, network issues, memory limits, bugs for which no fix is available, or fixing them is impossible because there is no access to the source code.

In those cases, if the failure is caused by random errors or transient system problems, one may wish to ignore the error and try again the same call in the hope that it succeeds. The option targetRunnerRetries indicates the number of times a targetRunner execution is repeated if it fails. Use this option only if you know additional repetitions could be successful.

If the target algorithm consistently fails for a particular set of configurations, these configurations may be declared as forbidden (forbiddenFile) so that irace avoids them. On the other hand, if the configurations that cause the problem are unknown, the targetRunner should return Inf so that irace immediately rejects the failing configuration. This immediate rejection should be used with care according to the goals of the tuning. For example, a configuration that crashes on a particular instance, e.g., by running out of memory, might still be considered acceptable if it gives very good results on other instances. The configurations which were rejected during the execution of irace are saved in the Rdata output file (see Section 9.2).



If the configuration budget is specified in total execution time (maxTime option), immediate rejected executions must provide the cost and time (which must be Inf 0). Nevertheless, rejected configurations will be excluded from the execution time estimation and the execution bound calculation.

### 10.9 Ablation Analysis

The ablation method [4] takes two configurations (source and target) and generates a sequence of configurations that differ between each other just in one parameter, where parameter values in source are replaced by values from target. The sequence can be seen as a "path" from the source to the target configuration. This can be used to find new better "intermediate" configurations or to analyse the impact of the parameters in the performance. To perform ablation use the ablation function and specify the IDs of the source and target configurations. By default, the source is taken as the first configuration evaluated by **irace** and the target as the best overall configuration found. The argument ab.params can be used to specify a subset of the parameters considered in the ablation. The option firstTest defines how many instances are selected for the evaluation of configurations, if a different number of instances is required it must be specified in the argument n.instance. If a PDF filename is provided (pdf.file), a plot will be produced from the ablation results (Fig. 11).

The function returns a list containing the following elements:

configurations: A dataframe of configurations tested during ablation.

instances: The instances used for the ablation.

scenario: Scenario options provided by the user.

trajectory: Best configuration IDs at each step of the ablation.

best: Best overall configuration found.




Figure 11: Example of plot generated by ablation().

### 10.10 Postselection race

After the configuration process is finished it is possible perform a postselection race by specifying the **irace** option **postselection** with value larger than 0. This option will perform a post-selection race of the set of best configurations of each iteration. The budget assigned for this race is obtained using the **postselection** option which defines a percentage of the **irace** configuration budget. This budget is not considered in the total configuration budget that is, these evaluations are extra computation.

The execution of the postselection race add an element (psrace.log) to the iraceResults list saved in the irace log file. The postselection log consists of a list with the following elements:

configurations: Configurations used in the postselection race.

instances: Instances used in the in the postselection race.

maxExperiments: Configuration budget assigned for the postselection race.

experiments: Matrix of experiments in the same format as the iraceResults\$experiments matrix. The column names indicate the candidate configuration identifier and the row names contain the name of the instances.

elites: Elite configurations obtained in the postselection race.

Optionally, it is possible to perform a postselection race with all elite configurations of the iterations or selecting a set of configurations from iraceResults\$allConfigurations.

# 11 List of command-line and scenario options

Most **irace** options can be specified in the command line using a flag or in the **irace** scenario file using the option name (or setting their value in the **scenario** list passed to the various R functions exported by the package). This section describes the various **irace** options that can be specified by the user in this way.



Relative filesystem paths (e.g., ../scenario/) given in the command-line are relative to the current working directory (the directory at which **irace** is invoked). However, paths given in the scenario file are relative to the directory containing the scenario file. See also Table 1.

### 11.1 General options

--help flag: -h or --help default:
Show the list of command-line options of irace.

--version flag: -v or --version default: Show the version of irace.

--check flag: -c or --check default:

Check that the scenario and parameter definitions are correct and test the execution of the target algorithm. See Section 4.

scenarioFile flag: -s or --scenario default: ./scenario.txt

File that contains the scenario setup and other irace options. All options listed in this section can be included in this file. See **\$IRACE\_HOME/templates/** for an example. Relative file-system paths specified in the scenario file are relative to the scenario file itself.

```
execDir flag: --exec-dir default: ./
```

Directory where the target algorithm executions will be performed. The default execution directory is the current directory.



The execution directory must exist before executing **irace**, it will not be created automatically.

```
logFile flag: -l or --log-file default: ./irace.Rdata
```

File to save tuning results as an R dataset. The provided path must be either an absolute path or relative to execDir. See Section 9.2 for details on the format of the R dataset.

debugLevel flag: --debug-level default: 0

Level of information to display in the text output of **irace**. A value of 0 silences all debug messages. Higher values provide more verbose debug messages. Details about the text output of **irace** are given in Section 9.1.

seed flag: --seed default:

Seed to initiallize the random number generator. The seed must be a positive integer. If the seed is "" or NULL, a random seed will be generated.

repairConfiguration default:

User-defined R function that takes a configuration generated by **irace** and repairs it. See Section 5.7 for details.

postselection flag: --postselection default: 0

Percentage of the configuration budget used to perform a postselection race of the best configurations of each iteration after the execution of **irace**. See Section 10.10.

aclib flag: --aclib default: 0

Enable/disable AClib mode. This option enables compatibility with GenericWrapper4AC (https://github.com/automl/GenericWrapper4AC/) as targetRunner script.

### 11.2 Elitist irace

 ${\it elitist} \quad \textit{flag: -e} \quad \textit{or} \quad \textit{--elitist} \quad \textit{default: 1}$ 

Enable/disable elitist irace.

In the **elitist** version of **irace** [8], elite configurations are not discarded from the race until non-elite configurations have been executed on the same instances as the elite configurations.

Each race begins by evaluating all configurations on a number of new instances. This number is defined by the option <code>elitistNewInstances</code>. After the new instances have been evaluated, configurations are evaluated on instances seen in the previous race. Elite configurations already have results for most of these previous instances and, therefore, do not need to be re-evaluated. Finally, after configurations have been evaluated on all these instances, the race continues by evaluating additional new instances.

The statistical tests can be performed at any moment during the race according to the setting of the options firstTest and eachTest. The elitist rule forbids discarding elite configurations, even if the show poor performance, until the last of the previous instances is seen in the race.

The **non-elitist** version of **irace** can discard elite configurations at any point of the race, instances are not re-used from one race to the next, and new instances are sampled for each race.

elitistNewInstances flag: --elitist-new-instances default: 1

Number of new instances added to each race before evaluating instances from previous races (only for elitist **irace**).



If deterministic is TRUE then the number of elitistNewInstances will be reduced or set to 0 once all instances have been evaluated.

### elitistLimit flag: --elitist-limit default: 2

Maximum number of statistical tests performed without successful elimination after all instances from the previous race have been evaluated. If the limit is reached, the current race is stopped. Only valid for elitist **irace**. Use 0 to disable the limit.

### 11.3 Internal irace options

### nbIterations flag: --iterations default: 0

Minimum number of iterations to be executed. Each iteration involves the generation of new configurations and the use of racing to select the best configurations. By default (with 0), **irace** calculates the minimum number of iterations as  $N^{\text{iter}} = \lfloor 2 + \log_2 N^{\text{param}} \rfloor$ , where  $N^{\text{param}}$  is the number of non-fixed parameters to be tuned. We recommend to use the default value.

# ${\tt nbExperimentsPerIteration} \qquad \textit{flag: --} {\tt experiments-per-iteration} \qquad \textit{default: } {\tt Optimization}$

Number of runs of the target algorithm per iteration. By default (when equal to 0), this value changes for each iteration and depends on the iteration index and the remaining budget. Further details are provided in the **irace** paper [8]. We recommend to use the default value.

### sampleInstances flag: --sample-instances default: 1

Enable/disable the sampling of the training instances. If the option sampleInstances is disabled, the instances are used in the order provided in the trainInstancesFile or in the order they are read from the trainInstancesDir whentrainInstancesFile is not provided. For more information about training instances see Section 5.4.

### minNbSurvival flag: --min-survival default: 0

Minimum number of configurations needed to continue the execution of each race (iteration). If the number of configurations alive in the race is not larger than this value, the current iteration will stop and a new iteration will start, even if there is budget left to continue the current race. By default (when equal to 0), the value is calculated automatically as  $\lfloor 2 + \log_2 N^{\mathrm{param}} \rfloor$ , where  $N^{\mathrm{param}}$  is the number of non-fixed parameters to be tuned.

### nbConfigurations flag: --num-configurations default: 0

The number of configurations that will be raced at each iteration. By default (when equal to 0), this value changes for each iteration and depends on nbExperimentsPerIteration, the iteration index and mu. The precise details are given in the irace paper [8]. We recommend to use the default value.

### mu flag: --mu default: 5

Parameter used to define the number of configurations to be sampled and evaluated at each iteration. The number of configurations will be calculated such that there is enough budget in each race to evaluate all configurations on at least  $\mu + \min(5, j)$  training instances, where j is the index of the current iteration. The value of  $\mu$  will be adjusted to never be lower than the value of firstTest. We recommend to use the default value and, if needed, adjust firstTestand eachTest, instead.

### softRestart flag: --soft-restart default: 1

Enable/disable the soft-restart strategy that avoids premature convergence of the probabilistic model. When a sampled configuration is similar to its parent configuration, the probabilistic model of these configurations is soft restarted. The soft-restart mechanism is

explained in the **irace** paper [8]. The similarity of categorical and ordinal parameters is given by the hamming distance, and the option **softRestartThreshold** defines the similarity of numerical parameters.

softRestartThreshold flag: --soft-restart-threshold default:

Soft restart threshold value for numerical parameters. By default, it is computed as  $10^{-digits}$ , where digits corresponds to the **irace** option explained in this section.

# 11.4 Target algorithm parameters

parameterFile flag: -p or --parameter-file default: ./parameters.txt File that contains the description of the parameters of the target algorithm. See Section 5.1.

forbiddenFile flag: --forbidden-file default:

File containing a list of logical expressions that cannot be true for any evaluated configuration. If empty or NULL, no forbidden configurations are considered. See Section 5.6 for more information.

 ${\tt digits} \quad \textit{flag: --digits} \quad \textit{default: 4} \\$ 

Maximum number of decimal places that are significant for numerical (real) parameters.

### 11.5 Target algorithm execution

targetRunner flag: --target-runner default: ./target-runner

This option defines a script or an R function that evaluates a configuration of the target algorithm on a particular instance. See Section 5.2 for details.

targetRunnerRetries flag: --target-runner-retries default: 0

Number of times to retry a call to targetRunner if the call failed.

targetRunnerData default:

Optional data passed to targetRunner. This is ignored by the default targetRunner function, but it may be used by custom targetRunner functions to pass persistent data around.

targetRunnerParallel default:

Optional R function to provide custom parallelization of targetRunner. See Section 6 for more information.

targetEvaluator flag: --target-evaluator default:

Optional script or R function that returns a numerical value for an experiment after all configurations have been executed on a given instance using targetRunner. See Section 5.3 for details.

deterministic flag: --deterministic default: 0

Enable/disable deterministic target algorithm mode. If the target algorithm is deterministic, configurations will be evaluated only once per instance. See Section 5.4 for more information.



If the number of instances provided is less than the value specified for the option firstTest, no statistical test will be performed.

parallel flag: --parallel default: 0

Number of calls of the targetRunner to execute in parallel. Values 0 or 1 mean no parallelization. For more information on parallelization, see Section 6.

loadBalancing flag: --load-balancing default: 1

Enable/disable load-balancing when executing experiments in parallel. Load-balancing makes better use of computing resources, but increases communication overhead. If this overhead is large, disabling load-balancing may be faster. See Section 6.

mpi flag: --mpi default: 0

Enable/disable use of **Rmpi** to execute the **targetRunner** in parallel using MPI protocol. When **mpi** is enabled, the option **parallel** is the number of slave nodes. See Section 6.

batchmode flag: --batchmode default: 0

Specify how irace waits for jobs to finish when targetRunner submits jobs to a batch cluster: sge, pbs, torque or slurm (targetRunner must submit jobs to the cluster using. for example, qsub). See Section 6.

### 11.6 Initial configurations

configurationsFile flag: --configurations-file default:

File containing a list of initial configurations. If empty or  $\mathtt{NULL}$ , **irace** will not use initial configurations. See Section 5.5.



The provided configurations must not violate the constraints described in parameterFile and forbiddenFile.

### 11.7 Training instances

trainInstancesDir flag: --train-instances-dir default: ./Instances

Directory where training instances are located; either absolute path or relative to current directory. See Section 5.4.

trainInstancesFile flag: --train-instances-file default:

File that contains a list of instances and optionally additional parameters for them. See Section 5.4.



The list of instances in trainInstancesFile is interpreted as file-system paths relative to trainInstancesDir. When using an absolute path or instances that are not files, set trainInstancesDir="".

# 11.8 Tuning budget

maxExperiments flag: --max-experiments default: 0

The maximum number of runs (invocations of targetRunner) that will be performed. It determines the maximum budget of experiments for the tuning. See Section 10.1.

maxTime flag: --max-time default: 0

The maximum total time in seconds for the runs of targetRunner that will be performed. The mean execution time of each run is estimated in order to calculate the maximum

number of experiments (see option budgetEstimation). When maxTime is positive, then targetRunner must return the execution time as its second output. See Section 10.1.

budgetEstimation flag: --budget-estimation default: 0.02

Fraction (smaller than 1) of the budget used to estimate the mean execution time of a configuration. Only used when maxTime > 0. See Section 10.1.

### 11.9 Statistical test

testType flag: --test-type default: F-test Specifies the statistical test used for elimination:

F-test (Friedman test)

t-test (pairwise t-tests with no correction)

t-test-bonferroni (t-test with Bonferroni's correction for multiple comparisons)

t-test-holm (t-test with Holm's correction for multiple comparisons).

We recommend to not use corrections for multiple comparisons because the test typically becomes too strict and the search stagnates. See Section 10.6 for details about choosing the statistical test most appropriate for your scenario.



The default setting of testType is F-test unless the capping option is enabled in which case, the default setting is defined as t-test.

firstTest flag: --first-test default: 5

Specifies how many instances are evaluated before the first elimination test.



The value of firstTest must be a multiple of eachTest.

eachTest flag: --each-test default: 1

Specifies how many instances are evaluated between elimination tests.

confidence flag: --confidence default: 0.95 Confidence level for the elimination test.

### 11.10 Adaptive capping

capping flag: --capping default: 0

Enable the use of adaptive capping. This option is only available when **elitist** is active. When using this option, **irace** provides an execution bound to each target algorithm execution (See Section 5.2). For more details about this option See Section 10.3.

cappingType flag: --capping-type default: median

Specifies the measure used to define the execution bound:

median (the median of the performance of the elite configurations)

mean (the mean of the performance of the elite configurations)

best (the best performance of the elite configurations)

worst (the worst performance of the elite configurations).

boundType flag: --bound-type default: candidate

Specifies how to calculate the performance of elite configurations for the execution bound:

candidate (performance of candidates is aggregated across the instances already executed)

instance (performance of candidates on each instance).

boundMax flag: --bound-max default: 0

Maximum execution bound for targetRunner. It must be specified when capping is enabled.

 ${\tt boundDigits} \quad \textit{flag: --bound-digits} \quad \textit{default: 0}$ 

Precision used for calculating the execution time. It must be specified when capping is enabled.

boundPar flag: --bound-par default: 1

Penalty used for PARX. This value is used to penalize timed out executions, see Section 10.3.

boundAsTimeout flag: --bound-as-timeout default: 1

Replace the configuration cost of bounded executions with boundMax. See Section 10.3.

### 11.11 Recovery

recoveryFile flag: --recovery-file default:

Previously saved **irace** log file that should be used to recover the execution of **irace**; either absolute path or relative to the current directory. If empty or NULL, recovery is not performed. For more details about recovery, see Section 8.

### 11.12 Testing

--only-test flag: --only-test default:

Run the configurations contained in the file provided as argument on the test instances. See Section 7.

testInstancesDir flag: --test-instances-dir default:

Directory where testing instances are located, either absolute or relative to the current directory.

testInstancesFile flag: --test-instances-file default:

File containing a list of test instances and, optionally, additional parameters for them.

testNbElites flag: --test-num-elites default: 1

Number of elite configurations returned by irace that will be tested if test instances are provided. For more information about the testing, see Section 7.

 ${\tt testIterationElites} \qquad \textit{flag: --test-iteration-elites} \qquad \textit{default: 0}$ 

Enable/disable testing the elite configurations found at each iteration.

# 12 FAQ (Frequently Asked Questions)

### 12.1 Is irace minimizing or maximizing the output of my algorithm?

By default, **irace** considers that the value returned by **targetRunner** (or by **targetEvaluator**, if used) should be **minimized**. In case of a maximization problem, one can simply multiply the value by -1 before returning it to irace. This is done, for example, when maximizing the hypervolume (see the last lines in **\$IRACE\_HOME/examples/hypervolume/target-evaluator**).

### 12.2 Is it possible to configure a MATLAB algorithm with irace?

Definitely. There are three main ways to achieve this:

- Edit the targetRunner script to call MATLAB in a non-interactive way. See the MATLAB documentation, or the following links.<sup>45</sup> You would need to pass the parameter received by targetRunner to your MATLAB script.<sup>67</sup> There is a minimal example in \$IRACE\_HOME/examples/matlab/.
- Call MATLAB code directly from R using the matlabr package (https://cran.r-project. org/package=matlabr). This is a better option if you are experienced in R. Define targetRunner as an R function instead of a path to a script. The function should call your MATLAB code with appropriate parameters.
- 3. Another possibility is calling MATLAB directly from a different programming language and write targetRunner in that programming language, for example, in Python (see examples in \$IRACE\_HOME/examples/target-runner-python/).8

# 12.3 My program works perfectly on its own, but not when running under irace. Is irace broken?

Every time this was reported, it was a difficult-to-reproduce bug, i.e., a Heisenbug, in the program (target algorithm), not in **irace**. To detect such bugs, we recommend that you use, within targetRunner, a memory debugger (e.g., valgrind) to run your program. For example, if your program is executed by targetRunner as:

```
${EXE} ${FIXED_PARAMS} -i ${INSTANCE} ${CONFIG_PARAMS} 1> ${STDOUT} 2> ${STDERR}
```

then replace that line with:

```
valgrind --error-exitcode=1 ${EXE} ${FIXED_PARAMS} -i ${INSTANCE} \
    ${CONFIG_PARAMS} 1> ${STDOUT} 2> ${STDERR}
```

 $<sup>^4 \</sup>verb|http://stackoverflow.com/questions/1518072/suppress-start-message-of-matlab|$ 

 $<sup>^5</sup> http://stackoverflow.com/questions/4611195/how-to-call-matlab-from-command-line-and-print-to-stdout-before-exiting$ 

 $<sup>^6</sup> https://www.mathworks.com/matlabcentral/answers/97204-how-can-i-pass-input-parameters-when-running-matlab-in-batch-mode-in-windows$ 

 $<sup>^{7}</sup> https://stackoverflow.com/questions/3335505/how-can-i-pass-command-line-arguments-to-a-standalone-matlab-executable-running$ 

<sup>8</sup>https://www.mathworks.com/help/matlab/matlab\_external/call-matlab-functions-from-python.html https://www.mathworks.com/help/matlab/matlab\_external/call-user-script-and-function-from-python.html

If there are bugs in your program, they will appear in \$STDERR, thus do not delete those files. Memory debuggers will significantly slowdown your code, so use them only as a means to find what is wrong with your target algorithm. Once you have fixed the bugs, you should remove the use of valgrind.

# 12.4 My program may be buggy and run into an infinite loop. Is it possible to set a maximum timeout?

We are not aware of any way to achieve this using R. However, in GNU/Linux, it is easy to implement by using the timeout command in targetRunner when invoking your program.

# 12.5 When using the mpi option, irace is aborted with an error message indicating that a function is not defined. How to fix this?

Rmpi does not work the same way when called from within a package and when called from a script or interactively. When irace creates the slave nodes, the slaves will load a copy of irace automatically. If the slave nodes are on different machines, they must have irace installed. If irace is not installed system-wide, R needs to be able to find irace on the slave nodes. This is usually done by setting R\_LIBS, .libPaths() or by loading irace using library() or require() with the argument "lib.loc". The settings on the master are not applied to the slave nodes automatically, thus the slave nodes may need their own settings. After spawning the slaves, it is too late to modify those settings, thus modifying the shell variable R\_LIBS seems the only valid way to tell the slaves where to find irace.

If the path is set correctly and the problem persists, please check these instructions:

- 1. Test that **irace** and **Rmpi** work. Run **irace** on a single machine (submit node), without calling qsub, mpirun or a similar wrapper around **irace** or R.
- 2. Test loading **irace** on the slave nodes. However, jobs submitted by **qsub/mpirun** may load R packages using a different mechanism from the way it happens if you log directly into the node (e.g., with **ssh**). Thus, you need to write a little R program such as:

```
library(Rmpi)
mpi.spawn.Rslaves(nslaves = 10)
paths <- mpi.applyLB(1:10, function(x) {
    library(irace); return(path.package("irace")) })
print(paths)</pre>
```

Submit this program to the cluster like you would submit **irace** (using qsub, mpirun or whatever program is used to submit jobs to the cluster).

3. In the script bin/parallel-irace-mpi, the function irace\_main() creates an MPI job for our cluster. You may need to speak with the admin of your cluster and ask them how to best submit a job for MPI. There may be some particular settings that you need. Rmpi normally creates log files; but irace suppresses those files unless debugLevel > 0.

Please contact us (Section 13) if you have further problems.

### 12.6 Error: 4 arguments passed to .Internal(nchar) which requires 3

This is a bug in R 3.2.0 on Windows. The solution is to update your version of R.

### 12.7 How are relative filesystem paths interpreted by irace?

The answer depends on where the path appears. Relative paths may appear as the argument of command-line options, as the value of options given in the scenario file, or within various scripts, functions or instance files. Table 1 summarizes how paths are translated from relative to absolute.

Table 1: Translation of relative to absolute filesystem paths.

Relative path appears as	is relative to			
a string within trainInstancesFile	trainInstancesDir			
a string within testInstancesFile	testInstancesDir			
code within targetRunner or targetEvaluator	execDir			
the value of logFile orlog-file	execDir			
the value of other options in the scenario file the value of other command-line options	the directory containing the scenario file invocation (working) directory of <b>irace</b>			
the varie of other command line options	mrocation (morning) antectory of nace			

# 12.8 My parameter space is small enough that irace could generate all possible configurations; however, irace generates repeated configurations and/or does not generate some of them. Is this a bug?

Currently, **irace** does not try to detect whether all possible configurations can be evaluated for the given budget, thus, the initial random sampling performed by **irace** may generate repeated configurations and/or never generate some configurations, which is not ideal. The ideal approach in such cases is to provide all configurations explicitly to **irace** (Section 5.5) and execute a single race (nbIterations=1). Hopefully, a future version of **irace** will automatically detect this case and switch to basic racing.

### 13 Resources and contact information

More information about the package can be found on the **irace** webpage:

```
http://iridia.ulb.ac.be/irace/
```

For questions and suggestions please contact the development team through the **irace** package Google group:

```
https://groups.google.com/d/forum/irace-package
```

or by sending an email to:

 $irace\hbox{-}package@googlegroups.com$ 

# 14 Acknowledgements

We would like to thank all the people that directly or indirectly have collaborated in the development and improvement of **irace**: Prasanna Balaprakash, Zhi (Eric) Yuan, Franco Mascia, Alberto Franzin, Anthony Antoun, Esteban Diaz Leiva, Federico Caselli, Pablo Valledor Pellicer, and André de Souza Andrade.

# Bibliography

- [1] M. Birattari. On the estimation of the expected performance of a metaheuristic on a class of instances, how many instances, how many runs? Technical Report TR/IRIDIA/2004-001, IRIDIA, Université Libre de Bruxelles, Belgium, 2004.
- [2] M. Birattari, Z. Yuan, P. Balaprakash, and T. Stützle. F-race and iterated F-race: An overview. In T. Bartz-Beielstein, M. Chiarandini, L. Paquete, and M. Preuss, editors, Experimental Methods for the Analysis of Optimization Algorithms, pages 311–336. Springer, Berlin, Germany, 2010.
- [3] B. Bischl, M. Lang, J. Bossek, L. Judt, J. Richter, T. Kuehn, and E. Studerus. *mlr: Machine Learning in R*, 2013. URL http://cran.r-project.org/package=mlr. R package.
- [4] C. Fawcett and H. H. Hoos. Analysing differences between algorithm configurations through ablation. *Journal of Heuristics*, 22(4):431–458, 2016.
- [5] C. M. Fonseca, L. Paquete, and M. López-Ibáñez. An improved dimension-sweep algorithm for the hypervolume indicator. In *Proceedings of the 2006 Congress on Evolutionary Computation (CEC 2006)*, pages 1157–1163. IEEE Press, Piscataway, NJ, July 2006. doi: 10.1109/CEC.2006.1688440.
- [6] F. Hutter, H. H. Hoos, K. Leyton-Brown, and T. Stützle. ParamILS: an automatic algorithm configuration framework. *Journal of Artificial Intelligence Research*, 36:267–306, Oct. 2009.
- [7] M. López-Ibáñez, J. Dubois-Lacoste, T. Stützle, and M. Birattari. The irace package, iterated race for automatic algorithm configuration. Technical Report TR/IRIDIA/2011-004, IRIDIA, Université Libre de Bruxelles, Belgium, 2011. URL http://iridia.ulb.ac.be/IridiaTrSeries/IridiaTr2011-004.pdf.
- [8] M. López-Ibáñez, J. Dubois-Lacoste, L. Pérez Cáceres, T. Stützle, and M. Birattari. The irace package: Iterated racing for automatic algorithm configuration. *Operations Research Perspectives*, 3:43–58, 2016. doi: 10.1016/j.orp.2016.09.002.
- [9] C. C. McGeoch. Analyzing algorithms by simulation: Variance reduction techniques and simulation speedups. *ACM Computing Surveys*, 24(2):195–212, 1992. doi: 10.1145/130844. 130853.
- [10] L. Pérez Cáceres, M. López-Ibáñez, H. H. Hoos, and T. Stützle. An experimental study of adaptive capping in irace. In R. Battiti, D. E. Kvasov, and Y. D. Sergeyev, editors, Learning and Intelligent Optimization, 11th International Conference, LION 11, volume 10556 of Lecture Notes in Computer Science, pages 235–250. Springer, Cham, Switzerland, 2017. doi: 10.1007/978-3-319-69404-7\_17.
- [11] M. Schneider and H. H. Hoos. Quantifying homogeneity of instance sets for algorithm configuration. In Y. Hamadi and M. Schoenauer, editors, Learning and Intelligent Optimization, 6th International Conference, LION 6, volume 7219 of Lecture Notes in Computer Science, pages 190–204. Springer, Heidelberg, Germany, 2012. doi: 10.1007/978-3-642-34413-8\_14.

# Appendix A Installing R

This section gives a quick R installation guide that will work in most cases. The official instructions are available at https://cran.r-project.org/doc/manuals/r-release/R-admin.html

# A.1 GNU/Linux

You should install R from your package manager. On a Debian/Ubuntu system it will be something like:

```
sudo apt-get install r-base
```

Once R is installed, you can launch R from the Terminal and from the R prompt install the **irace** package (see Section 3.2).

### A.2 OS X

You can install R directly from a CRAN mirror.<sup>9</sup> Alternatively, if you use homebrew, you can just brew the R formula from the science tap (unfortunately it does not come already bottled so you need to have Xcode<sup>10</sup> installed to compile it):

```
brew tap homebrew/science
brew install r
```

Once R is installed, you can launch R from the Terminal (or from your Applications), and from the R prompt install the **irace** package (see Section 3.2).

### A.3 Windows

You can install R from a CRAN mirror.<sup>11</sup> We recommend that you install R on a filesystem path without spaces, special characters or long names, such as C:\R. Once R is installed, you can launch the R console and install the **irace** package from it (see Section 3.2).

# Appendix B targetRunner troubleshooting checklist

If the targetRunner script fails to return the output expected by irace, it can be sometimes difficult to diagnose where the problem lies. The more descriptive errors provided by your script, the easier it will be to debug it. If targetRunner enters an infinite loop, irace will wait indefinitely (see FAQ in Section 12.4). If you are using temporary files to redirect the output of your algorithm, check that these files are properly created. We recommend to follow the structure of the example file (target-runner) provided in \$IRACE\_HOME/templates. The following error examples are based on that example file.

In case of failure of targetRunner, irace will print an error on its output describing which execution of targetRunner failed. Follow this checklist to detect where the problem is:

1. Make sure that your targetRunner script or program is at the specified location. If you see this error:

<sup>9</sup>https://cran.r-project.org/bin/macosx/

<sup>10</sup>Xcode download webpage: https://developer.apple.com/xcode/download/

<sup>11</sup>https://cran.r-project.org/bin/windows/

Error: == irace == target runner '~/tuning/target-runner' does not exist

it means that **irace** cannot find the target-runner file. Check that the file is at the path specified by the error.

2. Make sure that your targetRunner script is an executable file and the user running irace has permission to execute it. The following errors:

```
Error: == irace == target runner '~/tuning/target-runner' is a directory,
not a file
```

or

```
Error: == irace == target runner '~/tuning/target-runner' is not executable
```

mean that your targetRunner is not an executable file. In the first case, the script is a folder and therefore there must be a problem with the name of the script. In the second case, you must make the file executable, which in GNU/Linux can be done by:

```
chmod +x ~/tuning/target-runner
```

3. If your targetRunner script calls another program, make sure it is at the location described in the script (variable EXE in the examples and templates). A typical output for such an error is:

```
Error: == irace == running command ''~/tuning/target-runner' 1 8 676651103 ~/tuning/Instances/1000-16.tsp --ras --localsearch 2 --alpha 4.03 --beta 1.89 --rho 0.02 --ants 37 --nnls 48 --dlb 0 --rasranks 15 2>\&1' had status 1 == irace == The call to target.runner.default was: ~/tuning/target-runner 1 8 676651103 ~/tuning/Instances/1000-16.tsp --ras --localsearch 2 --alpha 4.03 --beta 1.89 --rho 0.02 --ants 37 --nnls 48 --dlb 0 --rasranks 15 == irace == The output was:
Tue May 3 19:00:37 UTC 2016: error: ~/bin/acotsp: not found or not executable (pwd: ~/tuning/acotsp-arena)
```

You may test your script by copying the command line shown in the error and executing target-runner directly on the execution directory (execDir). In this case, the command line is:

```
~/tuning/target-runner 1 8 676651103 ~/tuning/Instances/1000-16.tsp --ras \
--localsearch 2 --alpha 4.03 --beta 1.89 --rho 0.02 --ants 37 --nnls 48 \
--dlb 0 --rasranks 15
```

This executes the targetRunner script as irace does. The output of this script must be only one number.

4. Check that your targetRunner script is actually returning one number as output. For example:

In the example above, the output of target-runner is "Solution: 24479793", which is not a number. If target-runner is parsing the output of the target algorithm, you need to verify that the code only parses the solution cost value.

5. Check that your targetRunner script is creating the output files for your algorithm. If you see an error as:

```
== irace == The output was: Tue May 3 19:41:40 UTC 2016: error: c1-9.stdout: No such file or directory
```

The output file of the execution of your algorithm has not been created (check permissions) or has been deleted before the result can be read.

6. Other errors can produce the following output:

```
== irace == The output was: Tue May 3 19:49:06 UTC 2016: error: c1-23.stdout: Output is not a number
```

This might be because your targetRunner script is not executing your algorithm correctly. To further investigate this issue, comment out the line that eliminates the temporary files that saves the output of your algorithm. Similar to this one

```
rm -f "${STDOUT}" "${STDERR}"
```

Execute directly the targetRunner command-line that is provided in the error message, look in your execution directory for the files that are created. Check the .stderr file for errors and the .stdout file to see the output that your algorithm produces.

7. Some command within targetRunner may not be working correctly. In that case, you must debug the commands individually exactly as **irace** executes them. In order to find where the problem is, print the commands to a log file before executing them. For example:

```
echo "$EXE ${FIXED_PARAMS} -i $INSTANCE ${CONFIG_PARAMS}" >> ${STDERR}.log $EXE ${FIXED_PARAMS} -i $INSTANCE ${CONFIG_PARAMS} 1> ${STDOUT} 2> ${STDERR}
```

then look at the \$STDERR.log file corresponding to the targetRunner call that failed and execute/debug the last command there.

- 8. If the language of your operating system, the target-runner or the target algorithm is not English, irace may not be able to recognize the numbers generated by target-runner. We recommend that you run irace, the target-runner and the target algorithm under an English locale (or make sure that their languages and number format are compatible).
- 9. It is possible that transient bugs in the target algorithm are only visible when running within **irace**, and all commands within **targetRunner** appear to work fine when executed directly in the command-line outside **irace**. See FAQ in Section 12.3) for suggestions on how to detect such bugs.
- 10. If your targetRunner script works when running irace with parallel=0 but it fails when using higher number of cores, this may be due to any number of reasons:

- If you submit jobs through a queuing system, the running environment when using the queuing system may not be the same as when you launch **irace** yourself. The queuing system may also send the job to different machines depending on the number of CPUs requested. One way to test this is to submit the failing execution of targetRunner to the queuing system, and specifically to any problematic machine.
- When using MPI, some calls to targetRunner may run on different computers than the one running the master irace process. See FAQ in Section 12.5.
- Does targetRunner read or create intermediate files? These files may cause a race condition when two calls to targetRunner happen at the same time. You have to make sure that parallel runs of targetRunner do not interfere with each other's files.
- Maybe these files consume too much memory or fill the filesystem when there are simultaneous targetRunner calls? Moreover, queuing systems have stricter limits for computing nodes than for the submit/host node.
- Does the machine or the queuing system impose any limits on number of processes or CPU/memory/filesystem usage per job? Such limits may only trigger when more than one process is executed in parallel, killing the targetRunner process before it has a chance to print anything useful. In that case, irace may not detect the the program finished unexpectedly, only that the expected output was not printed.

# Appendix C targetEvaluator troubleshooting checklist

Even if targetRunner appears to work, the use of targetEvaluator may lead to other problems. The same checklist of targetRunner can be followed here. In addition, we list here other potential problems unique to targetEvaluator:

1. If targetEvaluator fails only in the second or later iteration, this may because output files or data generated by a previous call to targetRunner are missing. Elite configurations are never re-executed on the same instance and seed pair, that is, irace will call only once targetRunner for each pair of configuration ID and instance ID. However, targetEvaluator is always re-executed, which takes into account any updated information (normalization bounds, reference sets/points, best-known values, etc.). Thus, any files or data generated by targetRunner for a given configuration must remain available to targetEvaluator as long as that configuration is alive. The list of alive configurations is passed to targetEvaluator, which may decide then which data to keep or remove.

# Appendix D Glossary

**Parameter tuning:** Process of searching good settings for the parameters of an algorithm under a particular tuning scenario (instances, execution time, etc.).

Scenario: Settings that define an instance of the tuning problem. These settings include the algorithm to be tuned (target), budget for the execution of the target algorithm (execution time, evaluations, iterations, etc.), set of problem instances and all the information that is required to perform the tuning.

Target algorithm: Algorithm whose parameters will be tuned.

Target parameter: Parameter of the target algorithm that will be tuned.

irace option: Configurable option of irace.

Elite configurations: Best configurations found so far by irace. New configurations for the next iteration of irace are sampled from the probabilistic models associated to the elite configurations. All elite configurations are also included in the next iteration.

**\$IRACE\_HOME:** The filesystem path where **irace** is installed. You can find this information by opening an R console and executing:

```
system.file(package = "irace")
```

# Appendix E NEWS

NEWS

3.3 (26/04/2019)

\* Fix buggy test that breaks CRAN.

(Manuel López-Ibáñez)

\* Do not print "23:59:59" when wall-clock time is actually close to zero.

(Manuel López-Ibáñez)

3.2 (24/04/2019)

\* Fix `irace --check --parallel 2` on Windows.

(Manuel López-Ibáñez)

\* Values of real-valued parameter are now printed with sufficient precision to satisfy `digits` (up to `digits=15`).

(Manuel López-Ibáñez)

 $\boldsymbol{\ast}$  It is possible to specify boundMax without capping.

(Leslie Pérez Cáceres, Manuel López-Ibáñez)

- \* `irace --check` will exit with code 1 if the check is unsuccessful (Manuel López-Ibáñez)
- \* Print where irace is installed with `--help`.

(Manuel López-Ibáñez)

\* irace will now complain if the output of target-runner or target-evaluator contains extra lines even if the first line of output is correct. This is to avoid parsing the wrong output. Unfortunately, this may break setups that relied on this behavior. The solution is to only print the output that irace expects.

(Manuel López-Ibáñez)

\* Completely re-implement `log` parameters to fix several bugs. Domains that contain zero or negative values are now rejected.

(Leslie Pérez Cáceres, Manuel López-Ibáñez)

- \* New option `aclib=` (`--aclib 1`) enables compatibility with the GenericWrapper4AC (https://github.com/automl/GenericWrapper4AC/) used by AClib (http://aclib.net/). This is EXPERIMENTAL.
  - `--aclib 1` also sets digits to 15 for compatibility with AClib defaults.

    (Manuel López-Ibáñez)
- st Fix printing of output when capping is enabled.

(Manuel López-Ibáñez)

- \* `checkTargetFiles()` (`--check`) samples an instance unless `sampleInstances` is FALSE. (Manuel López-Ibáñez)
- \* Fix symbol printed in elimination test. (Manuel López-Ibáñez)
- \* Use `dynGet()` to find `targetRunner` and `targetEvaluator`.

  As a result, we now require R >= 3.2.

(Manuel López-Ibáñez)

\* All tests now use `testthat`.

(Manuel López-Ibáñez)

\* New function `scenario.update.paths()`

(Manuel López-Ibáñez)

- \* Fix assert failure that may happen when `elitistNewInstances` is larger than `firstTest`. Reported by Jose Riveaux. (Manuel López-Ibáñez)
- \* Fix bug in `checkTargetFiles()` (`--check`) with capping.

(Leslie Pérez Cáceres)

\* Clarify a few errors/warnings when `maxTime` > 0.

(Manuel López-Ibáñez, suggested by Haroldo Gambini Santos)

### 3.1 (12/07/2018)

\* Use testthat for unit testing.

(Manuel López-Ibáñez)

\* Allow instances to be a list of arbitrary R objects (`mlr` bugfix).

(Manuel López-Ibáñez)

### 3.0 (05/07/2018)

\* irace now supports adaptive capping for computation time minimization.

The default value of the testType option is t-test when adaptive capping is enabled. Please see the user-guide for details.

(Leslie Pérez Cáceres, Manuel López-Ibáñez)

- \* The package contains an `ablation()` function implementing the ablation method for parameter importance analysis by Fawcett and Hoos (2016).

  (Leslie Pérez Cáceres, Manuel López-Ibáñez)
- \* New option `postselection` executes a post-selection race.

(Leslie Pérez Cáceres)

- \* At the end of each race, if the race stops before evaluating all instances seen in previous races, then the best overall may be different than the best of the race. We now print the best overall (best-so-far). Elites evaluated on more instances are considered better than those evaluated on fewer.

  (Manuel López-Ibáñez, Leslie Pérez Cáceres)
- \* Last active parameter values of numerical parameters (`i` and `r`) are carried by the sampling model. When a value must be assigned and the parameter was previously not active, the sampling is performed around the last value. (Leslie Pérez Cáceres, Manuel López-Ibáñez)
- \* R help pages are now generated with Roxygen2.

(Leslie Pérez Cáceres, Manuel López-Ibáñez)

\* The user guide documents --version, --help, and --check.

(Manuel López-Ibáñez)

\* A return value of `Inf` from `targetRunner`/`targetEvaluation` results in

the immediate rejection of the configuration without any further evaluation. This is useful for handling unreliable or broken configurations that should not stop irace. (Manuel López-Ibáñez)

- \* Numerical parameters may be sampled on a logarithmic scale using `i,log` or `r,log`. (Alberto Franzin)
- \* New `target-runner.bat` for Windows contributed by André de Souza Andrade.
- \* Fixed all shell scripts calling functions before defining them, which is not portable.

(Manuel López-Ibáñez)

\* Fixed `--parallel` bug in Windows that resulted in `Error in checkForRemoteErrors(val)`.

(Manuel López-Ibáñez)

\* Improve error message when no training instances are given.

(Manuel López-Ibáñez)

### 2.4 (03/08/2017)

\* The output of irace now specifies in which order, if any, configurations are printed.

(Manuel López-Ibáñez, suggested by Markus Wagner)

\* Several fixes for handling paths in Windows.

(Manuel López-Ibáñez)

\* readConfigurationsFile() now has a text= argument, which allows reading configurations from a string.

(Manuel López-Ibáñez)

 $\ast$  User-provided functions (targetRunner, targetEvaluator and repairConfiguration) and user-provided conditions for forbidden configurations are now byte-compiled when read, which should make their evaluation noticeably faster.

(Manuel López-Ibáñez)

\* The argument 'experiment' passed to the R function targetRunner does not contain anymore an element 'extra.params'. Similarly, the 'scenario' structure does not contain anymore the elements 'instances.extra.params' and 'testInstances.extra.params'. Any instance-specific parameters values now form part of the character string that defines an instance and it is up to the user-defined targetRunner to parse them appropriately. These changes  $% \left( 1\right) =\left( 1\right) \left( 1\right) \left$ make no difference when targetRunner is an external script, or when instances and instance-specific parameter values are read from a file.

(Manuel López-Ibáñez)

### 2.3

\* Fix bug that will cause iraceResults\$experimentLog to count calls to  ${\tt targetEvaluator}\ \ {\tt as}\ \ {\tt experiments},\ \ {\tt even}\ \ {\tt if}\ \ {\tt no}\ \ {\tt call}\ \ {\tt to}\ \ {\tt targetRunner}\ \ {\tt was}$ performed. This does not affect the computation of the budget consumed and, thus, it does not affect the termination criteria of irace. The bug triggers an assertion that terminates irace, thus no run that was successful with version 2.2 is affected.

(Manuel López-Ibáñez)

- \* Command-line parameters are printed to stdout (useful for future replications). (Manuel López-Ibáñez, suggested by Markus Wagner)
- \* Users may provide a function to repair configurations before being evaluated. See the scenario variable repairConfiguration.

(Manuel López-Ibáñez)

- \* The option --sge-cluster (sgeCluster) was removed and replaced by
  --batchmode (batchmode). It is now the responsibility of the target-runner
  to parse the output of the batch job submission command (e.g., qsub or
  squeue), and return just the job ID. Values supported are: "sge", "torque",
  "pbs" and "slurm". (Manuel López-Ibáñez)
- \* The option --parallel can now be combined with --batchmode to limit the number of jobs submitted by irace at once. This may be useful in batch clusters that have a small queue of jobs.

(Manuel López-Ibáñez)

\* New examples under inst/examples/batchmode-cluster/.

(Manuel López-Ibáñez)

\* It is now possible to include scenario definition files from other scenario files by using:

```
eval.parent(source("scenario-common.txt", chdir = TRUE, local = TRUE))
```

This feature is VERY experimental and the syntax is likely to change in the future. (Manuel López-Ibáñez)

- \* Fix a bug that re-executed elite results under some circumstances. (Leslie Pérez Cáceres)
- \* Restrict the number of maximum configurations per race to 1024. (Leslie Pérez Cáceres)
- \* Do not warn if the last line in the instance file does not terminate with a newline. (Manuel López-Ibáñez)
- \* Fix bug when deterministic == 1. (Manuel López-Ibáñez, Leslie Pérez Cáceres)
- \* Update manual and vignette with details about the expected arguments and return value of targetRunner and targetEvaluator. (Manuel López-Ibáñez)
- st Many updates to the User Guide vignette. (Manuel López-Ibá $ilde{ ilde{n}}$ ez)
- \* Fix \dontrun example in irace-package.Rd (Manuel López-Ibáñez)
- \* Fix bug: If testInstances contains duplicates, results of testing are not correctly saved in iraceResults\$testing\$experiments nor reported correctly at the end of a run. Now unique IDs of the form 1t, 2t, ... are used for each testing instance. These IDs are used for the rownames of iraceResults\$testing\$experiments and the names of the scenario\$testInstances and iraceResults\$testing\$seeds vectors. (Manuel López-Ibáñez)
- $\ast$  Fix bug where irace keeps retrying the target-runner call even if it succeeds. (Manuel López-Ibáñez)
- \* New command-line parameter

--only-test FILE

which just evaluates the configurations given in FILE on the testing instances defined by the scenario. Useful if you decide on the testing instances only after running irace. (Manuel López-Ibáñez)

\* Bugfix: When using maxTime != 0, the number of experiments performed may be miscounted in some cases. (Manuel López-Ibáñez)

### 2.1

- \* Fix CRAN errors in tests. (Manuel López-Ibáñez)
- \* Avoid generating too many configurations at once if the initial time estimation is too small. (Manuel López-Ibáñez)

### 2.0

- \* Minimum R version is 2.15.
- \* Elitist irace by default, it can be disabled with parameter --elitist 0. (Leslie Pérez Cáceres, Manuel López-Ibáñez)
- \* The parameter --test-type gains two additional values:
  - t-test-bonferroni (t-test with Bonferroni's correction for multiple comparisons),
  - t-test-holm (t-test with Holm's correction for multiple comparisons)

(Manuel López-Ibáñez)

- \* MPI does not create log files with --debug-level 0. (Manuel López-Ibáñez)
- \* For simplicity, the parallel-irace-\* scripts do not use an auxiliary `tune-main` script. For customizing them, make a copy and edit them directly.

  (Manuel López-Ibáñez)
- \* New parameters:
  - --target-runner-retries : Retry target-runner this many times in case of error.

(Manuel López-Ibáñez)

- \* We print diversity measures after evaluating on each instance: (Leslie Pérez Cáceres)
  - Kendall's W (also known as Kendall's coefficient of concordance) If 1, all candidates have ranked in the same order in all instances. If 0, the ranking of each candidate on each instance is essentially random.

$$W = Friedman / (m * (k-1))$$

- Spearman's rho: average (Spearman) correlation coefficient computed on the ranks of all pairs of raters. If there are no repeated data values, a perfect Spearman correlation of +1 or -1 occurs when each of the variables is a perfect monotone function of the other.
- \* Many internal and external interfaces have changed. For example, now we consistently use 'scenario' to denote the settings passed to irace and 'configuration' instead of 'candidate' to denote the parameter settings passed to the target algorithm. Other changes are:

```
parameters$boundary -> parameters$domain
hookRun -> targetRunner
hookEvaluate -> targetEvaluator
tune-conf -> scenario.txt
instanceDir -> trainInstancesDir
instanceFile -> testInstancesDir
testInstanceFile -> testInstancesFile
```

- \* Minimal example of configuring a MATLAB program (thanks to Esteban Diaz Leiva)
- \* Paths to files or directories given in the scenario file are relative to the scenario file (except for --log-file, which is an output file and it is relative to --exec-dir). Paths given in the command-line are relative to the current working directory. Given

```
$ cat scenario/scenario.txt
targetRunner <- "./target-runner"
$ irace -s scenario/scenario.txt</pre>
```

irace will search for "./scenario/target-runner", but given

\$ irace -s scenario/scenario.txt --target-runner ./target-runner

irace will search for "./target-runner". (Manuel López-Ibáñez)

- \* New command-line wrapper for Windows installed at 'system.file("bin/irace.bat", package="irace")' (thanks to Anthony Antoun)
- \* Budget can be specified as maximum time (maxTime, --max-time) consumed by the target algorithm. See the documentation for the details about how this is handled. (Leslie Pérez Cáceres, Manuel López-Ibáñez)

- \* The best configurations found, either at the end or at each iteration of an irace run, can now be applied to a set of test instances different from the training instances. See options testInstanceDir, testInstanceFile, testNbElites, and testIterationElites. (Leslie Pérez Cáceres, Manuel López-Ibáñez)
- \* The R interfaces of hookRun, hookEvaluate and hookRunParallel have changed. See help(hook.run.default) and help(hook.evaluate.default) for examples of the new interfaces.
- \* Printing of race progress now reports the actual configuration and instance IDs, and numbers are printed in a more human-readable format. (Leslie Pérez Cáceres, Manuel López-Ibáñez)
- \* Reduce memory use for very large values of maxExperiments.

  (Manuel López-Ibáñez, thanks to Federico Caselli for identifying the issue)
- \* New option --load-balancing (loadBalancing) for disabling load-balancing when executing jobs in parallel. Load-balancing makes better use of computing resources, but increases communication overhead. If this overhead is large, disabling load-balancing may be faster.

  (Manuel López-Ibáñez, thanks to Federico Caselli for identifying the issue)

- \* The option --parallel in Windows now uses load-balancing by default. (Manuel López-Ibáñez)
- \* The wall-clock time after finishing each task is printed in the output. (Manuel López-Ibáñez, thanks to Federico Caselli for providing an initial patch)

### 1.06

- \* Fix bug that could introduce spurious whitespace when printing the final configurations. (Manuel López-Ibáñez)
- \* Fix bug if there are more initial candidates than needed for the first race. (Leslie Pérez Cáceres, Manuel López-Ibáñez)
- \* New configuration options, mainly for R users:
  - hookRunParallel: Optional R function to provide custom parallelization of hook.run.
  - hookRunData: Optional data passed to hookRun. This is ignored by the default hookRun function, but it may be used by custom hookRun R functions to pass persistent data around.
     (Manuel López-Ibáñez)

- \* New option --version. (Manuel López-Ibáñez)
- \* Terminate early if there is no sufficient budget to run irace with the given settings. (Manuel López-Ibáñez)
- \* The option --parallel (without --mpi) now works under Windows. (Manuel López-Ibáñez, thanks to Pablo Valledor Pellicer for testing it)
- \* Improved error handling when running under Rmpi. Now irace will terminate as soon as the master node detects at least one failed slave node. This avoids irace reporting two times the same error. Also, irace will print all the unique errors returned by all slaves and not just the first one.

  (Manuel López-Ibáñez)
- \* Forbidden configurations may be specified in terms of constraints on their values. Forbidden configurations will never be evaluated by irace. See --forbidden-file and inst/templates/forbidden.tmpl. (Manuel López-Ibáñez)
- \* New option --recovery-file (recoveryFile) allows resuming a previous irace run. (Leslie Pérez Cáceres)
- \* The confidence level for the elimination test is now configurable with parameter --confidence. (Leslie Pérez Cáceres)
- \* Much more robust handling of relative/absolute paths. Improved support for Windows. (Leslie Pérez Cáceres, Manuel López-Ibáñez)
- \* Provide better error messages for incorrect parameter descriptions. (Manuel López-Ibáñez)
  Examples:

```
x "" i (0, 0)  # lower and upper bounds are the same x "" r (1e-4, 5e-4) # given digits=2, ditto x "" i (-1, -2)  # lower bound must be smaller than upper bound x "" c ("a", "a") # duplicated values
```

- \* Print elapsed time for calls to hook-run if debugLevel >=1. (Manuel López-Ibáñez)
- \* examples/hook-run-python/hook-run: A multi-purpose hook-run written in Python. (Franco Mascia)
- \* Parallel mode in an SGE cluster (--sge-cluster) is more robust. (Manuel López-Ibáñez)

### 1.04

- \* Replace obsolete package multicore by package parallel (requires R >= 2.14.0)
- \* Use load-balancing (mc.preschedule = FALSE) in mclapply.

### 1.03

- \* Use reg.finalizer to finish Rmpi properly without clobbering .Last().
- \* Remove uses of deprecated as.real().
- \* Nicer error handling in readParameters.
- \* Add hypervolume (multi-objective) example.
- $\boldsymbol{\ast}$  Fix several bugs in the computation of similar candidates.

### 1.02

- \* More concise output.
- \* The parameters expName and expDescription are now useless and they were removed.
- \* Faster computation of similar candidates (Jeremie Dubois-Lacoste and Leslie Pérez Cáceres).
- \* Fix bug when saving instances in tunerResults\$experiments.
- \* irace.cmdline ("--help") does not try to quit R anymore.

- \* Fix bug caused by file.exists (and possibly other functions) not handling directory names with a trailing backslash or slash on Windows.
- \* Fix bug using per-instance parameters (Leslie Pérez Cáceres).
- \* Fix bug when reading initial candidates from a file.