


```
apt-get install chrony
```

```
apt-get install acl attr samba smbclient winbind krb5.config  
krb5.user libpam-winbind libnss-winbind libpam-krb5 dnsutils
```



TÖBBI ÜRES

Kimásoljuk `/etc/samba/smb.conf` tartalmát és az `/etc/krb5.conf`-ot

Ez után le kell törölni és ezt le kell futatni :

```
samba-tool domain provision --use-rfc2307 --dns-  
backend=SAMBA_INTERNAL --realm=sg1.lan -- domain=sg1 --server-  
role=dc --adminpass=passw0rd
```

`/var/lib/samba/private/krb5.conf` másolása az `/etc` -be

```

GNU nano 7.2 /etc/chrony/chrony.conf *
# Uncomment the following line to turn logging on.
#log tracking measurements statistics

# Log files location.
logdir /var/log/chrony

# Stop bad estimates upsetting machine clock.
maxupdateskew 100.0

# This directive enables kernel synchronisation (every 11 minutes) of the
# real-time clock. Note that it can't be used along with the 'rtcfile' directive.
rtcsync

# Step the system clock instead of slewing it if the adjustment is larger than
# one second, but only in the first three clock updates.
makestep 1 3

# Get TAI-UTC offset and leap seconds from the system tz database.
# This directive must be commented out when using time sources serving
# leap-smeared time.
leapsectz right/UTC

bindcmdaddress 172.16.109.1
allow 172.16.109.0/24

```

chown root:_chrony /var/lib/samba/ntp-signd

chmod 750 /var/lib/samba/ntp_signd

```

GNU nano 7.2 /etc/chrony/chrony.conf *
# Uncomment the following line to turn logging on.
#log tracking measurements statistics

# Log files location.
logdir /var/log/chrony

# Stop bad estimates upsetting machine clock.
maxupdateskew 100.0

# This directive enables kernel synchronisation (every 11 minutes) of the
# real-time clock. Note that it can't be used along with the 'rtcfile' directive.
rtcsync

# Step the system clock instead of slewing it if the adjustment is larger than
# one second, but only in the first three clock updates.
makestep 1 3

# Get TAI-UTC offset and leap seconds from the system tz database.
# This directive must be commented out when using time sources serving
# leap-smeared time.
leapsectz right/UTC

bindcmdaddress 172.16.109.1
allow 172.16.109.0/24

```

nano /etc/samba/smb.conf

```
GNU nano 7.2 /etc/samba/smb.conf *
# Global parameters
[global]
    dns forwarder = 8.8.8.8
    netbios name = SZEB
    realm = SG1.LAN
    server role = active directory domain controller
    workgroup = SG1
    idmap_ldb:use rfc2307 = yes
    inherit acls = yes
[sysvol]
    path = /var/lib/samba/sysvol
    read only = No
[netlogon]
    path = /var/lib/samba/sysvol/sg1.lan/scripts
    read only = No
```

```
systemctl stop smbd nmbd winbind
```

```
systemctl disable smbd nmbd winbind
```

```
Systemctl unmask samba-ad-dc
```

```
Systemctl start samba-ad-dc
```

```
Systemctl enable samba-ad-dc
```

//felhasználó létrehozása

```
(sudo) samba-tool user create Joci passw0rd
```

Dankó Máté 13/D