Permittivity of free space: $\epsilon_0 = 8.854 \times 10^{-12}$

Elementary charge: $e = 1.602 \cdot 10^{-19}$

Proton mass: $1.673 \cdot 10^{-27}$ Electron mass: $9.11 \cdot 10^{-31}$ Speed of light: $c = 3 \cdot 10^8$

Permeability constant: $\mu_0 = 1.26 \times 10^{-6}$

Moving Conductor

$$I = \frac{\Delta V}{R} = \frac{\varepsilon}{R} = \frac{v l B}{R}$$

$$F_{\text{mag}} = F_{\text{pull}} = I l B = \frac{v l^2 B^2}{R}$$

$$P_{\text{input}} = P_{\text{dissipated}} = I^2 R = \frac{v^2 l^2 B^2}{R}$$

 $\Phi_m = \vec{A} \cdot \vec{B} = |A||B|\cos\theta$ (uniform magnetic field)

- Increasing flux: The induced magnetic field points opposite the applied magnetic field.
- Decreasing flux: The induced magnetic field points in the same direction as the applied magnetic field.
- Steady flux: There is no induced magnetic field.

$$arepsilon_{
m induced} = rac{d\Phi_m}{dt} \quad I_{
m induced} = rac{arepsilon_{
m induced}}{R}$$

$$E_{
m inside} = rac{r}{2} \Big| rac{dB}{dt} \Big| \quad {
m Solenoid}$$

$$rac{V_2}{V_1} = rac{N_2}{N_1} \quad {
m Transformers}$$

Inductors

$$L = \frac{\Phi_m}{I} \text{ henry (H)}$$

$$\Delta V_L = -L \frac{dI}{dt} \quad U_L = L \int_0^I I dI = \frac{1}{2} L I^2$$

LC Circuits

$$I = -\frac{dQ}{dt} \quad Q(t) = Q_0 \cos \omega t$$
$$\omega = \frac{1}{\sqrt{IC}} \quad f = \omega/2\pi$$

LR Circuits

$$I = I_0 e^{-t/(L/R)}$$

$$\tau = \frac{L}{R} \quad \text{where current has decreased to } e^{-1}$$

Right-hand rule (wire)

- 1. Point thumb in the direction of current
- 2. Point fingers in the direction of magnetic field
- 3. Point palm in the face of force on wire

$$\vec{E}_B = \vec{E}_A + \vec{v}_{BA} \times \vec{B}_A$$

$$\vec{B}_B = \vec{B}_A - \frac{1}{c^2} \vec{v}_{BA} \times \vec{E}_A$$

$$a \times b = \begin{vmatrix} \hat{\imath} & \hat{\jmath} & \hat{k} \\ a_x & a_y & a_z \\ b_x & b_y & b_z \end{vmatrix}$$

$$I_{\text{disp}} = \epsilon_0 \frac{d\Phi_e}{dt} = \epsilon_0 \frac{dE \cdot A}{dt}$$

$$\oint \vec{E} \cdot d\vec{A} = \frac{Q_{\text{in}}}{\epsilon_0} \quad \text{Gauss's Law}$$

$$\oint \vec{B} \cdot d\vec{A} = 0 \quad \text{Gauss's Law for Magnetism}$$

$$\oint \vec{E} \cdot d\vec{s} = -\frac{d\Phi_m}{dt} \quad \text{Faraday's Law}$$

$$\oint \vec{B} \cdot d\vec{s} = \mu_0 I_{\text{through}} + \epsilon_0 \mu_0 \frac{d\Phi_e}{dt} \quad \text{Ampere-Maxwell Law}$$

$$\vec{F} = q(\vec{E} + \vec{v} \times \vec{B}) \quad \text{Lorentz Force Law}$$

$$E(x, t) = E_0 \cos(kx - \omega t + \phi)$$

- 1. $k = \frac{2\pi}{\lambda}$ where k is wave number and λ is wavelength
- 2. $T = \frac{2\pi}{\omega}$ where T is period and ω is angular frequency
- 3. $f = \frac{1}{T}$ where f is frequency
- 4. $v = f\lambda$ where v is the propagation speed
- 5. $v = \frac{E_0}{B_0}$ where E_0 and B_0 are the electric and magnetic field components

$$E = cB$$

$$I = \frac{P}{4\pi r^2} = \frac{c\epsilon_0 E_0^2}{2}$$

$$\langle S \rangle = \frac{1}{\mu_0} EB \sin \theta$$

Right-hand rule (electromagnetic waves)

- 1. Point index finger in the direction of electric field
- 2. Point middle finger in the direction of magnetic field
- 3. Point thumb in the direction of motion

$$\begin{split} I_{\rm transmitted} &= \frac{1}{2} I_0 \quad \text{unpolarized} \\ I_{\rm transmitted} &= I_0 \cos^2 \theta \quad \text{polarized} \end{split}$$

$$\varepsilon = \varepsilon_0 \cos \omega t \quad \omega = 2\pi f$$

 $v_R = i_R R$ (AC circuit) and V_R is the maximum voltage

Capacitor circuit

$$\begin{split} v_C &= V_C \cos \omega t \\ q &= C v_C \\ i_C &= -\omega C V_C \sin \omega t = \omega C V_C \cos (\omega t + \frac{\pi}{2}) \\ X_C &= \frac{1}{\omega C} \quad I_C = \frac{V_C}{X_C} \quad (X_C \text{ is Capacitive reactance}) \\ \omega_C &= \frac{1}{RC} \quad (\text{RC Circuit}) \end{split}$$

Inductor circuit

$$i_L=I_L\cos(\omega t-\frac{\pi}{2})$$

$$X_L=\omega L\quad I_L=\frac{V_L}{X_L}\quad (X_L\text{ is Inductive reactance})$$

Series RLC Circuit

$$Z = \sqrt{R^2 + (X_L - X_C)^2} \quad \text{(impedance)}$$

$$I_{\text{peak}} = \frac{\varepsilon_0}{Z}$$

$$\phi = \tan^{-1}\left(\frac{X_L - X_C}{R}\right)$$
 (angle between emf and current)
$$\omega_0 = \frac{1}{\sqrt{LC}}$$
 (resonance frequency)

- If $V_C > V_L$, the circuit operates below resonance frequency
- If $V_L > V_C$, the circuit operates above resonance frequency

$$p = i\varepsilon$$
 (AC circuit)

i and ε are instantaneous current and potential difference

$$P_R = \frac{1}{2}I_R^2 R = I_{\rm rms}V_{\rm rms}$$
$$x_{\rm rms} = \frac{x}{\sqrt{2}}$$

$$P_{\text{source}} = \frac{1}{2} I \varepsilon_0 \cos \phi = I_{\text{rms}} \varepsilon_{\text{rms}} \cos \phi = P_{\text{max}} \cos^2 \phi$$

 $\cos \phi$ is the power factor, ϕ is the phase between current and emf, $P_{
m mas}=rac{1}{2}I_{
m max}arepsilon_0.$ In an AC circuit with a capacitor, the current leads the voltage

by $\frac{\pi}{2}$ so current reaches maximum $\frac{T}{4}$ before voltage. In an AC circuit with an inductor, the current lags the voltage by $\frac{\pi}{2}$ so current reaches maximum $\frac{T}{4}$ after voltage.