
Topology Diagram:



Network Address Table:

#	Host Name	Host	IP	Given IP	Host bit	Net hit	IP address
,,,	Host I dille	Host		GIVEN II	Host bit	11Ct bit	ii dddicss
Α	The White	5000	5002	8192	13	19	172.152.0.0/19
	Walkers						
В	The Stormlands	2000	2002	2048	11	21	172.152.32.0/21
С	The North	1024	1026	2048	11	21	172.152.40.0/21
D	The Reach	1000	1002	1024	10	22	172.152.48.0/22
E	The Iron Island	800	802	1024	10	22	172.152.52.0/22
F	The Rocks	480	482	512	9	23	172.152.56.0/23
G	The Mountain	250	252	256	8	24	172.152.58.0/24
	Vale						
H	The Drone	124	126	128	7	25	172.152.59.0/25
I	Router 6 -	2	4	4	2	30	172.152.59.128/30
	Router 8						
J	Router 9 -	2	4	4	2	30	172.152.59.132/30
	Router 7						
K	Router 8 -	2	4	4	2	30	172.152.59.136/30
	Router 9						
L	Router 7 –	2	4	4	2	30	172.152.59.140/30
	Router 6						
M	Router 6 –	2	4	4	2	30	172.152.59.144/30
	Router 9						

IP Address Table:

Network Port		IP address	Subnet Mask	Default Gateway
	Fa0/0	172.152.56.1	255.255.254.0	N/A

1		T	1	
R6	Fa0/1	172.152.48.1	255.255.252.0	
	S1/0	172.152.59.129	255.255.255.252	
	S1/1	172.152.59.141	255.255.255.252	
	S1/2	172.152.59.146	255.255.255.252	
R7	Fa0/0	172.152.32.1	255.255.248.0	N/A
	Fa0/1	172.125.58.1	255.255.255.0	
	S1/0	172.152.59.134	255.255.255.252	
	S1/1	172.152.59.142	255.255.255.252	
R9	F0/0	172.152.0.1	255.255.224.0	N/A
	F0/1	172.152.40.1	255.255.248.0	
	S1/0	172.152.59.133	255.255.255.252	
	S1/1	172.152.59.138	255.255.255.252	
	21/2	.=0.4=0.=0.446		
	S1/2	172.152.59.146	255.255.255.252	21/2
R8	Fa0/0	172.152.52.1	255.255.252.0	N/A
	Fa0/1	172.152.59.1	255.255.255.120	
	S1/0	172.152.59.130	255.255.255.252	
	S1/1	172.152.59.137	255.255.255.252	
PC5	Fa0	172.152.56.2	255.255.254.0	172.152.56.1
PC6	Fa0	172.152.48.2	255.255.252.0	172.152.48.1
PC7	Fa0	172.152.32.2	255.255.248.0	172.152.32.1
PC8	Fa0	172.152.58.2	255.255.255.0	172.152.58.1
PC9	Fa0	172.152.59.2	255.255.255.128	172.152.59.1
PC11	Fa0	172.152.0.2	255.255.224.0	172.152.0.1
PC12	Fa0	172.152.40.3	255.255.248.0	172.152.40.1
Server 2	Fa0	172.152.56.4	255.255.254.0	172.152.56.1

Comion 3	Fa0	172.152.0.4	255.255.224.0	172.152.0.1
Server 3	FaU	1/2.152.0.4	255.255.224.0	1/2.152.0.1
Laptop 5	Fa0	172.152.56.3	255.255.254.0	172.152.56.1
Laptop 6	Fa0	172.152.48.3	255.255.252.0	172.152.48.1
Laptop 7	Fa0	172.152.32.3	255.255.248.0	172.152.32.1
Laptop 8	Fa0	172.152.58.3	255.255.255.0	172.152.58.1
Laptop 9	Fa0	172.152.59.3	255.255.255.128	172.152.59.1
Laptop 10	Fa0	172.152.0.3	255.255.224.0	172.152.0.1
Laptop 11	Fa0	172.152.40.2	255.255.248.0	172.152.40.1
Laptop 0	Fa0	172.152.52.2	255.255.252.0	172.152.52.1
Printer	Fa0	172.152.52.3	255.255.252.0	N/A

The Commands of All Routers:

Router 9:

Router>

Router>enconf t

Router>en

Router#conf t

Router(config)#in s1/0

Router(config-if)#ip add

Router(config-if)#ip address 172.152.59.131 255.255.255.252

Router(config-if)#ip address 172.152.59.133 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#exit

Router#

Router#

Router#conf t

Router(config)#router rip

Router(config-router)#version 2

Router(config-router)#no

Router(config-router)#no auto

Router(config-router)#no auto-summary

Router(config-router)#netwrok 172.152.32.0

Router(config-router)#network 172.152.32.0

Router(config-router)#passive in

Router(config-router)#passive

Router(config-router)#passive-interface f0/0

Router(config-router)#network 172.152.58.0

Router(config-router)#passive

Router(config-router)#passive-interface f0/0

Router(config-router)#passive-interface f0/1

Router(config-router)#deafault

Router(config-router)#default

Router(config-router)#default-information originate

Router(config-router)#end

Router#

Router#copy run start
Destination filename [startup-config]?
Building configuration...
[OK]
Router#
Router#

Router>en

Router#conf t

Router(config)#in s1/0

Router(config-if)#clock rate 64000

Router(config-if)#ip

Router(config-if)#ip add

Router(config-if)#ip address 172.152.59.134 255.255.255.252

Router(config-if)#no shut Router(config-if)#no shutdown

Router>en

Router#conf t

Router(config)#in s1/1

Router(config-if)#ip add

Router(config-if)#ip address 172.152.59.138 255.255.255.252

Router(config-if)#no shut

Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit

Router(config)#

Router(config)#ip route 0.0.0.0 0.0.0.0 172.152.59.137 Router(config)#ip route 172.152.59.0 255.255.255.128 172.

Router(config)#ip route 172.152.59.0 255.255.255.128 172.152.59.137 Router(config)#ip route 172.152.52.0 255.255.252.0 172.152.59.137 Router(config)#no shut Router(config)#no shutdown

Router to Switch

Router>en
Router#conf t

Router(config)#in f0/0 Router(config-if)#ip add Router(config-if)#ip address 172.152.32.1 255.255.248.0 Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit
Router(config)#in f0/1
Router(config-if)#ip add
Router(config-if)#ip address 172.152.3
Router(config-if)#ip address 172.152.58.1 255.255.255.0
Router(config-if)#no shut
Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit Router(config)#

Router>en
Router#conf t

Router(config)#in s1/1
Router(config-if)#clock rate 64000
Router(config-if)#ip add
Router(config-if)#ip address 172.152.59.137 255.255.252
Router(config-if)#no shut
Router(config-if)#no shutdown

Router(config-if)#exit

Router 7:

Router to switch

Router>en
Router#conf t

Router(config)#in f0/0
Router(config-if)#ip a
Router(config-if)#ip add
Router(config-if)#ip address 172.152.0.1 255.255.224.0
Router(config-if)#no shut
Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit
Router(config)#in f0/1
Router(config-if)#ip add
Router(config-if)#ip address 172.152.40.1 255.255.248.0
Router(config-if)#no shut
Router(config-if)#no shutdown

Router to Router

Router>en
Router#conf t

Router(config)#in s1/0
Router(config-if)#ip add
Router(config-if)#ip address 172.152.59.131 255.255.255.252
Bad mask /30 for address 172.152.59.131
Router(config-if)#ip address 172.152.59.133 255.255.255.252
Router(config-if)#no shutdown

Router(config-if)#exit Router(config)#exit Router#

Router#

Router>en

Router#conf t

Router(config)#in se1/1

Router(config-if)#ip add

Router(config-if)#ip address 172.152.59.142 255.255.255.252

Router(config-if)#clock rate 64000

Router(config-if)#no shutdown

Router(config-if)#exit

Router>en

Router#conf t

Router(config)#in se1/1

Router(config-if)#ip add

Router(config-if)#ip address 172.152.59.142 255.255.255.252

Router(config-if)#clock rate 64000

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#

Router(config)#ip route 0.0.0.0 0.0.0.0 se1/1

Router(config)#router rip

Router(config-router)#version 2

Router(config-router)#no auto

Router(config-router)#no auto-summary

Router(config-router)#network 172.152.48.0

Router(config-router)#passive

Router(config-router)#passive-interface f0/1

Router(config-router)#network 172.152.56.0

Router(config-router)#passive

Router(config-router)#passive-interface f0/0

Router(config-router)#default

Router(config-router)#default-information originate

Router(config-router)#end

Router#

Router#copy run start Router 6:

Router>en
Router#conf t

Router(config)#interface s1/0 Router(config-if)#clock rate 64000 Router(config-if)#ip address 172.152.59.129

Router(config-if)#ip address 172.152.59.129 255.255.255.252 Router(config-if)#no shutdown

Router(config-if)#exit Router(config)#

Router(config)#
Router(config)#in f0/0
Router(config-if)#ip add
Router(config-if)#ip address 172.152.56.1 255.255.254.0
Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit
Router(config)#in f0/1
Router(config-if)#ip add
Router(config-if)#ip address 172.152.48.1 255.255.252.0
Router(config-if)#no shut
Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit Router(config)#

Router to Router

Router>en
Router#conf t
Router(config)#ip route 172.152.59.1 255.255.255.128
Router(config)#ip route 172.152.59.1 255.255.255.128 172.152.59.130
Router(config)#ip route 172.152.59.1 255.255.255.0 172.152.59.130

Router(config)#ip route 172.152.59.0 255.255.255.128 172.152.59.130 Router(config)#ip route 172.152.52.0 255.252.255.0 172.152.59.130 Router(config)#ip route 172.152.52.0 255.255.252.0 172.152.59.130 Router(config)#exit Router#

Router#exit

Router/en
Router#conf t
Router(config)#in se1/1
Router(config-if)#ip add
Router(config-if)#ip address 172.152.59.141 255.255.252 Router(config-if)#no shut
Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit

Router/en
Router(config)#in se1/1
Router(config-if)#ip add
Router(config-if)#ip address 172.152.59.141 255.255.255
Router(config-if)#no shut
Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit Router(config)#

Router(config)#ip route 0.0.0.0 0.0.0 se1/1 Router(config)#router rip Router(config-router)#version 2 Router(config-router)#no auto Router(config-router)#no auto-summary Router(config-router)#network 172.152.32.0 Router(config-router)#passive Router(config-router)#passive-interface f0/0

Router(config-router)#network 172.152.58.0

Router(config-router)#passive

Router(config-router)#passive-interface f0/1

Router(config-router)#default

Router(config-router)#default-information originate

Router(config-router)#end

Router#

Router#copy run start

Destination filename [startup-config]? Building configuration...

Router>

Router>en

Router#conf t

Router(config)#in s1/2

Router(config-if)#ip ad

Router(config-if)#ip address 172.152.59.146 255.255.255.252

Router(config-if)#clock rate 64000

Router(config-if)#no shut

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#in s1/2

Router(config-if)#ip ad

Router(config-if)#ip address 172.152.59.146 255.255.255.252

Router(config-if)#clock rate 64000

Router(config-if)#no shut

Router(config-if)#no shutdown

Router(config-if)#exit

Router(config)#

Router(config)#ip route 0.0.0.0 0.0.0.0 172.152.59.147

Router(config)#ip route 172.152.0.0 255.255.224.0

Router(config)#ip route 172.152.0.0 255.255.224.0 172.152.59.145

Router(config)#ip route 172.152.40.0 255.255.248.0 172.152.59.145

Router(config)#exit

Router#

Router>en

Router#cof t

Router#conf t

Router(config)#ip route 0.0.0.0 0.0.0.0 172.152.59.145

Router(config)#ip route 0.0.0.0 0.0.0.0 172.152.59.146

Router(config)#ip route 0.0.0.0 0.0.0.0 172.152.59.130

Router(config)#ip route

Router(config)#ip route 172.152.56.0 255.255.254.0

Router(config)#ip route 172.152.56.0 255.255.254.0 172.152.59.146

Router(config)#ip route 172.152.48.0 255.255.252.0 172.152.59.146

Router(config)#

Router(config)#ip route 0.0.0.0 0.0.0.0 172.152.59.147

Router(config)#ip route 172.152.0.0 255.255.224.0

Router(config)#ip route 172.152.0.0 255.255.224.0 172.152.59.145

Router(config)#ip route 172.152.40.0 255.255.248.0 172.152.59.145

Router(config)#exit

Router#

Router#conf t

Router(config)#ip route 172.152.0.0 255.255.224.0 172.152.59.142 Router(config)#ip route 172.152.0.0 255.255.224.0 172.152.59.142 5

Router(config)#ip route 172.152.40.0 255.255.248.0 172.152.59.142 5

Router(config)#

Router 8:

Router>en

Router#conf t

Router(config)#in s1/0

Router(config-if)#ip add

Router(config-if)#ip address 172.152.59.130 255.255.255.252

Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit

Router(config)#

Router(config)#in f0/1

Router(config-if)#ip add

Router(config-if)#ip address 172.152.59.1 255.255.255.128 Router(config-if)#no shut Router(config-if)#no shutdown

Router(config-if)#

Router(config-if)#exit Router(config)#in f0/0 Router(config-if)#ip add Router(config-if)#ip address 172.152.52.1 255.255.252.0 Router(config-if)#no shutdown

Router(config-if)#

Router to Router

Router(config-if)#exit

Router(config)#

Router(config)#interface FastEthernet0/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/1

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/0

Router(config-if)#

Router(config-if)#exit

Router(config)#interface FastEthernet0/0

Router(config-if)#exit

Router(config)#exit Router#

Router>en

Router#cof t

Router#conf t

Router(config)#ip route 172.152.56.0 255.255.254.0 172.152.129

Router(config)#ip route 172.152.56.0 255.255.254.0 172.152.59.129

Router(config)#ip route 172.152.48.0 255.255.252.0 172.152.59.129

Router(config)#exit

Router#

Router#exit

```
Router/en
Router#conf t
Router(config)#in s1/1
Router(config-if)#clock rate 64000
Router(config-if)#ip add
Router(config-if)#ip address 172.152.59.137 255.255.255.252
Router(config-if)#no shut
Router(config-if)#no shutdown
```

Router(config-if)#exit

Router con0 is now available

The Configurations Of All Routers & Switches:

Router 6:

```
interface FastEthernet0/0 ip address 172.152.56.1 255.255.254.0 duplex auto speed auto !
interface FastEthernet0/1 ip address 172.152.48.1 255.255.252.0 duplex auto speed auto !
interface Serial1/0 ip address 172.152.59.129 255.255.252 clock rate 64000 !
```

```
interface Serial 1/1 ip address
172.152.59.141 255.255.255.252
interface Serial1/2
ip address 172.152.59.146 255.255.255.252 clock
rate 64000
interface Serial1/3
no ip address clock
rate 2000000
shutdown
interface Serial 1/4
no ip address clock
rate 2000000
shutdown
interface Serial 1/5
no ip address clock
rate 2000000
shutdown
interface Serial 1/6
no ip address clock
rate 2000000
shutdown
interface Serial 1/7
no ip address clock
rate 2000000
shutdown
router rip version 2 passive-
interface FastEthernet0/0
passive-interface FastEthernet0/1
network 172.152.0.0 default-
information originate no auto-
summary
ip classless
ip route 172.152.59.0 255.255.255.128 172.152.59.130 ip
route 172.152.52.0 255.255.252.0 172.152.59.130
ip route 0.0.0.0 0.0.0.0 Serial 1/1 ip route 0.0.0.0
0.0.0.0 172.152.59.147 ip route 172.152.0.0
```

Router 7:

```
interface FastEthernet0/0 ip address 172.152.32.1 255.255.248.0 duplex auto speed auto ! interface FastEthernet0/1 ip address 172.152.58.1 255.255.255.0 duplex auto speed auto ! interface Serial1/0 ip address 172.152.59.134 255.255.252 clock rate 64000 !
```

```
interface Serial 1/1 ip address
172.152.59.142 255.255.255.252 clock rate
64000
interface Serial1/2
no ip address clock
rate 2000000
shutdown
interface Serial 1/3
no ip address clock
rate 2000000
shutdown
interface Serial 1/4
no ip address clock
rate 2000000
shutdown
interface Serial 1/5
no ip address clock
rate 2000000
shutdown
interface Serial 1/6
no ip address clock
rate 2000000
shutdown
interface Serial 1/7 no
ip address clock rate
2000000 shutdown
! router rip version 2 passive-
interface FastEthernet0/0
passive-interface FastEthernet0/1
network 172.152.0.0 default-
information originate no auto-
summary
ip classless ip route 0.0.0.0
0.0.0.0 Serial 1/0 ip route
0.0.0.0 0.0.0.0 Serial 1/1
ip flow-export version 9
```

```
!
!
!
!
!
!
!
!
!
!
line con 0
!
line aux 0
!
line vty 0 4 login
!
!
end
```

Router 8:

```
interface FastEthernet0/0 ip address
172.152.52.1 255.255.252.0 duplex
auto speed auto
interface FastEthernet0/1 ip address
172.152.59.1 255.255.255.128 duplex
auto
speed auto
interface Serial 1/0 ip address
172.152.59.130 255.255.255.252
interface Serial 1/1 ip address
172.152.59.137 255.255.255.252 clock rate
64000
interface Serial1/2
no ip address clock
rate 2000000
shutdown
```

```
interface Serial 1/3
no ip address clock
rate 2000000
shutdown
interface Serial 1/4
no ip address clock
rate 2000000
shutdown
interface Serial 1/5
no ip address clock
rate 2000000
shutdown
interface Serial 1/6
no ip address clock
rate 2000000
shutdown
interface Serial 1/7
no ip address clock
rate 2000000
shutdown
ip classless
ip route 172.152.56.0 255.255.254.0 172.152.59.129
ip route 172.152.48.0 255.255.252.0 172.152.59.129
ip route 0.0.0.0 0.0.0.0 172.152.59.138 ip route
172.152.0.0 255.255.224.0 172.152.59.138 ip route
172.152.40.0 255.255.248.0 172.152.59.138 ip
route 0.0.0.0 0.0.0.0 172.152.59.129
```

```
ip flow-export version 9
line con 0
line aux 0
line vty 0 4 login
end Router
9:
interface FastEthernet0/0 ip address
172.152.0.1 255.255.224.0 duplex
auto speed auto
interface FastEthernet0/1 ip address
172.152.40.1 255.255.248.0 duplex
auto speed auto
interface Serial 1/0 ip address
172.152.59.133 255.255.255.252
interface Serial 1/1 ip address
172.152.59.138 255.255.255.252
interface Serial 1/2 ip address
172.152.59.145 255.255.255.252
interface Serial 1/3
no ip address clock
rate 2000000
shutdown
interface Serial1/4
no ip address clock
```

!

```
rate 2000000
shutdown
interface Serial 1/5
no ip address clock
rate 2000000
shutdown
interface Serial 1/6
no ip address clock
rate 2000000
shutdown
interface Serial 1/7
no ip address clock
rate 2000000
shutdown
router rip version 2 passive-
interface FastEthernet0/0
passive-interface FastEthernet0/1
network 172.152.0.0 default-
information originate no auto-
summary
ip classless ip route 0.0.0.0 0.0.0.0 Serial 1/0 ip route
0.0.0.0 0.0.0.0 172.152.59.137 ip route 172.152.59.0
255.255.255.128 172.152.59.137 ip route
172.152.52.0 255.255.252.0 172.152.59.137 ip route
0.0.0.0 0.0.0.0 172.152.59.146 ip route 0.0.0.0 0.0.0.0
172.152.59.130 ip route 172.152.56.0 255.255.254.0
172.152.59.146 ip route 172.152.48.0 255.255.252.0
172.152.59.146 ip route 172.152.56.0 255.255.254.0
172.152.59.134 5 ip route 172.152.48.0 255.255.252.0
172.152.59.134 5
ip route 0.0.0.0 0.0.0.0 172.152.59.134
ip flow-export version 9
```

```
!
line con 0
line aux 0
! line vty 0
4 login
!
end The
Rocks:
interface Vlan1 no
ip address
shutdown
!
line con 0
! line vty 0
4 login line
vty 5 15
login
!
!
end The
Reach:
interface Vlan1 no
ip address
shutdown
line con 0
line vty 0 4
login line
```

```
vty 5 15 login ! ! ! ! ! end
```

The drone:

```
interface Vlan1 no
ip address
shutdown
!
!
!
!
line con 0
! line vty 0
4 login line
vty 5 15
login
!
!
!
```

The Iron Island:

!

The Mountain and Vale:

```
interface Vlan1 no
ip address
shutdown
!
!
!
!
line con 0
! line vty 0
4 login line
vty 5 15
login
!
!
```

Beyond The Wall:

!

The North: