# 第10章 IP访问列表

# 10.1 利用 IP 标准访问列表进行网络流量的控制

#### 【实验名称】

编号的标准 IP 访问列表。

#### 【实验目的】

掌握路由器上编号的标准 IP 访问列表规则及配置。

#### 【背景描述】

你是一个公司的网络管理员,公司的经理部、财务部门和销售部门分属不同的3个网 段,三部门之间用路由器进行信息传递,为了安全起见,公司领导要求销售部门不能对财 务部门进行访问, 但经理部可以对财务部门进行访问。

PC1 代表经理部的主机,PC2 代表销售部门的主机、PC3 代表财务部门的主机。

#### 【技术原理】

IP ACL (IP 访问控制列表或 IP 访问列表)是实现对流经路由器或交换机的数据包根 据一定的规则进行过滤,从而提高网络可管理性和安全性。 IP ACL 分为两种:标准 IP 访问列表和扩展 IP 访问列表。

标准 IP 访问列表可以根据数据包的源 IP 地址定义规则,进行数据包的过滤。

扩展 IP 访问列表可以根据数据包的源 IP、目的 IP、源端口、目的端口、协议来定义 规则,进行数据包的过滤。

IP ACL 基于接口进行规则的应用,分为:入栈应用和出栈应用。

入栈应用是指由外部经该接口进行路由器的数据包进行过滤。

出栈应用是指路由器从该接口向外转发数据时进行数据包的过滤。

IP ACL 的配置有两种方式:按照编号的访问列表,按照命名的访问列表。

标准 IP 访问列表编号范围是 1~99、1300~1999, 扩展 IP 访问列表编号范围是 100~199、 2000~2699。 【实现功能】

实现网段间互相访问的安全控制。

## 实验设备】

R1762 路由器(两台)、V.35 线缆(1条)、直连线或交叉线(3条)

【实验拓扑】




图 28

个网 对财

根

#### 【实验步骤】

步骤1. 基本配置。

#### ○ Router1 基本配置

#### Red-Giant>enable

Red-Giant#configure terminal

Red-Giant (config) #hostname Router1

Router1(config)# interface fastEthernet 1/0

Router1(config-if)#ip add 172.16.1.1 255.255.255.0

Router1 (config-if) #no shutdown

Router1(config-if)# interface fastEthernet 1/1

Router1(config-if) #ip add 172.16.2.1 255.255.255.0

Router1(config-if) #no shutdown

Router1(config-if)#interface serial 1/2

Router1(config-if) #ip add 172.16.3.1 255.255.255.0

Router1(config-if)#clock rate 64000

Router1(config-if) #no shutdown

Router1 (config-if) #end

#### 测试命令: show ip interface brief。

Router1#show ip int brief		!观察接□状态	
Interface	IP-Address(Pri)	OK?	Status
serial 1/2	172.16.3.1/24	YES	UP
serial 1/3	no address	YES	DOWN
FastEthernet 1/0	172.16.1.1/24	YES	UP
FastEthernet 1/1	172.16.2.1/24	YES	UP

Null 0

no address

YES

### ○ Router2基本配置

#### Red-Giant>enable

Red-Giant#configure terminal

Red-Giant(config)#hostname Router2

Router2(config) # interface fastEthernet 1/0

Router2(config-if) #ip add 172.16.4.1 255.255.255.0

Router2(config-if) #no shutdown

Router2(config-if)#exit

Router2(config-if)#interface serial 1/2

Router2(config-if) #ip add 172.16.3.1 255.255.255.0

Router2(config-if)#no shutdown

Router2(config-if)#end

## 测试命令: show ip interface brief。

# Router2#show ip int brief

!查看路由表信息

Interface	Inc brief			
serial 1/2	IP-Address(Pri)	Otto	!观察接[	J
	172.16.3.2/24	OK?	Status	
		YES	UP	
FastEth		YES	DOWN	
Null a		YES	UP	
		YES	DOFFE	
₩ 配置静态路由	no address	YES		
FastEthernet 1/0 FastEthernet 1/1 Null 0 配置静态路由	no address 172.16.4.1/24 no address no address	YES YES YES	UP	

Router1(config)#ip route 172.16.4.0 255.255.255.0 serial 1/2 Router2(config)#ip route 172.16.1.0 255.255.255.0 serial 1/2 Router2(config) #ip route 172.16.2.0 255.255.255.0 serial 1/2

测试命令: show ip route。

## Router1#show ip route

Codes: C - connected, S - static, R - RIP

O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2 \* - candidate default

Gateway of last resort is no set

- C 172.16.1.0/24 is directly connected, FastEthernet 1/0 C 172.16.1.1/32 is local host.
- C 172.16.2.0/24 is directly connected, FastEthernet 1/1 172.16.2.1/32 is local host.

```
第10章 IP访问列表
       c 172.16.3.0/24 is directly connected, serial 1/2
       c 172.16.3.1/32 is local host.
          172.16.4.0/24 is directly connected, serial 1/2
       Router2#show ip route
       codes: C - connected, S - static, R - RIP
           O - OSPF, IA - OSPF inter area
           N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
           El - OSPF external type 1, E2 - OSPF external type 2
     Gateway of last resort is no set
        172.16.1.0/24 is directly connected, serial 1/2
        172.16.2.0/24 is directly connected, serial 1/2
     c 172.16.3.0/24 is directly connected, serial 1/2
       172.16.3.2/32 is local host.
       172.16.4.0/24 is directly connected, FastEthernet 1/0
    c 172.16.4.1/32 is local host.
  步骤2. 配置标准 IP 访问控制列表。
    Router2(config) #access-list 1 deny 172.16.2.0 0.0.0.255
      ! 拒绝来自 172.16.2.0 网段的流量通过
   Router2(config) #access-list 1 permit 172.16.1.0 0.0.0.255
    ! 允许来自 172.16.1.0 网段的流量通过
   验证测试:
   Router2#show access-lists 1
   Standard IP access list 1 includes 2 items:
     deny 172.16.2.0, wildcard bits 0.0.0.255
     permit 172.16.1.0, wildcard bits 0.0.0.255
步骤3. 把访问控制列表在接口下应用。
  Router2(config) # interface fastEthernet 1/0
  Router2(config-if)#ip access-group 1 out ! 在接口下访问控制列表出栈流量调用
 Router2#show ip interface fastEthernet 1/0
 FastEthernet 1/0
  IP interface state is: UP
  IP interface type is: BROADCAST
  IP interface MTU is: 1500
  IP address is:
   172.16.4.1/24 (primary)
```

态

```
IP address negotiate is: OFF
   Forward direct-boardcast is: ON
   ICMP mask reply is: ON
   Send ICMP redirect is: ON
  Send ICMP unreachabled is: ON
  DHCP relay is: OFF
 Fast switch is: ON
 Route horizontal-split is: ON
 Help address is: 0.0.0.0
 Proxy ARP is: ON
Outgoing access list is 1.
Inbound access list is not set.
```

!查看访问列表在接口上的<sub>应用</sub>

#### 步骤4. 验证测试。

ping(172.16.2.0 网段的主机不能 ping 通 172.16.4.0 网段的主机: 172.16.1.0 网段的主 机能 ping 通 172.16.4.0 网段的主机)。 【注意事项】

- 1、注意在访问控制列表的网络掩码是反掩码。
- 2、标准控制列表要应用在尽量靠近目的地址的接口。

### 【参考配置】

```
Router1#show running-config
Building configuration...
```

```
!查看路由器 1 的全部配置
```

```
Current configuration : 544 bytes
    version 8.32 (building 53)
    hostname Router1
   interface serial 1/2
   ip address 172.16.3.1 255.255.255.0
  clock rate 64000
 interface serial 1/3
 clock rate 64000
interface FastEthernet 1/0
```