Machine-Level Programming I: Basics

Introduction to Computer Systems 4th Lecture, Sep. 21, 2016

Instructors:

Xiangqun Chen , Junlin Lu Guangyu Sun , Xuetao Guan Shiliang Zhang

Today: Machine Programming I: Basics

- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations

Intel x86 Processors

Dominate laptop/desktop/server market

Evolutionary design

- Backwards compatible up until 8086, introduced in 1978
- Added more features as time goes on

Complex instruction set computer (CISC)

- Many different instructions with many different formats
 - But, only small subset encountered with Linux programs
- Hard to match performance of Reduced Instruction Set Computers (RISC)
- But, Intel has done just that!
 - In terms of speed. Less so for low power.

Intel x86 Evolution: Milestones

Name Date Transistors MHz

■ 8086 1978 29K 5-10

■ First 16-bit Intel processor. Basis for IBM PC & DOS

1MB address space

■ 386 1985 275K 16-33

First 32 bit Intel processor, referred to as IA32

Added "flat addressing", capable of running Unix

■ Pentium 4E 2004 125M 2800-3800

First 64-bit Intel x86 processor, referred to as x86-64

■ Core 2 2006 291M 1060-3500

First multi-core Intel processor


■ Core i7 2008 731M 1700-3900

Four cores (our shark machines)

Intel x86 Processors, cont.

Machine Evolution

| 386 | 1985 | 0.3M |
|-------------|------|------|
| Pentium | 1993 | 3.1M |
| Pentium/MMX | 1997 | 4.5M |
| PentiumPro | 1995 | 6.5M |
| Pentium III | 1999 | 8.2M |
| Pentium 4 | 2001 | 42M |
| Core 2 Duo | 2006 | 291M |
| Core i7 | 2008 | 731M |



Added Features

- Instructions to support multimedia operations
- Instructions to enable more efficient conditional operations
- Transition from 32 bits to 64 bits
- More cores

2015 State of the Art


Core i7 Broadwell 2015

Desktop Model

- 4 cores
- Integrated graphics
- 3.3-3.8 GHz
- **65W**

Server Model

- 8 cores
- Integrated I/O
- 2-2.6 GHz
- **45W**



x86 Clones: Advanced Micro Devices (AMD)

Historically

- AMD has followed just behind Intel
- A little bit slower, a lot cheaper

Then

- Recruited top circuit designers from Digital Equipment Corp. and other downward trending companies
- Built Opteron: tough competitor to Pentium 4
- Developed x86-64, their own extension to 64 bits

Recent Years

- Intel got its act together
 - Leads the world in semiconductor technology
- AMD has fallen behind
 - Relies on external semiconductor manufacturer

Intel's 64-Bit History

- 2001: Intel Attempts Radical Shift from IA32 to IA64
 - Totally different architecture (Itanium)
 - Executes IA32 code only as legacy
 - Performance disappointing
- 2003: AMD Steps in with Evolutionary Solution
 - x86-64 (now called "AMD64")
- Intel Felt Obligated to Focus on IA64
 - Hard to admit mistake or that AMD is better
- 2004: Intel Announces EM64T extension to IA32
 - Extended Memory 64-bit Technology
 - Almost identical to x86-64!
- All but low-end x86 processors support x86-64
 - But, lots of code still runs in 32-bit mode

Our Coverage

■ IA32

- The traditional x86
- For this course: RIP, Fall 2016

■ x86-64

- The standard
- Server> gcc hello.c
- Server> qcc -m64 hello.c

Presentation

- Book covers x86-64
- Web aside on IA32
- We will only cover x86-64

Today: Machine Programming I: Basics

- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations

Definitions

- Architecture: (also ISA: instruction set architecture) The parts of a processor design that one needs to understand or write assembly/machine code.
 - Examples: instruction set specification, registers.
- Microarchitecture: Implementation of the architecture.
 - Examples: cache sizes and core frequency.


Code Forms:

- Machine Code: The byte-level programs that a processor executes
- Assembly Code: A text representation of machine code

Example ISAs:

- Intel: x86, IA32, Itanium, x86-64
- ARM: Used in almost all mobile phones

Assembly/Machine Code View



Programmer-Visible State


- PC: Program counter
 - Address of next instruction
 - Called "RIP" (x86-64)
- Register file
 - Heavily used program data
- Condition codes
 - Store status information about most recent arithmetic or logical operation
 - Used for conditional branching

Memory

- Byte addressable array
- Code and user data
- Stack to support procedures

Turning C into Object Code

- Code in files p1.c p2.c
- Compile with command: gcc -Og p1.c p2.c -o p
 - Use basic optimizations (-Og) [New to recent versions of GCC]
 - Put resulting binary in file p



Compiling Into Assembly

C Code (sum.c)

Generated x86-64 Assembly

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

Obtain (on shark machine) with command

```
gcc -Og -S sum.c
```

Produces file sum.s

Warning: Will get very different results on non-Shark machines (Andrew Linux, Mac OS-X, ...) due to different versions of gcc and different compiler settings.

Assembly Characteristics: Data Types

- "Integer" data of 1, 2, 4, or 8 bytes
 - Data values
 - Addresses (untyped pointers)
- **■** Floating point data of 4, 8, or 10 bytes
- Code: Byte sequences encoding series of instructions
- No aggregate types such as arrays or structures
 - Just contiguously allocated bytes in memory

Assembly Characteristics: Operations

- Perform arithmetic function on register or memory data
- Transfer data between memory and register
 - Load data from memory into register
 - Store register data into memory
- Transfer control
 - Unconditional jumps to/from procedures
 - Conditional branches

Object Code

Code for sumstore

0x0400595: 0x53 0x48 0x89 0xd3 0xe8 0xf2 0xff 0xff

0xff

0x48

0x5b

0xc3

- Total of 14 bytes
- 0x89 Each instruction 0x03 1, 3, or 5 bytes
 - Starts at address 0x0400595

Assembler

- Translates .s into .o
- Binary encoding of each instruction
- Nearly-complete image of executable code
- Missing linkages between code in different files

Linker

- Resolves references between files
- Combines with static run-time libraries
 - E.g., code for malloc, printf
- Some libraries are dynamically linked
 - Linking occurs when program begins execution

Machine Instruction Example

0x40059e: 48 89 03

C Code

Store value t where designated by dest

Assembly

- Move 8-byte value to memory
 - Quad words in x86-64 parlance
- Operands:

t: Register %rax

dest: Register %rbx

*dest: Memory M[%rbx]

Object Code

- 3-byte instruction
- Stored at address 0x40059e

Disassembling Object Code

Disassembled

```
0000000000400595 <sumstore>:
 400595:
          53
                           push
                                  %rbx
 400596: 48 89 d3
                                  %rdx,%rbx
                           mov
 400599: e8 f2 ff ff ff callq 400590 <plus>
 40059e: 48 89 03
                                  %rax, (%rbx)
                           mov
 4005a1:
          5b
                                  %rbx
                           pop
 4005a2: c3
                           retq
```

Disassembler

```
objdump -d sum
```

- Useful tool for examining object code
- Analyzes bit pattern of series of instructions
- Produces approximate rendition of assembly code
- Can be run on either a .out (complete executable) or .o file

Alternate Disassembly

Object

Disassembled

```
0 \times 0400595:
    0 \times 53
    0 \times 48
    0x89
    0xd3
    0xe8
    0xf2
    0xff
    Oxff
    0xff
    0x48
    0x89
    0 \times 03
    0x5b
    0xc3
```

```
Dump of assembler code for function sumstore:
    0x00000000000400595 <+0>: push %rbx
    0x0000000000400596 <+1>: mov %rdx,%rbx
    0x0000000000400599 <+4>: callq 0x400590 <plus>
    0x000000000040059e <+9>: mov %rax,(%rbx)
    0x00000000004005a1 <+12>:pop %rbx
    0x000000000004005a2 <+13>:retq
```

Within gdb Debugger

```
gdb sum disassemble sumstore
```

Disassemble procedure

```
x/14xb sumstore
```

Examine the 14 bytes starting at sumstore

What Can be Disassembled?

```
% objdump -d WINWORD.EXE
WINWORD.EXE: file format pei-i386
No symbols in "WINWORD.EXE".
Disassembly of section .text:
30001000 <.text>:
30001000:
30001001:
               Reverse engineering forbidden by
30001003:
             Microsoft End User License Agreement
30001005:
3000100a:
```

- Anything that can be interpreted as executable code
- Disassembler examines bytes and reconstructs assembly source

Today: Machine Programming I: Basics


- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations

x86-64 Integer Registers

| %rax | %eax | % r8 | %r8d |
|------|------|-------------|-------|
| %rbx | %ebx | %r9 | %r9d |
| %rcx | %ecx | %r10 | %r10d |
| %rdx | %edx | %r11 | %r11d |
| %rsi | %esi | %r12 | %r12d |
| %rdi | %edi | %r13 | %r13d |
| %rsp | %esp | %r14 | %r14d |
| %rbp | %ebp | %r15 | %r15d |

Can reference low-order 4 bytes (also low-order 1 & 2 bytes)

Some History: IA32 Registers



Origin (mostly obsolete)

accumulate

counter

data

base

source index

destination index

stack pointer base pointer

Moving Data

Moving Data movq Source, Dest:

Operand Types

- Immediate: Constant integer data
 - Example: \$0x400, \$-533
 - Like C constant, but prefixed with \\$'
 - Encoded with 1, 2, or 4 bytes
- **Register:** One of 16 integer registers
 - Example: %rax, %r13
 - But %rsp reserved for special use
 - Others have special uses for particular instructions
- Memory: 8 consecutive bytes of memory at address given by register
 - Simplest example: (%rax)
 - Various other "address modes"

```
%rax
%rcx
%rdx
%rbx
%rsi
%rdi
%rsp
%rbp
```

%rN

movq Operand Combinations

```
Source Dest Src, Dest
             C Analog
```

Cannot do memory-memory transfer with a single instruction

Simple Memory Addressing Modes

- Normal (R) Mem[Reg[R]]
 - Register R specifies memory address
 - Aha! Pointer dereferencing in C

```
movq (%rcx),%rax
```


- Displacement D(R) Mem[Reg[R]+D]
 - Register R specifies start of memory region
 - Constant displacement D specifies offset

```
movq 8(%rbp),%rdx
```

Example of Simple Addressing Modes

```
void swap
    (long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```

void swap (long *xp, long *yp) { long t0 = *xp; long t1 = *yp; *xp = t1; *yp = t0; }




| Register | Value |
|----------|-------|
| %rdi | хр |
| %rsi | ур |
| %rax | t0 |
| %rdx | t1 |

Registers


| %rdi | 0x120 |
|------|-------|
| %rsi | 0x100 |
| %rax | |
| %rdx | |

Memory




swap:


```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```




swap:

```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```







Simple Memory Addressing Modes

- Normal (R) Mem[Reg[R]]
 - Register R specifies memory address
 - Aha! Pointer dereferencing in C

```
movq (%rcx),%rax
```

- Displacement D(R) Mem[Reg[R]+D]
 - Register R specifies start of memory region
 - Constant displacement D specifies offset

```
movq 8(%rbp),%rdx
```

Complete Memory Addressing Modes

Most General Form

D(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]+D]

D: Constant "displacement" 1, 2, or 4 bytes

Rb: Base register: Any of 16 integer registers

Ri: Index register: Any, except for %rsp

S: Scale: 1, 2, 4, or 8 (why these numbers?)

Special Cases

(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]]

D(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]+D]

(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]]

Address Computation Examples

| %rdx | 0xf000 |
|------|--------|
| %rcx | 0x0100 |

| Expression | Address Computation | Address |
|---------------|---------------------|---------|
| 0x8(%rdx) | 0xf000 + 0x8 | 0xf008 |
| (%rdx,%rcx) | 0xf000 + 0x100 | 0xf100 |
| (%rdx,%rcx,4) | 0xf000 + 4*0x100 | 0xf400 |
| 0x80(,%rdx,2) | 2*0xf000 + 0x80 | 0x1e080 |

Today: Machine Programming I: Basics

- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations

Address Computation Instruction

■ leaq Src, Dst

- Src is address mode expression
- Set Dst to address denoted by expression

Uses

- Computing addresses without a memory reference
 - E.g., translation of p = &x[i];
- Computing arithmetic expressions of the form x + k*y
 - k = 1, 2, 4, or 8

Example

```
long m12(long x)
{
   return x*12;
}
```

Converted to ASM by compiler:

```
leaq (%rdi,%rdi,2), %rax # t <- x+x*2
salq $2, %rax # return t<<2</pre>
```

Some Arithmetic Operations

Two Operand Instructions:

| Format | Computation | | |
|--------|-------------|--------------------|------------------|
| addq | Src,Dest | Dest = Dest + Src | |
| subq | Src,Dest | Dest = Dest – Src | |
| imulq | Src,Dest | Dest = Dest * Src | |
| salq | Src,Dest | Dest = Dest << Src | Also called shiq |
| sarq | Src,Dest | Dest = Dest >> Src | Arithmetic |
| shrq | Src,Dest | Dest = Dest >> Src | Logical |
| xorq | Src,Dest | Dest = Dest ^ Src | |
| andq | Src,Dest | Dest = Dest & Src | |
| orq | Src,Dest | Dest = Dest Src | |

- Watch out for argument order!
- No distinction between signed and unsigned int (why?)

Some Arithmetic Operations

One Operand Instructions

```
incq Dest Dest = Dest + 1

decq Dest Dest = Dest - 1

negq Dest Dest = -Dest

notq Dest Dest = \sim Dest
```

See book for more instructions

Arithmetic Expression Example

```
long arith
(long x, long y, long z)
{
  long t1 = x+y;
  long t2 = z+t1;
  long t3 = x+4;
  long t4 = y * 48;
  long t5 = t3 + t4;
  long rval = t2 * t5;
  return rval;
}
```

```
arith:
  leaq (%rdi,%rsi), %rax
  addq %rdx, %rax
  leaq (%rsi,%rsi,2), %rdx
  salq $4, %rdx
  leaq 4(%rdi,%rdx), %rcx
  imulq %rcx, %rax
  ret
```

Interesting Instructions

- leaq: address computation
- **salq**: shift
- imulq: multiplication
 - But, only used once

Understanding Arithmetic Expression Example

```
long arith
(long x, long y, long z)
  long t1 = x+y;
  long t2 = z+t1;
  long t3 = x+4;
  long t4 = y * 48;
  long t5 = t3 + t4;
  long rval = t2 * t5;
  return rval;
```

```
arith:
  leaq (%rdi,%rsi), %rax # t1
  addq %rdx, %rax # t2
  leaq (%rsi,%rsi,2), %rdx
  salq $4, %rdx # t4
  leaq 4(%rdi,%rdx), %rcx # t5
  imulq %rcx, %rax # rval
  ret
```

| Register | Use(s) |
|----------|-------------------|
| %rdi | Argument x |
| %rsi | Argument y |
| %rdx | Argument z |
| %rax | t1, t2, rval |
| %rdx | t4 |
| %rcx | t5 |

Machine Programming I: Summary

History of Intel processors and architectures

Evolutionary design leads to many quirks and artifacts

C, assembly, machine code

- New forms of visible state: program counter, registers, ...
- Compiler must transform statements, expressions, procedures into low-level instruction sequences

Assembly Basics: Registers, operands, move

 The x86-64 move instructions cover wide range of data movement forms

Arithmetic

 C compiler will figure out different instruction combinations to carry out computation