NOTE

When we use the term "dynamically" in this chapter, we mean using reflection to perform some task whose type safety is enforced only at runtime. This is similar in principle to *dynamic binding* via C#'s dynamic keyword, although the mechanism and functionality is different.

Dynamic binding is much easier to use and employs the Dynamic Language Runtime (DLR) for dynamic language interoperability. Reflection is relatively clumsy to use, but it is more flexible in terms of what you can do with the CLR. For instance, reflection lets you obtain lists of types and members, instantiate an object whose name comes from a string, and build assemblies on the fly.

Reflecting and Activating Types

In this section, we examine how to obtain a Type, inspect its metadata, and use it to dynamically instantiate an object.

Obtaining a Type

An instance of System. Type represents the metadata for a type. Because Type is widely used, it lives in the System namespace rather than the System. Reflection namespace.

You can get an instance of a System. Type by calling GetType on any object or with C#'s typeof operator:

```
Type t1 = DateTime.Now.GetType();  // Type obtained at runtime
Type t2 = typeof (DateTime);  // Type obtained at compile time
```

You can use typeof to obtain array types and generic types, as follows:

You can also retrieve a Type by name. If you have a reference to its Assembly, call Assembly. GetType (we describe this further in the section

"Reflecting Assemblies"):

```
Type t = Assembly.GetExecutingAssembly().GetType ("Demos.TestProgram");
```

If you don't have an Assembly object, you can obtain a type through its assembly qualified name (the type's full name followed by the assembly's fully or partially qualified name). The assembly implicitly loads as if you called Assembly.Load(string):

```
Type t = Type.GetType ("System.Int32, System.Private.CoreLib");
```

After you have a System. Type object, you can use its properties to access the type's name, assembly, base type, visibility, and so on:

```
Type stringType = typeof (string);
string name = stringType.Name;  // String
Type baseType = stringType.BaseType;  // typeof(Object)
Assembly assem = stringType.Assembly;  // System.Private.CoreLib
bool isPublic = stringType.IsPublic;  // true
```

A System. Type instance is a window into the entire metadata for the type —and the assembly in which it's defined.

NOTE

System. Type is abstract, so the typeof operator must actually give you a subclass of Type. The subclass that the CLR uses is internal to .NET and is called RuntimeType.

TypeInfo

Should you target .NET Core 1.x (or an older Windows Store profile), you'll find most of Type's members are missing. These missing members are exposed instead on a class called TypeInfo, which you obtain by calling GetTypeInfo. So, to get our previous example to run, you would do this:

```
Type stringType = typeof(string);
string name = stringType.Name;
Type baseType = stringType.GetTypeInfo().BaseType;
Assembly assem = stringType.GetTypeInfo().Assembly;
bool isPublic = stringType.GetTypeInfo().IsPublic;
```

TypeInfo also exists in .NET Core 2 and 3 and .NET 5+ (and .NET Framework 4.5+ and all .NET Standard versions), so the preceding code works almost universally. TypeInfo also includes additional properties and methods for reflecting over members.

Obtaining array types

As we just saw, typeof and GetType work with array types. You can also obtain an array type by calling MakeArrayType on the *element* type:

```
Type simpleArrayType = typeof (int).MakeArrayType();
Console.WriteLine (simpleArrayType == typeof (int[]));  // True
```

You can create multidimensional arrays by passing an integer argument to MakeArrayType:

```
Type cubeType = typeof (int).MakeArrayType (3);  // cube shaped
Console.WriteLine (cubeType == typeof (int[,,]));  // True
```

GetElementType does the reverse: it retrieves an array type's element type:

```
Type e = typeof (int[]).GetElementType();  // e == typeof (int)
```

GetArrayRank returns the number of dimensions of a rectangular array:

```
int rank = typeof (int[,,]).GetArrayRank(); // 3
```

Obtaining nested types

To retrieve nested types, call GetNestedTypes on the containing type:

```
foreach (Type t in typeof (System.Environment).GetNestedTypes())
  Console.WriteLine (t.FullName);
```

```
OUTPUT: System.Environment+SpecialFolder
```

Or:

The one caveat with nested types is that the CLR treats a nested type as having special "nested" accessibility levels:

Type Names

A type has Namespace, Name, and FullName properties. In most cases, FullName is a composition of the former two:

```
Type t = typeof (System.Text.StringBuilder);

Console.WriteLine (t.Namespace);  // System.Text
Console.WriteLine (t.Name);  // StringBuilder
Console.WriteLine (t.FullName);  // System.Text.StringBuilder
```

There are two exceptions to this rule: nested types and closed generic types.

NOTE

Type also has a property called AssemblyQualifiedName, which returns FullName followed by a comma and then the full name of its assembly. This is the same string that you can pass to Type.GetType, and it uniquely identifies a type within the default loading context.

Nested type names

With nested types, the containing type appears only in FullName:

```
Type t = typeof (System.Environment.SpecialFolder);

Console.WriteLine (t.Namespace);  // System
Console.WriteLine (t.Name);  // SpecialFolder
Console.WriteLine (t.FullName);  // System.Environment+SpecialFolder
```

The + symbol differentiates the containing type from a nested namespace.

Generic type names

Generic type names are suffixed with the 'symbol, followed by the number of type parameters. If the generic type is unbound, this rule applies to both Name and FullName:

```
Type t = typeof (Dictionary<,>); // Unbound
Console.WriteLine (t.Name); // Dictionary'2
Console.WriteLine (t.FullName); // System.Collections.Generic.Dictionary'2
```

If the generic type is closed, however, FullName (only) acquires a substantial extra appendage. Each type parameter's full *assembly qualified name* is enumerated:

```
Console.WriteLine (typeof (Dictionary<int,string>).FullName);

// OUTPUT:
System.Collections.Generic.Dictionary`2[[System.Int32,
System.Private.CoreLib, Version=4.0.0.0, Culture=neutral,
PublicKeyToken=7cec85d7bea7798e],[System.String, System.Private.CoreLib,
Version=4.0.0.0, Culture=neutral, PublicKeyToken=7cec85d7bea7798e]]
```

This ensures that AssemblyQualifiedName (a combination of the type's full name and assembly name) contains enough information to fully identify both the generic type and its type parameters.

Array and pointer type names

Arrays present with the same suffix that you use in a typeof expression:

```
Console.WriteLine (typeof ( int[] ).Name);  // Int32[]
Console.WriteLine (typeof ( int[,] ).Name);  // Int32[,]
```

```
Console.WriteLine (typeof ( int[,] ).FullName); // System.Int32[,]
```

Pointer types are similar:

```
Console.WriteLine (typeof (byte*).Name); // Byte*
```

ref and out parameter type names

A Type describing a ref or out parameter has an & suffix:

```
public void RefMethod (ref int p)
{
   Type t = MethodInfo.GetCurrentMethod().GetParameters()[0].ParameterType;
   Console.WriteLine (t.Name); // Int32&
}
```

More on this later, in the section "Reflecting and Invoking Members".

Base Types and Interfaces

Type exposes a BaseType property:

```
Type base1 = typeof (System.String).BaseType;
Type base2 = typeof (System.IO.FileStream).BaseType;
Console.WriteLine (base1.Name);  // Object
Console.WriteLine (base2.Name);  // Stream
```

The GetInterfaces method returns the interfaces that a type implements:

```
foreach (Type iType in typeof (Guid).GetInterfaces())
   Console.WriteLine (iType.Name);

IFormattable
IComparable
IComparable'1
IEquatable'1
```

(The GetInterfaceMap method returns a struct that shows how each member of an interface is implemented in a class or struct—we illustrate a

use for this advanced feature in "Calling Static Virtual/Abstract Interface Members".)

Reflection provides three dynamic equivalents to C#'s static is operator:

IsInstanceOfType

Accepts a type and instance

IsAssignableFrom and (from .NET 5) IsAssignableTo

Accepts two types

Here's an example of the first:

```
object obj = Guid.NewGuid();
Type target = typeof (IFormattable);
bool isTrue = obj is IFormattable;  // Static C# operator
bool alsoTrue = target.IsInstanceOfType (obj);  // Dynamic equivalent
```

IsAssignableFrom is more versatile:

```
Type target = typeof (IComparable), source = typeof (string);
Console.WriteLine (target.IsAssignableFrom (source));  // True
```

The IsSubclassOf method works on the same principle as IsAssignableFrom but excludes interfaces.

Instantiating Types

There are two ways to dynamically instantiate an object from its type:

- Call the static Activator. CreateInstance method
- Call Invoke on a ConstructorInfo object obtained from calling GetConstructor on a Type (advanced scenarios)

Activator. CreateInstance accepts a Type and optional arguments that it passes to the constructor:

CreateInstance lets you specify many other options such as the assembly from which to load the type and whether to bind to a nonpublic constructor. A MissingMethodException is thrown if the runtime can't find a suitable constructor.

Calling Invoke on a ConstructorInfo is necessary when your argument values can't disambiguate between overloaded constructors. For example, suppose that class X has two constructors: one accepting a parameter of type string and another accepting a parameter of type StringBuilder. The target is ambiguous should you pass a null argument into Activator.CreateInstance. This is when you need to use a ConstructorInfo, instead:

```
// Fetch the constructor that accepts a single parameter of type string:
ConstructorInfo ci = typeof (X).GetConstructor (new[] { typeof (string) });
// Construct the object using that overload, passing in null:
object foo = ci.Invoke (new object[] { null });
```

Or, if you're targeting .NET Core 1, an older Windows Store profile:

```
ConstructorInfo ci = typeof (X).GetTypeInfo().DeclaredConstructors
   .FirstOrDefault (c =>
        c.GetParameters().Length == 1 &&
        c.GetParameters()[0].ParameterType == typeof (string));
```

To obtain a nonpublic constructor, you need to specify BindingFlags—see "Accessing Nonpublic Members" in the later section "Reflecting and Invoking Members".

WARNING

Dynamic instantiation adds a few microseconds onto the time taken to construct the object. This is quite a lot in relative terms because the CLR is ordinarily very fast in instantiating objects (a simple new on a small class takes in the region of tens of nanoseconds).

To dynamically instantiate arrays based on just element type, first call MakeArrayType. You can also instantiate generic types: we describe this in the next section.

To dynamically instantiate a delegate, call Delegate. CreateDelegate. The following example demonstrates instantiating both an instance delegate and a static delegate:

You can invoke the Delegate object that's returned by calling DynamicInvoke, as we did in this example, or by casting to the typed delegate:

```
IntFunc f = (IntFunc) staticD;
Console.WriteLine (f(3));  // 9 (but much faster!)
```

You can pass a MethodInfo into CreateDelegate instead of a method name. We describe MethodInfo shortly, in "Reflecting and Invoking Members", along with the rationale for casting a dynamically created delegate back to the static delegate type.

Generic Types

A Type can represent a closed or unbound generic type. Just as at compile time, a closed generic type can be instantiated, whereas an unbound type cannot:

```
Type closed = typeof (List<int>);
List<int> list = (List<int>) Activator.CreateInstance (closed); // OK

Type unbound = typeof (List<>);
object anError = Activator.CreateInstance (unbound); // Runtime error
```

The MakeGenericType method converts an unbound into a closed generic type. Simply pass in the desired type arguments:

```
Type unbound = typeof (List<>);
Type closed = unbound.MakeGenericType (typeof (int));
```

The GetGenericTypeDefinition method does the opposite:

```
Type unbound2 = closed.GetGenericTypeDefinition(); // unbound == unbound2
```

The IsGenericType property returns true if a Type is generic, and the IsGenericTypeDefinition property returns true if the generic type is unbound. The following tests whether a type is a nullable value type:

```
Type nullable = typeof (bool?);
Console.WriteLine (
  nullable.IsGenericType &&
  nullable.GetGenericTypeDefinition() == typeof (Nullable<>>)); // True
```

GetGenericArguments returns the type arguments for closed generic types:

```
Console.WriteLine (closed.GetGenericArguments()[0]); // System.Int32
Console.WriteLine (nullable.GetGenericArguments()[0]); // System.Boolean
```

For unbound generic types, GetGenericArguments returns pseudotypes that represent the placeholder types specified in the generic type definition:

```
Console.WriteLine (unbound.GetGenericArguments()[0]);  // T
```

NOTE

At runtime, all generic types are either *unbound* or *closed*. They're unbound in the (relatively unusual) case of an expression such as typeof(Foo<>); otherwise, they're closed. There's no such thing as an *open* generic type at runtime: all open types are closed by the compiler. The method in the following class always prints False:

```
class Foo<T>
{
  public void Test()
    => Console.Write (GetType().IsGenericTypeDefinition);
}
```

Reflecting and Invoking Members

The GetMembers method returns the members of a type. Consider the following class:

```
class Walnut
{
  private bool cracked;
  public void Crack() { cracked = true; }
}
```

We can reflect on its public members, as follows:

```
MemberInfo[] members = typeof (Walnut).GetMembers();
foreach (MemberInfo m in members)
  Console.WriteLine (m);
```

This is the result:

Void Crack()
System.Type GetType()
System.String ToString()
Boolean Equals(System.Object)
Int32 GetHashCode()
Void .ctor()

REFLECTING MEMBERS WITH TYPEINFO

TypeInfo exposes a different (and somewhat simpler) protocol for reflecting over members. Using this API is optional (except in .NET Core 1 and older Windows Store apps given that there's no exact equivalent to the GetMembers method).

Instead of exposing methods like GetMembers that return arrays,

TypeInfo exposes *properties* that return IEnumerable<T>, upon which
you typically run LINQ queries. The broadest is DeclaredMembers:

```
IEnumerable<MemberInfo> members =
  typeof(Walnut).GetTypeInfo().DeclaredMembers;
```

Unlike with GetMembers(), the result excludes inherited members:

```
Void Crack()
Void .ctor()
Boolean cracked
```

There are also properties for returning specific kinds of members (DeclaredProperties, DeclaredMethods, DeclaredEvents, and so on) and methods for returning a specific member by name (e.g., GetDeclaredMethod). The latter cannot be used on overloaded methods (because there's no way to specify parameter types). Instead, you run a LINQ query over DeclaredMethods:

When called with no arguments, GetMembers returns all the public members for a type (and its base types). GetMember retrieves a specific member by name—although it still returns an array because members can be overloaded:

MemberInfo also has a property called MemberType of type MemberTypes. This is a flags enum with these values:

```
All Custom Field NestedType TypeInfo
Constructor Event Method Property
```

When calling GetMembers, you can pass in a MemberTypes instance to restrict the kinds of members that it returns. Alternatively, you can restrict the result set by calling GetMethods, GetFields, GetProperties, GetEvents, GetConstructors, or GetNestedTypes. There are also singular versions of each of these to home in on a specific member.

NOTE

It pays to be as specific as possible when retrieving a type member so that your code doesn't break if additional members are added later. If you're retrieving a method by name, specifying all parameter types ensures that your code will still work if the method is later overloaded (we provide examples shortly, in "Method Parameters").

A MemberInfo object has a Name property and two Type properties:

DeclaringType

Returns the Type that defines the member

ReflectedType

Returns the Type upon which GetMembers was called

The two differ when called on a member that's defined in a base type: DeclaringType returns the base type, whereas ReflectedType returns the subtype. The following example highlights this:

```
// MethodInfo is a subclass of MemberInfo; see Figure 18-1.

MethodInfo test = typeof (Program).GetMethod ("ToString");
MethodInfo obj = typeof (object) .GetMethod ("ToString");

Console.WriteLine (test.DeclaringType);  // System.Object
Console.WriteLine (obj.DeclaringType);  // System.Object

Console.WriteLine (test.ReflectedType);  // Program
Console.WriteLine (obj.ReflectedType);  // System.Object

Console.WriteLine (test == obj);  // False
```

Because they have different ReflectedTypes, the test and obj objects are not equal. Their difference, however, is purely a fabrication of the reflection API; our Program type has no distinct ToString method in the underlying type system. We can verify that the two MethodInfo objects refer to the same method in either of two ways:

A MethodHandle is unique to each (genuinely distinct) method within a process; a MetadataToken is unique across all types and members within an assembly module.

MemberInfo also defines methods to return custom attributes (see "Retrieving Attributes at Runtime").

NOTE

You can obtain the MethodBase of the currently executing method by calling MethodBase.GetCurrentMethod

Member Types

MemberInfo itself is light on members because it's an abstract base for the types shown in Figure 18-1.




Figure 18-1. Member types

You can cast a MemberInfo to its subtype, based on its MemberType property. If you obtained a member via GetMethod, GetField, GetProperty, GetEvent, GetConstructor, or GetNestedType (or their plural versions), a cast isn't necessary. Table 18-1 summarizes what methods to use for each kind of C# construct.

Table 18-1. Retrieving member metadata

C# construct	Method to use	Name to use	Result
Method	GetMethod	(method name)	MethodInfo
Property	GetProperty	(property name)	PropertyInfo
Indexer	GetDefaultMember s		MemberInfo[] (containing PropertyI nfo objects if compiled in C#)
Field	GetField	(field name)	FieldInfo
Enum member	GetField	(member name)	FieldInfo
Event	GetEvent	(event name)	EventInfo
Constructor	GetConstructor		ConstructorInfo
Finalizer	GetMethod	"Finalize"	MethodInfo
Operator	GetMethod	"op_" + operator name	MethodInfo
Nested type	GetNestedType	(type name)	Туре

Each MemberInfo subclass has a wealth of properties and methods, exposing all aspects of the member's metadata. This includes such things as visibility, modifiers, generic type arguments, parameters, return type, and custom attributes.

Here is an example of using GetMethod:

All *Info instances are cached by the reflection API on first use:

```
MethodInfo method = typeof (Walnut).GetMethod ("Crack");
MemberInfo member = typeof (Walnut).GetMember ("Crack") [0];
Console.Write (method == member); // True
```

As well as preserving object identity, caching improves the performance of what is otherwise a fairly slow API.

C# Members Versus CLR Members

The preceding table illustrates that some of C#'s functional constructs don't have a 1:1 mapping with CLR constructs. This makes sense because the CLR and reflection API were designed with all .NET languages in mind—you can use reflection even from Visual Basic.

Some C# constructs—namely indexers, enums, operators, and finalizers—are contrivances as far as the CLR is concerned. Specifically:

- A C# indexer translates to a property accepting one or more arguments, marked as the type's [DefaultMember].
- A C# enum translates to a subtype of System. Enum with a static field for each member.
- A C# operator translates to a specially named static method, starting in "op_"; for example, "op_Addition".
- A C# finalizer translates to a method that overrides Finalize.

Another complication is that properties and events actually comprise two things:

- Metadata describing the property or event (encapsulated by PropertyInfo or EventInfo)
- One or two backing methods

In a C# program, the backing methods are encapsulated within the property or event definition. But when compiled to IL, the backing methods present as ordinary methods that you can call like any other. This means that GetMethods returns property and event backing methods alongside ordinary methods:

```
class Test { public int X { get { return 0; } set {} } }

void Demo()
{
   foreach (MethodInfo mi in typeof (Test).GetMethods())
      Console.Write (mi.Name + " ");
}

// OUTPUT:
get_X set_X GetType ToString Equals GetHashCode
```

You can identify these methods through the IsSpecialName property in MethodInfo. IsSpecialName returns true for property, indexer, and event accessors, as well as operators. It returns false only for conventional C# methods—and the Finalize method if a finalizer is defined.

Here are the backing methods that C# generates:

C# construct	Member type	Methods in IL
Property	Property	get_ <i>xxx</i> and set_ <i>xxx</i>
Indexer	Property	get_Item and set_Item
Event	Event	add_ <i>xxx</i> and remove_ <i>xxx</i>

Each backing method has its own associated MethodInfo object. You can access these as follows:

GetAddMethod and GetRemoveMethod perform a similar job for EventInfo.

To go in the reverse direction—from a MethodInfo to its associated PropertyInfo or EventInfo—you need to perform a query. LINQ is ideal for this job:

Init-only properties

Init-only properties, introduced in C# 9, can be set via an object initializer but are subsequently treated as read-only by the compiler. From the CLR's perspective, an init accessor is just like an ordinary set accessor, but with a special flag applied to the set method's return type (which means something to the compiler).

Curiously, this flag is not encoded as a convention attribute. Instead, it uses a relatively obscure mechanism called a *modreq*, which ensures that previous versions of the C# compiler (which don't recognize the new modreq) ignore the accessor rather than treat the property as writable.

The modreq for init-only accessors is called IsExternalInit, and you can query for it as follows:

```
bool IsInitOnly (PropertyInfo pi) => pi
    .GetSetMethod().ReturnParameter.GetRequiredCustomModifiers()
    .Any (t => t.Name == "IsExternalInit");
```

NullabilityInfoContext

From .NET 6, you can use the NullabilityInfoContext class to obtain information about the nullability annotations for a field, property, event or parameter:

```
void PrintPropertyNullability (PropertyInfo pi)
{
  var info = new NullabilityInfoContext().Create (pi);
  Console.WriteLine (pi.Name + " read " + info.ReadState);
  Console.WriteLine (pi.Name + " write " + info.WriteState);
  // Use info.Element to get nullability info for array elements
}
```

Generic Type Members

You can obtain member metadata for both unbound and closed generic types:

```
PropertyInfo unbound = typeof (IEnumerator<>) .GetProperty ("Current");
PropertyInfo closed = typeof (IEnumerator<int>).GetProperty ("Current");
Console.WriteLine (unbound); // T Current
Console.WriteLine (closed); // Int32 Current

Console.WriteLine (unbound.PropertyType.IsGenericParameter); // True
Console.WriteLine (closed.PropertyType.IsGenericParameter); // False
```

The MemberInfo objects returned from unbound and closed generic types are always distinct, even for members whose signatures don't feature generic type parameters:

```
PropertyInfo unbound = typeof (List<>) .GetProperty ("Count");
PropertyInfo closed = typeof (List<int>).GetProperty ("Count");

Console.WriteLine (unbound); // Int32 Count
Console.WriteLine (closed); // Int32 Count

Console.WriteLine (unbound == closed); // False

Console.WriteLine (unbound.DeclaringType.IsGenericTypeDefinition); // True
Console.WriteLine (closed.DeclaringType.IsGenericTypeDefinition); // False
```

Members of unbound generic types cannot be *dynamically invoked*.

Dynamically Invoking a Member

NOTE

Dynamically invoking a member can be accomplished more easily using the Uncapsulator open-source library (available on NuGet and GitHub). Uncapsulator was written by the author, and provides a fluent API for invoking public and non-public members via reflection, using a custom dynamic binder.

After you have a MethodInfo, PropertyInfo, or FieldInfo object, you can dynamically call it or get/set its value. This is called *late binding* because you choose which member to invoke at runtime rather than compile time.

To illustrate, the following uses ordinary *static binding*:

```
string s = "Hello";
int length = s.Length;
```

Here's the same thing performed dynamically with late binding:

```
object s = "Hello";
PropertyInfo prop = s.GetType().GetProperty ("Length");
int length = (int) prop.GetValue (s, null); // 5
```

GetValue and SetValue get and set the value of a PropertyInfo or FieldInfo. The first argument is the instance, which can be null for a static member. Accessing an indexer is just like accessing a property called "Item," except that you provide indexer values as the second argument when calling GetValue or SetValue.

To dynamically call a method, call Invoke on a MethodInfo, providing an array of arguments to pass to that method. If you get any of the argument types wrong, an exception is thrown at runtime. With dynamic invocation,

you lose compile-time type safety, but you still have runtime type safety (just as with the dynamic keyword).

Method Parameters

Suppose that we want to dynamically call string's Substring method. Statically, we would do this, as follows:

Here's the dynamic equivalent with reflection and late binding:

```
Type type = typeof (string);
Type[] parameterTypes = { typeof (int) };
MethodInfo method = type.GetMethod ("Substring", parameterTypes);
object[] arguments = { 2 };
object returnValue = method.Invoke ("stamp", arguments);
Console.WriteLine (returnValue); // "amp"
```

Because the Substring method is overloaded, we had to pass an array of parameter types to GetMethod to indicate which version we wanted. Without the parameter types, GetMethod would throw an AmbiguousMatchException.

The GetParameters method, defined on MethodBase (the base class for MethodInfo and ConstructorInfo), returns parameter metadata. We can continue our previous example, as follows:

Dealing with ref and out parameters

To pass ref or out parameters, call MakeByRefType on the type before obtaining the method. For instance, you can dynamically execute this code:

```
int x;
bool successfulParse = int.TryParse ("23", out x);

as follows:

object[] args = { "23", 0 };
Type[] argTypes = { typeof (string), typeof (int).MakeByRefType() };
MethodInfo tryParse = typeof (int).GetMethod ("TryParse", argTypes);
bool successfulParse = (bool) tryParse.Invoke (null, args);

Console.WriteLine (successfulParse + " " + args[1]);  // True 23
```

This same approach works for both ref and out parameter types.

Retrieving and invoking generic methods

Explicitly specifying parameter types when calling GetMethod can be essential in disambiguating overloaded methods. However, it's impossible to specify generic parameter types. For instance, consider the System.Linq.Enumerable class, which overloads the Where method, as follows:

```
public static IEnumerable<TSource> Where<TSource>
  (this IEnumerable<TSource> source, Func<TSource, bool> predicate);
public static IEnumerable<TSource> Where<TSource>
  (this IEnumerable<TSource> source, Func<TSource, int, bool> predicate);
```

To retrieve a specific overload, we must retrieve all methods and then manually find the desired overload. The following query retrieves the former overload of Where:

```
from m in typeof (Enumerable).GetMethods()
where m.Name == "Where" && m.IsGenericMethod
let parameters = m.GetParameters()
where parameters.Length == 2
let genArg = m.GetGenericArguments().First()
```

```
let enumerableOfT = typeof (IEnumerable<>).MakeGenericType (genArg)
let funcOfTBool = typeof (Func<,>).MakeGenericType (genArg, typeof (bool))
where parameters[0].ParameterType == enumerableOfT
    && parameters[1].ParameterType == funcOfTBool
select m
```

Calling .Single() on this query gives the correct MethodInfo object with unbound type parameters. The next step is to close the type parameters by calling MakeGenericMethod:

```
var closedMethod = unboundMethod.MakeGenericMethod (typeof (int));
```

In this case, we've closed TSource with int, allowing us to call Enumerable. Where with a source of type IEnumerable<int> and a predicate of type Func<int, bool>:

```
int[] source = { 3, 4, 5, 6, 7, 8 };
Func<int, bool> predicate = n => n % 2 == 1;  // Odd numbers only
```

We can now invoke the closed generic method:

```
var query = (IEnumerable<int>) closedMethod.Invoke
  (null, new object[] { source, predicate });
foreach (int element in query) Console.Write (element + "|"); // 3|5|7|
```

NOTE

If you're using the System.Linq.Expressions API to dynamically build expressions (Chapter 8), you don't need to go to this trouble to specify a generic method. The Expression.Call method is overloaded to let you specify the closed type arguments of the method that you want to call:

```
int[] source = { 3, 4, 5, 6, 7, 8 };
Func<int, bool> predicate = n => n % 2 == 1;

var sourceExpr = Expression.Constant (source);
var predicateExpr = Expression.Constant (predicate);

var callExpression = Expression.Call (
   typeof (Enumerable), "Where",
   new[] { typeof (int) }, // Closed generic arg type.
   sourceExpr, predicateExpr);
```

Using Delegates for Performance

Dynamic invocations are relatively inefficient, with an overhead typically in the few-microseconds region. If you're calling a method repeatedly in a loop, you can shift the per-call overhead into the nanoseconds region by instead calling a dynamically instantiated delegate that targets your dynamic method. In the following example, we dynamically call string's Trim method a million times without significant overhead:

This is faster because the costly late binding (shown in bold) happens just once.

Accessing Nonpublic Members

All of the methods on types used to probe metadata (e.g., GetProperty, GetField, etc.) have overloads that take a BindingFlags enum. This enum serves as a metadata filter and allows you to change the default selection criteria. The most common use for this is to retrieve nonpublic members (this works only in desktop apps).

For instance, consider the following class:

```
class Walnut
{
  private bool cracked;
  public void Crack() { cracked = true; }

  public override string ToString() { return cracked.ToString(); }
}
```

We can *uncrack* the walnut, as follows:

Using reflection to access nonpublic members is powerful, but it is also dangerous because you can bypass encapsulation, creating an unmanageable dependency on the internal implementation of a type.

The BindingFlags enum

BindingFlags is intended to be bitwise-combined. To get any matches at all, you need to start with one of the following four combinations:

```
BindingFlags.Public | BindingFlags.Instance
BindingFlags.Public | BindingFlags.Static
BindingFlags.NonPublic | BindingFlags.Instance
BindingFlags.NonPublic | BindingFlags.Static
```

NonPublic includes internal, protected, protected internal, and private.

The following example retrieves all the public static members of type object:

```
BindingFlags publicStatic = BindingFlags.Public | BindingFlags.Static;
MemberInfo[] members = typeof (object).GetMembers (publicStatic);
```

The following example retrieves all the nonpublic members of type object, both static and instance:

```
BindingFlags nonPublicBinding =
   BindingFlags.NonPublic | BindingFlags.Static | BindingFlags.Instance;

MemberInfo[] members = typeof (object).GetMembers (nonPublicBinding);
```

The DeclaredOnly flag excludes functions inherited from base types, unless they are overridden.

NOTE

The DeclaredOnly flag is somewhat confusing in that it *restricts* the result set (whereas all the other binding flags *expand* the result set).

Generic Methods

You cannot directly invoke generic methods; the following throws an exception:

```
class Program
{
  public static T Echo<T> (T x) { return x; }

  static void Main()
  {
    MethodInfo echo = typeof (Program).GetMethod ("Echo");
    Console.WriteLine (echo.IsGenericMethodDefinition); // True
```

An extra step is required, which is to call MakeGenericMethod on the MethodInfo, specifying concrete generic type arguments. This returns another MethodInfo, which you can then invoke, as follows:

```
MethodInfo echo = typeof (Program).GetMethod ("Echo");
MethodInfo intEcho = echo.MakeGenericMethod (typeof (int));
Console.WriteLine (intEcho.IsGenericMethodDefinition);  // False
Console.WriteLine (intEcho.Invoke (null, new object[] { 3 } ));  // 3
```

Anonymously Calling Members of a Generic Interface

Reflection is useful when you need to invoke a member of a generic interface and you don't know the type parameters until runtime. In theory, the need for this arises rarely if types are perfectly designed; of course, types are not always perfectly designed.

For instance, suppose that we want to write a more powerful version of ToString that could expand the result of LINQ queries. We could start out as follows:

```
public static string ToStringEx <T> (IEnumerable<T> sequence)
{
   ...
}
```

This is already quite limiting. What if sequence contained *nested* collections that we also want to enumerate? We'd need to overload the method to cope:

```
public static string ToStringEx <T> (IEnumerable<IEnumerable<T>> sequence)
```

And then what if sequence contained groupings, or *projections* of nested sequences? The static solution of method overloading becomes impractical

—we need an approach that can scale to handle an arbitrary object graph, such as the following:

```
public static string ToStringEx (object value)
  if (value == null) return "<null>";
  StringBuilder sb = new StringBuilder();
  if (value is List<>)
                                                                  // Error
    sb.Append ("List of " + ((List<>) value).Count + " items");
                                                                // Error
 if (value is IGrouping<,>)
                                                                  // Error
    sb.Append ("Group with key=" + ((IGrouping<,>) value).Key);
                                                                 // Error
  // Enumerate collection elements if this is a collection,
  // recursively calling ToStringEx()
  // ...
  return sb.ToString();
}
```

Unfortunately, this won't compile: you cannot invoke members of an *unbound* generic type such as List<> or IGrouping<>. In the case of List<>, we can solve the problem by using the nongeneric IList interface, instead:

```
if (value is IList)
  sb.AppendLine ("A list with " + ((IList) value).Count + " items");
```

NOTE

We can do this because the designers of List<> had the foresight to implement IList classic (as well as IList *generic*). The same principle is worthy of consideration when writing your own generic types: having a nongeneric interface or base class upon which consumers can fall back can be extremely valuable.

The solution is not as simple for IGrouping<,>. Here's how the interface is defined:

There's no nongeneric type we can use to access the Key property, so here we must use reflection. The solution is not to invoke members of an unbound generic type (which is impossible) but to invoke members of a *closed* generic type, whose type arguments we establish at runtime.

NOTE

In the following chapter, we solve this more simply with C#'s dynamic keyword. A good indication for dynamic binding is when you would otherwise need to perform *type gymnastics*—as we are doing right now.

The first step is to determine whether value implements IGrouping<,>, and if so, obtain its closed generic interface. We can do this most easily by executing a LINQ query. Then, we retrieve and invoke the Key property:

```
sb.Append ("Group with key=" + key + ": ");
}

if (value is IEnumerable)
  foreach (object element in ((IEnumerable)value))
    sb.Append (ToStringEx (element) + " ");

if (sb.Length == 0) sb.Append (value.ToString());

return "\r\n" + sb.ToString();
}
```

This approach is robust: it works whether IGrouping<,> is implemented implicitly or explicitly. The following demonstrates this method:

```
Console.WriteLine (ToStringEx (new List<int> { 5, 6, 7 } ));
Console.WriteLine (ToStringEx ("xyyzzz".GroupBy (c => c) ));

List of 3 items: 5 6 7

Group with key=x: x

Group with key=y: y y

Group with key=z: z z z
```

Calling Static Virtual/Abstract Interface Members

From .NET 7 and C# 11, interfaces can define static virtual and abstract members (see "Static virtual/abstract interface members"). An example is the .NET IParsable<TSelf> interface:

```
public interface IParsable<TSelf> where TSelf : IParsable<TSelf>
{
    static abstract TSelf Parse (string s, IFormatProvider provider);
    ...
}
```

With a constrained type parameter, static abstract interface members can be called polymorphically:

```
T ParseAny<T> (string s) where T : IParsable<T> => T.Parse (s, null);
```

To call a static abstract interface member via reflection, you must obtain a MethodInfo from the concrete type that implements the interface—not from the interface itself. The obvious solution is to retrieve the concrete member by signature:

```
MethodInfo GetParseMethod (Type concreteType) =>
  concreteType.GetMethod ("Parse",
   new[] { typeof (string), typeof (IFormatProvider) });
```

However, this will fail if the member has been implemented explicitly. To solve this in a general fashion, we will start by writing a function that retrieves the MethodInfo on a concrete type that implements a specified interface method:

The key to making this work is the call to GetInterfaceMap. This method returns the following struct:

```
public struct InterfaceMapping
{
   public MethodInfo[] InterfaceMethods;  // These arrays each
   public MethodInfo[] TargetMethods;  // have the same length.
   ...
}
```

This struct tells us how the members of the implemented interface (InterfaceMethods) map to the concrete type's members (TargetMethods).

NOTE

GetInterfaceMap works with ordinary (instance) methods as well; it just happens to be particularly useful when working with static abstract interface members.

We then used LINQ's Zip method to align the elements in the two arrays, allowing us to easily obtain the target method corresponding to the interface method with the desired signature.

We can now use this to write a reflection-based ParseAny method:

When calling GetImplementedInterfaceMethod, we needed to provide the (closed) interface type, which we obtained by calling GetInterface("IParsable`1") on the concrete type. Given that (in this scenario) we knew the desired interface at compile time, we could have used the following expression instead:

```
typeof (IParsable<>).MakeGenericType (type)
```

Reflecting Assemblies

You can dynamically reflect an assembly by calling GetType or GetTypes on an Assembly object. The following retrieves from the current assembly, the type called TestProgram in the Demos namespace:

```
Type t = Assembly.GetExecutingAssembly().GetType ("Demos.TestProgram");
```

You can also obtain an assembly from an existing type:

```
typeof (Foo).Assembly.GetType ("Demos.TestProgram");
```

The next example lists all the types in the assembly *mylib.dll* in *e*:\demo:

```
Assembly a = Assembly.LoadFile (@"e:\demo\mylib.dll");
foreach (Type t in a.GetTypes())
   Console.WriteLine (t);

Or:

Assembly a = typeof (Foo).GetTypeInfo().Assembly;
foreach (Type t in a.ExportedTypes)
   Console.WriteLine (t);
```

GetTypes and ExportedTypes return only top-level and not nested types.

Modules

Calling GetTypes on a multimodule assembly returns all types in all modules. As a result, you can ignore the existence of modules and treat an assembly as a type's container. There is one case, though, for which modules are relevant—and that's when dealing with metadata tokens.

A metadata token is an integer that uniquely refers to a type, member, string, or resource within the scope of a module. IL uses metadata tokens, so if you're parsing IL, you'll need to be able to resolve them. The methods for doing this are defined in the Module type and are called ResolveType, ResolveMember, ResolveString, and ResolveSignature. We revisit this in the final section of this chapter, on writing a disassembler.

You can obtain a list of all the modules in an assembly by calling GetModules. You can also access an assembly's main module directly via

its ManifestModule property.

Working with Attributes

The CLR allows additional metadata to be attached to types, members, and assemblies through attributes. This is the mechanism by which some important CLR functions (such as assembly identification or the marshaling of types for native interoperability) are directed, making attributes an indivisible part of an application.

A key characteristic of attributes is that you can write your own and then use them just as you would any other attribute to "decorate" a code element with additional information. This additional information is compiled into the underlying assembly and can be retrieved at runtime using reflection to build services that work declaratively, such as automated unit testing.

Attribute Basics

There are three kinds of attributes:

- Bit-mapped attributes
- Custom attributes
- Pseudocustom attributes

Of these, only custom attributes are extensible.

NOTE

The term "attribute" by itself can refer to any of the three, although in the C# world, it most often refers to custom attributes or pseudocustom attributes.

Bit-mapped attributes (our terminology) map to dedicated bits in a type's metadata. Most of C#'s modifier keywords, such as public, abstract, and

sealed, compile to bit-mapped attributes. These attributes are very efficient because they consume minimal space in the metadata (usually just one bit), and the CLR can locate them with little or no indirection. The reflection API exposes them via dedicated properties on Type (and other MemberInfo subclasses), such as IsPublic, IsAbstract, and IsSealed. The Attributes property returns a flags enum that describes most of them in one hit:

```
static void Main()
{
   TypeAttributes ta = typeof (Console).Attributes;
   MethodAttributes ma = MethodInfo.GetCurrentMethod().Attributes;
   Console.WriteLine (ta + "\r\n" + ma);
}
```

Here's the result:

```
AutoLayout, AnsiClass, Class, Public, Abstract, Sealed, BeforeFieldInit PrivateScope, Private, Static, HideBySig
```

In contrast, *custom attributes* compile to a blob that hangs off the type's main metadata table. All custom attributes are represented by a subclass of System.Attribute and, unlike bit-mapped attributes, are extensible. The blob in the metadata identifies the attribute class, and also stores the values of any positional or named argument that was specified when the attribute was applied. Custom attributes that you define yourself are architecturally identical to those defined in the .NET libraries.

Chapter 4 describes how to attach custom attributes to a type or member in C#. Here, we attach the predefined Obsolete attribute to the Foo class:

```
[Obsolete] public class Foo {...}
```

This instructs the compiler to incorporate an instance of ObsoleteAttribute into the metadata for Foo, which then can be reflected at runtime by calling GetCustomAttributes on a Type or MemberInfo object.

Pseudocustom attributes look and feel just like standard custom attributes. They are represented by a subclass of System. Attribute and are attached in the standard manner:

```
[System.Runtime.InteropServices.StructLayout(LayoutKind.Sequential)]
class SystemTime { ... }
```

The difference is that the compiler or CLR internally optimizes pseudocustom attributes by converting them to bit-mapped attributes. Examples include StructLayout, In, and Out (Chapter 24). Reflection exposes pseudocustom attributes through dedicated properties such as IsLayoutSequential, and in many cases they are also returned as System.Attribute objects when you call GetCustomAttributes. This means that you can (almost) ignore the difference between pseudo- and non-pseudocustom attributes (a notable exception is when using Reflection.Emit to generate types dynamically at runtime; see "Emitting Assemblies and Types").

The AttributeUsage Attribute

AttributeUsage is an attribute applied to attribute classes. It instructs the compiler how the target attribute should be used:

```
public sealed class AttributeUsageAttribute : Attribute
{
  public AttributeUsageAttribute (AttributeTargets validOn);

  public bool AllowMultiple { get; set; }
  public bool Inherited { get; set; }
  public AttributeTargets ValidOn { get; }
}
```

AllowMultiple controls whether the attribute being defined can be applied more than once to the same target; Inherited controls whether an attribute applied to a base class also applies to derived classes (or in the case of methods, whether an attribute applied to a virtual method also applies to

overriding methods). ValidOn determines the set of targets (classes, interfaces, properties, methods, parameters, etc.) to which the attribute can be attached. It accepts any combination of values from the AttributeTargets enum, which has the following members:

All	Delegate	GenericParameter	Parameter
Assembly	Enum	Interface	Property
Class	Event	Method	ReturnValue
Constructor	Field	Module	Struct

To illustrate, here's how the authors of .NET have applied AttributeUsage to the Serializable attribute:

This is, in fact, almost the complete definition of the Serializable attribute. Writing an attribute class that has no properties or special constructors is this simple.

Defining Your Own Attribute

Here's how to write your own attribute:

1. Derive a class from System.Attribute or a descendent of System.Attribute. By convention, the class name should end with the word "Attribute," although this isn't required.

- 2. Apply the AttributeUsage attribute, described in the preceding section.
 - If the attribute requires no properties or arguments in its constructor, the job is done.
- 3. Write one or more public constructors. The parameters to the constructor define the positional parameters of the attribute and will become mandatory when using the attribute.
- 4. Declare a public field or property for each named parameter you wish to support. Named parameters are optional when using the attribute.

NOTE

Attribute properties and constructor parameters must be of the following types:

- A sealed primitive type: in other words, bool, byte, char, double, float, int, long, short, or string
- The Type type
- An enum type
- A one-dimensional array of any of these

When an attribute is applied, it must also be possible for the compiler to statically evaluate each of the properties or constructor arguments.

The following class defines an attribute for assisting an automated unittesting system. It indicates that a method should be tested, the number of test repetitions, and a message in case of failure:

```
[AttributeUsage (AttributeTargets.Method)]
public sealed class TestAttribute : Attribute
{
   public int         Repetitions;
   public string FailureMessage;

   public TestAttribute () : this (1) { }
```

```
public TestAttribute (int repetitions) { Repetitions = repetitions; }
}
```

Here's a Foo class with methods decorated in various ways with the Test attribute:

```
class Foo
{
    [Test]
    public void Method1() { ... }

    [Test(20)]
    public void Method2() { ... }

    [Test(20, FailureMessage="Debugging Time!")]
    public void Method3() { ... }
}
```

Retrieving Attributes at Runtime

There are two standard ways to retrieve attributes at runtime:

- Call GetCustomAttributes on any Type or MemberInfo object
- Call Attribute.GetCustomAttribute or Attribute.GetCustomAttributes

These latter two methods are overloaded to accept any reflection object that corresponds to a valid attribute target (Type, Assembly, Module, MemberInfo, or ParameterInfo).

NOTE

You can also call GetCustomAttributesData() on a type or member to obtain attribute information. The difference between this and GetCustomAttributes() is that the former lets you know you *how* the attribute was instantiated: it reports the constructor overload that was used, and the value of each constructor argument and named parameter. This is useful when you want to emit code or IL to reconstruct the attribute to the same state (see "Emitting Type Members").

Here's how we can enumerate each method in the preceding Foo class that has a TestAttribute:

To complete the illustration on how we could use this to write a unit-testing system, here's the same example expanded so that it actually calls the methods decorated with the Test attribute:

```
}
```

Returning to attribute reflection, here's an example that lists the attributes present on a specific type:

```
object[] atts = Attribute.GetCustomAttributes (typeof (Test));
foreach (object att in atts) Console.WriteLine (att);

[Serializable, Obsolete]
class Test
{
}
```

And, here's the output:

```
System.ObsoleteAttribute
System.SerializableAttribute
```

Dynamic Code Generation

The System.Reflection.Emit namespace contains classes for creating metadata and IL at runtime. Generating code dynamically is useful for certain kinds of programming tasks. An example is the regular expressions API, which emits performant types tuned to specific regular expressions. Another example is Entity Framework Core, which uses Reflection.Emit to generate proxy classes to enable lazy loading.

Generating IL with DynamicMethod

The DynamicMethod class is a lightweight tool in the System.Reflection.Emit namespace for generating methods on the fly. Unlike TypeBuilder, it doesn't require that you first set up a dynamic assembly, module, and type in which to contain the method. This makes it suitable for simple tasks—as well as serving as a good introduction to Reflection.Emit.

NOTE

A DynamicMethod and the associated IL are garbage-collected when no longer referenced. This means you can repeatedly generate dynamic methods without filling up memory. (To do the same with dynamic *assemblies*, you must apply the AssemblyBuilderAccess.RunAndCollect flag when creating the assembly.)

Here is a simple use of DynamicMethod to create a method that writes Hello world to the console:

OpCodes has a static read-only field for every IL opcode. Most of the functionality is exposed through various opcodes, although ILGenerator also has specialized methods for generating labels and local variables and for exception handling. A method always ends in Opcodes.Ret, which means "return," or some kind of branching/throwing instruction. The EmitWriteLine method on ILGenerator is a shortcut for Emitting a number of lower-level opcodes. We would get the same result if we replaced the call to EmitWriteLine with this:

Note that we passed typeof(Test) into DynamicMethod's constructor. This gives the dynamic method access to the nonpublic methods of that type, allowing us to do this:

Understanding IL requires a considerable investment of time. Rather than understand all the opcodes, it's much easier to compile a C# program and then examine, copy, and tweak the IL. LINQPad displays the IL for any method or code snippet that you type, and assembly viewing tools such ILSpy are useful for examining existing assemblies.

The Evaluation Stack

Central to IL is the concept of the *evaluation stack*. To call a method with arguments, you first push ("load") the arguments onto the evaluation stack and then call the method. The method then pops the arguments it needs from the evaluation stack. We demonstrated this previously, in calling Console.WriteLine. Here's a similar example with an integer:

To add two numbers together, you first load each number onto the evaluation stack, and then call Add. The Add opcode pops two values from the evaluation stack and pushes the result back on. The following adds 2 and 2, and then writes the result using the writeLine method obtained previously:

To calculate 10 / 2 + 1, you can do either this:

```
gen.Emit (OpCodes.Ldc_I4, 10);
gen.Emit (OpCodes.Ldc_I4, 2);
gen.Emit (OpCodes.Div);
gen.Emit (OpCodes.Ldc_I4, 1);
gen.Emit (OpCodes.Add);
gen.Emit (OpCodes.Call, writeLineInt);

or this:

gen.Emit (OpCodes.Ldc_I4, 1);
gen.Emit (OpCodes.Ldc_I4, 10);
gen.Emit (OpCodes.Ldc_I4, 2);
gen.Emit (OpCodes.Div);
gen.Emit (OpCodes.Add);
gen.Emit (OpCodes.Call, writeLineInt);
```

Passing Arguments to a Dynamic Method

The Ldarg and Ldarg_XXX opcodes load an argument passed into a method onto the stack. To return a value, leave exactly one value on the stack upon finishing. For this to work, you must specify the return type and argument types when calling DynamicMethod's constructor. The following creates a dynamic method that returns the sum of two integers:

```
DynamicMethod dynMeth = new DynamicMethod ("Foo",
 typeof (int),
                                            // Return type = int
 new[] { typeof (int), typeof (int) },
                                            // Parameter types = int, int
 typeof (void));
ILGenerator gen = dynMeth.GetILGenerator();
gen.Emit (OpCodes.Ldarg_0);
                                // Push first arg onto eval stack
gen.Emit (OpCodes.Ldarg 1);
                                // Push second arg onto eval stack
gen.Emit (OpCodes.Add);
                                // Add them together (result on stack)
gen.Emit (OpCodes.Ret);
                                // Return with stack having 1 value
int result = (int) dynMeth.Invoke (null, new object[] { 3, 4 } );
```

WARNING

When you exit, the evaluation stack must have exactly 0 or 1 item (depending on whether your method returns a value). If you violate this, the CLR will refuse to execute your method. You can remove an item from the stack without processing it by emitting OpCodes.Pop.

Rather than calling Invoke, it can be more convenient to work with a dynamic method as a typed delegate. The CreateDelegate method achieves just this. In our case, the delegate that we need has two integer parameters and an integer return type. We can use the Func<int, int, int> delegate for this purpose. The last line of our preceding example then becomes the following:

NOTE

A delegate also eliminates the overhead of dynamic method invocation—saving a few microseconds per call.

We demonstrate how to pass by reference in "Emitting Type Members".

Generating Local Variables

You can declare a local variable by calling DeclareLocal on an ILGenerator. This returns a LocalBuilder object, which you can use in conjunction with opcodes such as Ldloc (load a local variable) or Stloc (store a local variable). Ldloc pushes the evaluation stack; Stloc pops it. For example, consider the following C# code:

```
int x = 6;
int y = 7;
x *= y;
Console.WriteLine (x);
```

The following generates the preceding code dynamically:

```
var dynMeth = new DynamicMethod ("Test", null, null, typeof (void));
ILGenerator gen = dynMeth.GetILGenerator();
LocalBuilder localX = gen.DeclareLocal (typeof (int));
                                                          // Declare x
LocalBuilder localY = gen.DeclareLocal (typeof (int));
                                                          // Declare y
gen.Emit (OpCodes.Ldc_I4, 6);
                                     // Push literal 6 onto eval stack
gen.Emit (OpCodes.Stloc, localX);
                                     // Store in localX
gen.Emit (OpCodes.Ldc_I4, 7);
                                    // Push literal 7 onto eval stack
gen.Emit (OpCodes.Stloc, localY);
                                     // Store in localY
gen.Emit (OpCodes.Ldloc, localX);
                                     // Push localX onto eval stack
gen.Emit (OpCodes.Ldloc, localY);
                                     // Push localY onto eval stack
gen.Emit (OpCodes.Mul);
                                     // Multiply values together
gen.Emit (OpCodes.Stloc, localX);
                                    // Store the result to localX
                                     // Write the value of localX
gen.EmitWriteLine (localX);
gen.Emit (OpCodes.Ret);
```

Branching

In IL, there are no while, do, and for loops; it's all done with labels and the equivalent of goto and conditional goto statements. These are the branching opcodes, such as Br (branch unconditionally), Brtrue (branch if the value on the evaluation stack is true), and Blt (branch if the first value is less than the second value).

To set a branch target, first call DefineLabel (this returns a Label object), and then call MarkLabel at the place where you want to anchor the label. For example, consider the following C# code:

```
int x = 5;
while (x <= 10) Console.WriteLine (x++);</pre>
```

We can emit this as follows:

```
ILGenerator gen = \dots
Label startLoop = gen.DefineLabel();
                                                      // Declare labels
Label endLoop = gen.DefineLabel();
LocalBuilder x = gen.DeclareLocal (typeof (int));
                                                      // int x
gen.Emit (OpCodes.Ldc_I4, 5);
gen.Emit (OpCodes.Stloc, x);
                                                      // x = 5
gen.MarkLabel (startLoop);
  gen.Emit (OpCodes.Ldc_I4, 10);
                                              // Load 10 onto eval stack
  gen.Emit (OpCodes.Ldloc, x);
                                              // Load x onto eval stack
  gen.Emit (OpCodes.Blt, endLoop);
                                              // if (x > 10) goto endLoop
  gen.EmitWriteLine (x);
                                              // Console.WriteLine (x)
  gen.Emit (OpCodes.Ldloc, x);
                                              // Load x onto eval stack
  gen.Emit (OpCodes.Ldc I4, 1);
                                              // Load 1 onto the stack
  gen.Emit (OpCodes.Add);
                                              // Add them together
  gen.Emit (OpCodes.Stloc, x);
                                             // Save result back to x
  gen.Emit (OpCodes.Br, startLoop);
                                             // return to start of loop
```

```
gen.MarkLabel (endLoop);
gen.Emit (OpCodes.Ret);
```

Instantiating Objects and Calling Instance Methods

The IL equivalent of new is the Newobj opcode. This takes a constructor and loads the constructed object onto the evaluation stack. For instance, the following constructs a StringBuilder:

```
var dynMeth = new DynamicMethod ("Test", null, null, typeof (void));
ILGenerator gen = dynMeth.GetILGenerator();
ConstructorInfo ci = typeof (StringBuilder).GetConstructor (new Type[0]);
gen.Emit (OpCodes.Newobj, ci);
```

After loading an object onto the evaluation stack, you can use the Call or Callvirt opcode to invoke the object's instance methods. Extending this example, we'll query the StringBuilder's MaxCapacity property by calling the property's get accessor and then write out the result:

To emulate C# calling semantics:

- Use Call to invoke static methods and value type instance methods.
- Use Callvirt to invoke reference type instance methods (whether or not they're declared virtual).

In our example, we used Callvirt on the StringBuilder instance—even though MaxProperty is not virtual. This doesn't cause an error: it simply performs a nonvirtual call, instead. Always invoking reference type instance

methods with Callvirt avoids risking the opposite condition: invoking a virtual method with Call. (The risk is real. The author of the target method may later *change* its declaration.) Callvirt also has the benefit of checking that the receiver is non-null.

WARNING

Invoking a virtual method with Call bypasses virtual calling semantics and calls that method directly. This is rarely desirable and, in effect, violates type safety.

In the following example, we construct a StringBuilder passing in two arguments, append ", world!" to the StringBuilder, and then call ToString on it:

```
// We will call: new StringBuilder ("Hello", 1000)
ConstructorInfo ci = typeof (StringBuilder).GetConstructor (
                     new[] { typeof (string), typeof (int) } );
gen.Emit (OpCodes.Ldstr, "Hello"); // Load a string onto the eval stack
gen.Emit (OpCodes.Ldc I4, 1000);
                                    // Load an int onto the eval stack
gen.Emit (OpCodes.Newobj, ci);
                                    // Construct the StringBuilder
Type[] strT = { typeof (string) };
gen.Emit (OpCodes.Ldstr, ", world!");
gen.Emit (OpCodes.Call, typeof (StringBuilder).GetMethod ("Append", strT));
gen.Emit (OpCodes.Callvirt, typeof (object).GetMethod ("ToString"));
gen.Emit (OpCodes.Call, typeof (Console).GetMethod ("WriteLine", strT));
gen.Emit (OpCodes.Ret);
dynMeth.Invoke (null, null);
                                   // Hello, world!
```

For fun, we called GetMethod on typeof(object) and then used Callvirt to perform a virtual method call on ToString. We could have gotten the same result by calling ToString on the StringBuilder type itself:

(The empty type array is required in calling GetMethod because StringBuilder overloads ToString with another signature.)

Exception Handling

ILGenerator provides dedicated methods for exception handling. Thus, the translation for this C# code:

```
{ throw new NotSupportedException(); }
  try
  catch (NotSupportedException ex) { Console.WriteLine (ex.Message);
                                     { Console.WriteLine ("Finally");
  finally
is this:
  MethodInfo getMessageProp = typeof (NotSupportedException)
                               .GetProperty ("Message").GetGetMethod();
  MethodInfo writeLineString = typeof (Console).GetMethod ("WriteLine",
                                                new[] { typeof (object) } );
  gen.BeginExceptionBlock();
    ConstructorInfo ci = typeof (NotSupportedException).GetConstructor (
                                                           new Type[0] );
    gen.Emit (OpCodes.Newobj, ci);
    gen.Emit (OpCodes.Throw);
  gen.BeginCatchBlock (typeof (NotSupportedException));
    gen.Emit (OpCodes.Callvirt, getMessageProp);
    gen.Emit (OpCodes.Call, writeLineString);
  gen.BeginFinallyBlock();
    gen.EmitWriteLine ("Finally");
  gen.EndExceptionBlock();
```

Just as in C#, you can include multiple catch blocks. To rethrow the same exception, emit the Rethrow opcode.

WARNING

ILGenerator provides a helper method called ThrowException. This contains a bug, however, preventing it from being used with a DynamicMethod. It works only with a MethodBuilder (see the next section).

Emitting Assemblies and Types

Although DynamicMethod is convenient, it can generate only methods. If you need to emit any other construct—or a complete type—you need to use the full "heavyweight" API. This means dynamically building an assembly and module. The assembly need not have a disk presence (in fact, it cannot, because .NET 5+ and .NET Core do not let you save generated assemblies to disk).

Let's assume that we want to dynamically build a type. Because a type must reside in a module within an assembly, we first must create the assembly and module before we can create the type. This is the job of the AssemblyBuilder and ModuleBuilder types:

```
AssemblyName aname = new AssemblyName ("MyDynamicAssembly");

AssemblyBuilder assemBuilder = AssemblyBuilder.DefineDynamicAssembly (aname, AssemblyBuilderAccess.Run);

ModuleBuilder modBuilder = assemBuilder.DefineDynamicModule ("DynModule");
```

NOTE

You can't add a type to an existing assembly, because an assembly is immutable after it's created.

Dynamic assemblies are not garbage-collected and remain in memory until the process ends, unless you specify AssemblyBuilderAccess.RunAndCollect when defining the assembly. Various restrictions apply to collectible assemblies (see http://albahari.com/dynamiccollect).

After we have a module in which the type can reside, we can use TypeBuilder to create the type. The following defines a class called Widget:

TypeBuilder tb = modBuilder.DefineType ("Widget", TypeAttributes.Public);

The TypeAttributes flags enum supports the CLR type modifiers you see when disassembling a type with *ildasm*. As well as member visibility flags, this includes type modifiers such as Abstract and Sealed—and Interface for defining a .NET interface. It also includes Serializable, which is equivalent to applying the [Serializable] attribute in C#, and Explicit, which is equivalent to applying

[StructLayout(LayoutKind.Explicit)]. We describe how to apply other kinds of attributes later in this chapter, in "Attaching Attributes".

NOTE

The DefineType method also accepts an optional base type:

- To define a struct, specify a base type of System.ValueType.
- To define a delegate, specify a base type of System.MulticastDelegate.
- To implement an interface, use the constructor that accepts an array of interface types.
- To define an interface, specify TypeAttributes.Interface | TypeAttributes.Abstract.

Defining a delegate type requires a number of extra steps. In his weblog, Joel Pobar demonstrates how this is done in his article titled "Creating delegate types via Reflection.Emit".

We can now create members within the type:

We're now ready to create the type, which finalizes its definition:

```
Type t = tb.CreateType();
```

After the type is created, we can use ordinary reflection to inspect and perform late binding:

The Reflection.Emit Object Model

Figure 18-2 illustrates the essential types in System.Reflection.Emit. Each type describes a CLR construct and is based on a counterpart in the System.Reflection namespace. This allows you to use emitted constructs

in place of normal constructs when building a type. For example, we previously called Console.WriteLine, as follows:

We could just as easily call a dynamically generated method by calling gen. Emit with a MethodBuilder instead of a MethodInfo. This is essential —otherwise, you couldn't write one dynamic method that called another in the same type.




Figure 18-2. System. Reflection. Emit

Recall that you must call CreateType on a TypeBuilder when you've finished populating it. Calling CreateType seals the TypeBuilder and all its members—so nothing more can be added or changed—and gives you back a real Type that you can instantiate.

Before you call CreateType, the TypeBuilder and its members are in an "uncreated" state. There are significant restrictions on what you can do with uncreated constructs. In particular, you cannot call any of the members that return MemberInfo objects, such as GetMembers, GetMethod, or

GetProperty—these all throw an exception. If you want to refer to members of an uncreated type, you must use the original emissions:

```
TypeBuilder tb = ...

MethodBuilder method1 = tb.DefineMethod ("Method1", ...);
MethodBuilder method2 = tb.DefineMethod ("Method2", ...);

ILGenerator gen1 = method1.GetILGenerator();

// Suppose we want method1 to call method2:

gen1.Emit (OpCodes.Call, method2);  // Right gen1.Emit (OpCodes.Call, tb.GetMethod ("Method2"));  // Wrong
```

After calling CreateType, you can reflect on and activate not only the Type returned but also the original TypeBuilder object. The TypeBuilder, in fact, morphs into a proxy for the real Type. You'll see why this feature is important in "Awkward Emission Targets".

Emitting Type Members

All the examples in this section assume a TypeBuilder, tb, has been instantiated, as follows:

```
AssemblyName aname = new AssemblyName ("MyEmissions");
AssemblyBuilder assemBuilder = AssemblyBuilder.DefineDynamicAssembly (
    aname, AssemblyBuilderAccess.Run);
ModuleBuilder modBuilder = assemBuilder.DefineDynamicModule ("MainModule");
TypeBuilder tb = modBuilder.DefineType ("Widget", TypeAttributes.Public);
```

Emitting Methods

You can specify a return type and parameter types when calling DefineMethod, in the same manner as when instantiating a DynamicMethod. For instance, the following method:

```
public static double SquareRoot (double value) => Math.Sqrt (value);
```

can be generated like this:

```
MethodBuilder mb = tb.DefineMethod ("SquareRoot",
 MethodAttributes.Static | MethodAttributes.Public,
 CallingConventions.Standard,
 typeof (double),
                                      // Return type
 new[] { typeof (double) } );  // Parameter types
mb.DefineParameter (1, ParameterAttributes.None, "value"); // Assign name
ILGenerator gen = mb.GetILGenerator();
gen.Emit (OpCodes.Ldarg 0);
                                                          // Load 1st arg
gen.Emit (OpCodes.Call, typeof(Math).GetMethod ("Sqrt"));
gen.Emit (OpCodes.Ret);
Type realType = tb.CreateType();
double x = (double) tb.GetMethod ("SquareRoot").Invoke (null,
                                               new object[] { 10.0 });
Console.WriteLine (x); // 3.16227766016838
```

Calling DefineParameter is optional and is typically done to assign the parameter a name. The number 1 refers to the first parameter (0 refers to the return value). If you call DefineParameter, the parameter is implicitly named __p1, __p2, and so on. Assigning names makes sense if you will write the assembly to disk; it makes your methods friendly to consumers.

NOTE

DefineParameter returns a ParameterBuilder object upon which you can call SetCustomAttribute to attach attributes (see "Attaching Attributes").

To emit pass-by-reference parameters, such as in the following C# method:

```
public static void SquareRoot (ref double value)
    => value = Math.Sqrt (value);
```

call MakeByRefType on the parameter type(s):

```
MethodBuilder mb = tb.DefineMethod ("SquareRoot",
 MethodAttributes.Static | MethodAttributes.Public,
 CallingConventions.Standard,
  null,
  new Type[] { typeof (double).MakeByRefType() } );
mb.DefineParameter (1, ParameterAttributes.None, "value");
ILGenerator gen = mb.GetILGenerator();
gen.Emit (OpCodes.Ldarg_0);
gen.Emit (OpCodes.Ldarg 0);
gen.Emit (OpCodes.Ldind_R8);
gen.Emit (OpCodes.Call, typeof (Math).GetMethod ("Sqrt"));
gen.Emit (OpCodes.Stind R8);
gen.Emit (OpCodes.Ret);
Type realType = tb.CreateType();
object[] args = { 10.0 };
tb.GetMethod ("SquareRoot").Invoke (null, args);
Console.WriteLine (args[0]);
                                                 // 3.16227766016838
```

The opcodes here were copied from a disassembled C# method. Notice the difference in semantics for accessing parameters passed by reference: Ldind and Stind mean "load indirectly" and "store indirectly," respectively. The R8 suffix means an eight-byte floating-point number.

The process for emitting out parameters is identical, except that you call DefineParameter, as follows:

```
mb.DefineParameter (1, ParameterAttributes.Out, "value");
```

Generating instance methods

To generate an instance method, specify MethodAttributes.Instance when calling DefineMethod:

```
MethodBuilder mb = tb.DefineMethod ("SquareRoot",
   MethodAttributes.Instance | MethodAttributes.Public
   ...
```

With instance methods, argument zero is implicitly this; the remaining arguments start at 1. So, Ldarg_0 loads this onto the evaluation stack; Ldarg_1 loads the first real method argument.

Overriding methods

Overriding a virtual method in a base class is easy: simply define a method with an identical name, signature, and return type, specifying MethodAttributes.Virtual when calling DefineMethod. The same applies when implementing interface methods.

TypeBuilder also exposes a method called DefineMethodOverride that overrides a method with a different name. This makes sense only with explicit interface implementation; in other scenarios, use DefineMethod.

HideBySig

If you're subclassing another type, it's nearly always worth specifying MethodAttributes. HideBySig when defining methods. HideBySig ensures that C#-style method-hiding semantics are applied, which is that a base method is hidden only if a subtype defines a method with an identical *signature*. Without HideBySig, method hiding considers only the *name*, so Foo(string) in the subtype will hide Foo() in the base type, which is generally undesirable.

Emitting Fields and Properties

To create a field, you call DefineField on a TypeBuilder, specifying the desired field name, type, and visibility. The following creates a private integer field called "length":

Creating a property or indexer requires a few more steps. First, call DefineProperty on a TypeBuilder, providing it with the name and type

of the property:

(If you're writing an indexer, the final argument is an array of indexer types.) Note that we haven't specified the property visibility: this is done individually on the accessor methods.

The next step is to write the get and set methods. By convention, their names are prefixed with "get_" or "set_". You then attach them to the property by calling SetGetMethod and SetSetMethod on the PropertyBuilder.

To give a complete example, let's take the following field and property declaration

and generate it dynamically:

```
FieldBuilder field = tb.DefineField ("_text", typeof (string),
                                      FieldAttributes.Private);
PropertyBuilder prop = tb.DefineProperty (
                                                      // Name of property
                         "Text",
                         PropertyAttributes.None,
                         typeof (string),
                                                      // Property type
                         new Type[0]);
                                                      // Indexer types
MethodBuilder getter = tb.DefineMethod (
  "get Text",
                                                      // Method name
  MethodAttributes.Public | MethodAttributes.SpecialName,
  typeof (string),
                                                      // Return type
```

```
// Parameter types
    new Type[0]);
  ILGenerator getGen = getter.GetILGenerator();
  getGen.Emit (OpCodes.Ldarg_0);
                                        // Load "this" onto eval stack
  getGen.Emit (OpCodes.Ldfld, field); // Load field value onto eval stack
                                        // Return
  getGen.Emit (OpCodes.Ret);
  MethodBuilder setter = tb.DefineMethod (
    "set Text",
    MethodAttributes.Assembly | MethodAttributes.SpecialName,
    null,
                                                          // Return type
    new Type[] { typeof (string) } );
                                                          // Parameter types
  ILGenerator setGen = setter.GetILGenerator();
  setGen.Emit (OpCodes.Ldarg_0);
                                       // Load "this" onto eval stack
  setGen.Emit (OpCodes.Ldarg 1);
                                      // Load 2nd arg, i.e., value
  setGen.Emit (OpCodes.Stfld, field); // Store value into field
  setGen.Emit (OpCodes.Ret);
                                        // return
  prop.SetGetMethod (getter);
                                        // Link the get method and property
  prop.SetSetMethod (setter);
                                        // Link the set method and property
We can test the property as follows:
```

```
Type t = tb.CreateType();
object o = Activator.CreateInstance (t);
t.GetProperty ("Text").SetValue (o, "Good emissions!", new object[0]);
string text = (string) t.GetProperty ("Text").GetValue (o, null);
Console.WriteLine (text);
                                     // Good emissions!
```

Notice that in defining the accessor MethodAttributes, we included SpecialName. This instructs compilers to disallow direct binding to these methods when statically referencing the assembly. It also ensures that the accessors are handled appropriately by reflection tools and Visual Studio's IntelliSense.

NOTE

You can emit events in a similar manner, by calling DefineEvent on a TypeBuilder. You then write explicit event accessor methods and attach them to the EventBuilder by calling SetAddOnMethod and SetRemoveOnMethod.

Emitting Constructors

You can define your own constructors by calling DefineConstructor on a type builder. You're not obliged to do so—a default parameterless constructor is automatically provided if you don't. The default constructor calls the base class constructor if subtyping, just like in C#. Defining one or more constructors displaces this default constructor.

If you need to initialize fields, the constructor's a good spot. In fact, it's the only spot: C#'s field initializers don't have special CLR support—they are simply a syntactic shortcut for assigning values to fields in the constructor.

So, to reproduce this:

```
class Widget
{
  int _capacity = 4000;
}
```

you would define a constructor, as follows:

Calling base constructors

If subclassing another type, the constructor we just wrote would *circumvent* the base class constructor. This is unlike C#, in which the base class constructor is always called, whether directly or indirectly. For instance, given the following code:

```
class A { public A() { Console.Write ("A"); } }
class B : A { public B() {} }
```

the compiler, in effect, will translate the second line into this:

```
class B : A { public B() : base() {} }
```

This is not the case when generating IL: you must explicitly call the base constructor if you want it to execute (which nearly always, you do). Assuming the base class is called A, here's how to do it:

```
gen.Emit (OpCodes.Ldarg_0);
ConstructorInfo baseConstr = typeof (A).GetConstructor (new Type[0]);
gen.Emit (OpCodes.Call, baseConstr);
```

Calling constructors with arguments is just the same as with methods.

Attaching Attributes

You can attach custom attributes to a dynamic construct by calling SetCustomAttribute with a CustomAttributeBuilder. For example, suppose that we want to attach the following attribute declaration to a field or property:

```
[XmlElement ("FirstName", Namespace="http://test/", Order=3)]
```

This relies on the XmlElementAttribute constructor that accepts a single string. To use CustomAttributeBuilder, we must retrieve this constructor as well as the two additional properties that we want to set (Namespace and Order):

```
Type attType = typeof (XmlElementAttribute);
ConstructorInfo attConstructor = attType.GetConstructor (
 new Type[] { typeof (string) } );
var att = new CustomAttributeBuilder (
                                        // Constructor
 attConstructor,
 new object[] { "FirstName" },
                               // Constructor arguments
 new PropertyInfo[]
   attType.GetProperty ("Namespace"), // Properties
   attType.GetProperty ("Order")
 },
 new object[] { "http://test/", 3 } // Property values
);
myFieldBuilder.SetCustomAttribute (att);
// or propBuilder.SetCustomAttribute (att);
// or typeBuilder.SetCustomAttribute (att); etc
```

Emitting Generic Methods and Types

All the examples in this section assume that modBuilder has been instantiated as follows:

```
AssemblyName aname = new AssemblyName ("MyEmissions");

AssemblyBuilder assemBuilder = AssemblyBuilder.DefineDynamicAssembly (
    aname, AssemblyBuilderAccess.Run);

ModuleBuilder modBuilder = assemBuilder.DefineDynamicModule ("MainModule");
```

Defining Generic Methods

To emit a generic method:

- 1. Call DefineGenericParameters on a MethodBuilder to obtain an array of GenericTypeParameterBuilder objects.
- 2. Call SetSignature on a MethodBuilder using these generic type parameters.

3. Optionally, name the parameters as you would otherwise.

For example, the following generic method:

The DefineGenericParameters method accepts any number of string arguments—these correspond to the desired generic type names. In this example, we needed just one generic type called T.

GenericTypeParameterBuilder is based on System. Type, so you can use it in place of a TypeBuilder when emitting opcodes.

GenericTypeParameterBuilder also lets you specify a base type constraint:

```
genericParams[0].SetBaseTypeConstraint (typeof (Foo));
```

and interface constraints:

```
genericParams[0].SetInterfaceConstraints (typeof (IComparable));
To replicate this:
   public static T Echo<T> (T value) where T : IComparable<T>
you would write:
    genericParams[0].SetInterfaceConstraints (
        typeof (IComparable<>).MakeGenericType (genericParams[0]) );
```

For other kinds of constraints, call SetGenericParameterAttributes.

This accepts a member of the GenericParameterAttributes enum, which includes the following values:

```
DefaultConstructorConstraint
NotNullableValueTypeConstraint
ReferenceTypeConstraint
Covariant
Contravariant
```

The last two are equivalent to applying the out and in modifiers to the type parameters.

Defining Generic Types

You can define generic types in a similar fashion. The difference is that you call DefineGenericParameters on the TypeBuilder rather than the MethodBuilder. So, to reproduce this:

```
public class Widget<T>
{
   public T Value;
}
```

you would do the following:

Generic constraints can be added, just as with a method.

Awkward Emission Targets

All of the examples in this section assume that a modBuilder has been instantiated as in previous sections.

Uncreated Closed Generics

Suppose that you want to emit a method that uses a closed generic type:

```
public class Widget
{
   public static void Test() { var list = new List<int>(); }
}
```

The process is fairly straightforward:

Now suppose that instead of a list of integers, we want a list of widgets:

```
public class Widget
{
   public static void Test() { var list = new List<Widget>(); }
}
```

In theory, this is a simple modification; all we do is replace this line:

```
Type variableType = typeof (List<int>);
with this one:
   Type variableType = typeof (List<>).MakeGenericType (tb);
```

Unfortunately, this causes a NotSupportedException to be thrown when we then call GetConstructor. The problem is that you cannot call GetConstructor on a generic type closed with an uncreated type builder. The same goes for GetField and GetMethod.

The solution is unintuitive. TypeBuilder provides three static methods:

```
public static ConstructorInfo GetConstructor (Type, ConstructorInfo);
public static FieldInfo GetField (Type, FieldInfo);
public static MethodInfo GetMethod (Type, MethodInfo);
```

Although it doesn't appear so, these methods exist specifically to obtain members of generic types closed with uncreated type builders! The first parameter is the closed generic type; the second parameter is the member that you want on the *unbound* generic type. Here's the corrected version of our example:

```
gen.Emit (OpCodes.Newobj, ci);
gen.Emit (OpCodes.Stloc, listVar);
gen.Emit (OpCodes.Ret);
```

Circular Dependencies

Suppose that you want to build two types that reference each other, such as these:

```
class A { public B Bee; }
class B { public A Aye; }
```

You can generate this dynamically, as follows:

```
var publicAtt = FieldAttributes.Public;

TypeBuilder aBuilder = modBuilder.DefineType ("A");
TypeBuilder bBuilder = modBuilder.DefineType ("B");

FieldBuilder bee = aBuilder.DefineField ("Bee", bBuilder, publicAtt);
FieldBuilder aye = bBuilder.DefineField ("Aye", aBuilder, publicAtt);

Type realA = aBuilder.CreateType();
Type realB = bBuilder.CreateType();
```

Notice that we didn't call CreateType on aBuilder or bBuilder until we populated both objects. The principle is this: first hook everything up, and then call CreateType on each type builder.

Interestingly, the realA type is valid but *dysfunctional* until you call CreateType on bBuilder. (If you started using aBuilder prior to this, an exception would be thrown when you tried to access field Bee.)

You might wonder how bBuilder knows to "fix up" realA after creating realB. The answer is that it doesn't: realA can fix *itself* the next time it's used. This is possible because after calling CreateType, a TypeBuilder morphs into a proxy for the real runtime type. So, realA, with its references to bBuilder, can easily obtain the metadata it needs for the upgrade.

This system works when the type builder demands simple information of the unconstructed type—information that can be *predetermined*—such as type, member, and object references. In creating realA, the type builder doesn't need to know, for instance, how many bytes realB will eventually occupy in memory. This is just as well because realB has not yet been created! But now imagine that realB was a struct. The final size of realB is now critical information in creating realA.

If the relationship is noncyclical; for instance:

```
struct A { public B Bee; }
struct B {
```

you can solve this by first creating struct B and then struct A. But consider this:

```
struct A { public B Bee; }
struct B { public A Aye; }
```

We won't try to emit this because it's nonsensical to have two structs contain each other (C# generates a compile-time error if you try). But the following variation is both legal and useful:

```
public struct S<T> { ... } // S can be empty and this demo will work.

class A { S<B> Bee; }
class B { S<A> Aye; }
```

In creating A, a TypeBuilder now needs to know the memory footprint of B, and vice versa. To illustrate, let's assume that struct S is defined statically. Here's the code to emit classes A and B:

```
var pub = FieldAttributes.Public;

TypeBuilder aBuilder = modBuilder.DefineType ("A");
TypeBuilder bBuilder = modBuilder.DefineType ("B");

aBuilder.DefineField ("Bee", typeof(S<>).MakeGenericType (bBuilder), pub);
```

```
bBuilder.DefineField ("Aye", typeof(S<>).MakeGenericType (aBuilder), pub);
Type realA = aBuilder.CreateType();  // Error: cannot load type B
Type realB = bBuilder.CreateType();
```

CreateType now throws a TypeLoadException no matter in which order you go:

- Call aBuilder.CreateType first, and it says "cannot load type B".
- Call bBuilder.CreateType first, and it says "cannot load type A"!

To solve this, you must allow the type builder to create realB partway through creating realA. You do this by handling the TypeResolve event on the AppDomain class just before calling CreateType. So, in our example, we replace the last two lines with this:

```
TypeBuilder[] uncreatedTypes = { aBuilder, bBuilder };

ResolveEventHandler handler = delegate (object o, ResolveEventArgs args)
{
   var type = uncreatedTypes.FirstOrDefault (t => t.FullName == args.Name);
   return type == null ? null : type.CreateType().Assembly;
};

AppDomain.CurrentDomain.TypeResolve += handler;

Type realA = aBuilder.CreateType();
Type realB = bBuilder.CreateType();
AppDomain.CurrentDomain.TypeResolve -= handler;
```

The TypeResolve event fires during the call to aBuilder.CreateType, at the point when it needs you to call CreateType on bBuilder.

NOTE

Handling the TypeResolve event as in this example is also necessary when defining a nested type, when the nested and parent types refer to each other.

Parsing IL

You can obtain information about the content of an existing method by calling GetMethodBody on a MethodBase object. This returns a MethodBody object that has properties for inspecting a method's local variables, exception handling clauses, and stack size, as well as the raw IL. Rather like the reverse of Reflection. Emit!

Inspecting a method's raw IL can be useful in profiling code. A simple use would be to determine which methods in an assembly have changed when an assembly is updated.

To illustrate parsing IL, we'll write an application that disassembles IL in the style of *ildasm*. This could be used as the starting point for a code analysis tool or a higher-level language disassembler.

NOTE

Remember that in the reflection API, all of C#'s functional constructs are either represented by a MethodBase subtype or (in the case of properties, events, and indexers) have MethodBase objects attached to them.

Writing a Disassembler

Here is a sample of the output that our disassembler will produce:

```
IL_00EB: ldfld Disassembler._pos
IL_00F0: ldloc.2
IL_00F1: add
IL_00F2: ldelema System.Byte
IL_00F7: ldstr "Hello world"
IL_00FC: call System.Byte.ToString
IL_0101: ldstr " "
IL_0106: call System.String.Concat
```

To obtain this output, we must parse the binary tokens that make up the IL. The first step is to call the GetILAsByteArray method on MethodBody to

obtain the IL as a byte array. To make the rest of the job easier, we will write this into a class as follows:

```
public class Disassembler
 public static string Disassemble (MethodBase method)
   => new Disassembler (method).Dis();
 StringBuilder _output; // The result to which we'll keep appending
 Module _module; // This will come in handy later
                        // The raw byte code
 byte[] _il;
                          // The position we're up to in the byte code
 int pos;
 Disassembler (MethodBase method)
   _module = method.DeclaringType.Module;
   _il = method.GetMethodBody().GetILAsByteArray();
 string Dis()
   _output = new StringBuilder();
   while (_pos < _il.Length) DisassembleNextInstruction();</pre>
   return _output.ToString();
 }
}
```

The static Disassemble method will be the only public member of this class. All other members will be private to the disassembly process. The Dis method contains the "main" loop where we process each instruction.

With this skeleton in place, all that remains is to write DisassembleNextInstruction. But before doing so, it will help to load all the opcodes into a static dictionary so that we can access them by their 8- or 16-bit value. The easiest way to accomplish this is to use reflection to retrieve all the static fields whose type is OpCode in the OpCodes class:

```
static Dictionary<short,OpCode> _opcodes = new Dictionary<short,OpCode>();
static Disassembler()
{
    Dictionary<short, OpCode> opcodes = new Dictionary<short, OpCode>();
```

We've written it in a static constructor so that it executes just once.

Now we can write DisassembleNextInstruction. Each IL instruction consists of a one- or two-byte opcode, followed by an operand of zero, one, two, four, or eight bytes. (An exception is inline switch opcodes, which are followed by a variable number of operands.) So, we read the opcode, then the operand, and then write out the result:

To read an opcode, we advance one byte and see whether we have a valid instruction. If not, we advance another byte and look for a two-byte instruction:

```
OpCode ReadOpCode()
{
   byte byteCode = _il [_pos++];
   if (_opcodes.ContainsKey (byteCode)) return _opcodes [byteCode];

   if (_pos == _il.Length) throw new Exception ("Unexpected end of IL");
   short shortCode = (short) (byteCode * 256 + _il [_pos++]);
```

```
if (!_opcodes.ContainsKey (shortCode))
    throw new Exception ("Cannot find opcode " + shortCode);
return _opcodes [shortCode];
}
```

To read an operand, we first must establish its length. We can do this based on the operand type. Because most are four bytes long, we can filter out the exceptions fairly easily in a conditional clause.

The next step is to call FormatOperand, which attempts to format the operand:

```
string ReadOperand (OpCode c)
{
  int operandLength =
   c.OperandType == OperandType.InlineNone
      ? 0 :
    c.OperandType == OperandType.ShortInlineBrTarget ||
    c.OperandType == OperandType.ShortInlineI ||
    c.OperandType == OperandType.ShortInlineVar
   c.OperandType == OperandType.InlineVar
      ? 2:
   c.OperandType == OperandType.InlineI8 ||
    c.OperandType == OperandType.InlineR
      ? 8:
    c.OperandType == OperandType.InlineSwitch
      ? 4 * (BitConverter.ToInt32 (_il, _pos) + 1) :
      4; // All others are 4 bytes
  if (_pos + operandLength > _il.Length)
    throw new Exception ("Unexpected end of IL");
  string result = FormatOperand (c, operandLength);
 if (result == null)
  {
                           // Write out operand bytes in hex
    result = "";
   for (int i = 0; i < operandLength; i++)</pre>
      result += _il [_pos + i].ToString ("X2") + " ";
  pos += operandLength;
 return result;
}
```

If the result of calling FormatOperand is null, it means the operand needs no special formatting, so we simply write it out in hexadecimal. We could test the disassembler at this point by writing a FormatOperand method that always returns null. Here's what the output would look like:

Although the opcodes are correct, the operands are not much use. Instead of hexadecimal numbers, we want member names and strings. The FormatOperand method, when it's written, will address this—identifying the special cases that benefit from such formatting. These comprise most four-byte operands and the short branch instructions:

```
string FormatOperand (OpCode c, int operandLength)
{
  if (operandLength == 0) return "";

  if (operandLength == 4)
    return Get4ByteOperand (c);
  else if (c.OperandType == OperandType.ShortInlineBrTarget)
    return GetShortRelativeTarget();
  else if (c.OperandType == OperandType.InlineSwitch)
    return GetSwitchTarget (operandLength);
  else
    return null;
}
```

There are three kinds of four-byte operands that we treat specially. The first is references to members or types—with these, we extract the member or type name by calling the defining module's ResolveMember method. The second case is strings—these are stored in the assembly module's metadata and can be retrieved by calling ResolveString. The final case is branch

targets, where the operand refers to a byte offset in the IL. We format these by working out the absolute address *after* the current instruction (+ four bytes):

```
string Get4ByteOperand (OpCode c)
  int intOp = BitConverter.ToInt32 (_il, _pos);
  switch (c.OperandType)
   case OperandType.InlineTok:
   case OperandType.InlineMethod:
   case OperandType.InlineField:
    case OperandType.InlineType:
     MemberInfo mi;
     try { mi = _module.ResolveMember (intOp); }
     catch { return null; }
     if (mi == null) return null;
     if (mi.ReflectedType != null)
        return mi.ReflectedType.FullName + "." + mi.Name;
     else if (mi is Type)
        return ((Type)mi).FullName;
        return mi.Name;
   case OperandType.InlineString:
      string s = _module.ResolveString (intOp);
     if (s != null) s = "'" + s + "'";
      return s;
   case OperandType.InlineBrTarget:
      return "IL_" + (_pos + intOp + 4).ToString ("X4");
   default:
     return null;
 }
}
```

NOTE

The point where we call ResolveMember is a good window for a code analysis tool that reports on method dependencies.

For any other four-byte opcode, we return null (this will cause ReadOperand to format the operand as hex digits).

The final kinds of operand that need special attention are short branch targets and inline switches. A short branch target describes the destination offset as a single signed byte, as at the end of the current instruction (i.e., + one byte). A switch target is followed by a variable number of four-byte branch destinations:

```
string GetShortRelativeTarget()
{
   int absoluteTarget = _pos + (sbyte) _il [_pos] + 1;
   return "IL_" + absoluteTarget.ToString ("X4");
}

string GetSwitchTarget (int operandLength)
{
   int targetCount = BitConverter.ToInt32 (_il, _pos);
   string [] targets = new string [targetCount];
   for (int i = 0; i < targetCount; i++)
   {
     int ilTarget = BitConverter.ToInt32 (_il, _pos + (i + 1) * 4);
     targets [i] = "IL_" + (_pos + ilTarget + operandLength).ToString ("X4");
   }
   return "(" + string.Join (", ", targets) + ")";
}</pre>
```

This completes the disassembler. We can test it by disassembling one of its own methods:

```
MethodInfo mi = typeof (Disassembler).GetMethod (
   "ReadOperand", BindingFlags.Instance | BindingFlags.NonPublic);
Console.WriteLine (Disassembler.Disassemble (mi));
```