

TEST OVERVIEW:

For this initial test, the waterfall for INT or RV will need to be at least 80-85% bidding SOV.

EXPERIMENT SETUP (*example: INT*)

- For all of these ad unit IDs, disable back to back.
 - NOTE: B2B (preloading next ad to be ready to show immediately after the current ad is closed) and auto retries (for instances of no ad) both need to be disabled.
 - NOTE: Please disable auto_retries AFTER MAX SDK initialization, otherwise it will crash.
 - B2B needs to be disabled BEFORE init

```
MaxSdk.SetExtraParameter("disable_b2b_ad_unit_ids",
    "${high},{med},{main}");
```
 - Auto retries needs to be disabled AFTER init

```
MaxSdk.SetInterstitialExtraParameter(high, "disable_auto_retries",
    "true");

MaxSdk.SetInterstitialExtraParameter(medium, "disable_auto_retries",
    "true");

MaxSdk.SetInterstitialExtraParameter(low, "disable_auto_retries",
    "true");
```
- [Enable selective init](#) inclusive of all the ad units that will be initialized per user. This will ensure that initialization is not affected by further delays if you have an account with a lot of ad units in use.
- Do not use any additional ad units aside from the ones explained above as it will break the ad load cycle (e.g backfill ad units, additional inter ad placements et al)

AD UNIT SETUP:

- Make sure to request interstitials in sequence as shown in the diagram.
- Use geo based floors in the MAX UI based on tiers for HIGH and MEDIUM ad units. Numbers will need to be adjusted once the first iteration is live. While an advanced approach here would be to leverage user based floors per impression on the client-side based on historical data, it is not tested and no recommendations can be made at this time.


Floors based on tiers:

- HIGH: Please refer to end of document for recommended floors
- MEDIUM: ½ of HIGH
- MAIN INTER ad unit: No floors. This is your waterfall with tags and bidders, optimized for high CPM with all the networks and price points.

AD LOAD SETUP:

- Post successful init, load HIGH_ad unit first. Wait for the results, and load the MEDIUM floor ad unit after.
- Upon no fill, LOAD the main ad unit without the bid floor and will have fill for all ad requests.
- Rinse and repeat. That means HIGH will show if it loads. If no fill, Medium will be loaded and shown, and If no fill, we will fallback to the main ad unit which will fill as usual.
- In addition to adload failed, display failure should also retrigger a new ad load cycle.
- Amazon APS has an extra parameter you'll have to set on first load. For this test, just use the main no floor ad unit ID.
- In this setup, the only retry is this new loop you are creating (ie if you get fill in the high waterfall, stop. Next retry starts at high, then medium, then main. If you get no fill at high, you ask for medium, Then if you get fill for medium, the next retry should still start at high).
- If all else fails for high, medium, and main, you retry at high again. You can stop at 3 retries if you'd like to avoid infinite loops that might cause crashes.

Flow chart of ad request logic below:



- We recommend keeping HIGH and MEDIUM bidder-only with at least 8-10 SDK bidders in the waterfall. Adding high priced point floors for select networks might be tested in new iterations but might be expected to induce latency with no incremental gains.
- Note that some networks will have fill and display issues when a different network placement ID is used in all ad units that are making these sequential ad load calls. We recommend using the same placement ID across all ad unit IDs.