



Mongoose New Tenant Guide

Release 9.03.11

Copyright © 2017 Infor

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement, the terms of which separate agreement shall govern your use of this material and all supplemental related materials ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above. Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Without limitation, U.S. export control laws and other applicable export and import laws govern your use of this material and you will neither export or re-export, directly or indirectly, this material nor any related materials or supplemental information in violation of such laws, or use such materials for any purpose prohibited by such laws.

Trademark Acknowledgements

The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or related affiliates and subsidiaries. All rights reserved. All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Release: \${drm-product-code} 9.03.11

Publication Date: June 23, 2017

Document code: lib_9.03.20_mongooseolh_mongoose_en-us

Contents

Contacting Infor.....5

About this guide.....7

Your application's URLs.....9

Setting up replication of security BODs between Ming.le and Mongoose.....11

Contacting Infor

If you have questions about Infor products, go to the Infor Xtreme Support portal.

If we update this document after the product release, we will post the new version on this website. We recommend that you check this website periodically for updated documentation.

If you have comments about Infor documentation, contact documentation@infor.com.

About this guide

This guide serves as a quick-start guide to help you find and connect to your new Mongoose environment, and to complete your post-provisioning steps.

Use this guide as a quick reference for your site. This guide does not teach you about general Mongoose practices.

Intended audience

This guide is for system administrators for Mongoose being used in a Platform as a Service (PaaS) environment.

Your application's URLs

These are the URLs you need to reach your environment:

Note: In each case, these values are used:

- `<farmid>` is the identifier for the server farm.
- `<tenantid>` is the identifier for the tenant.
- `<envid>` is the identifier for the environment.
- Environment-specific - Web client:
`https://<farmid>ap.mongoose.awsdev.infor.io/WSWebClient/default.aspx?configgroup=<tenantid>_Mongoose_<envid>&forcesso=1`
- Environment-specific - WinStudio Click-Once installation:
`https://<farmid>ap.mongoose.awsdev.infor.io/ClientDeploy/Mongoose.application?configgroup=<tenantid>_Mongoose_<envid>`
- All customer environments - Web client:
`https://<farmid>ap.mongoose.awsdev.infor.io/WSWebClient/default.aspx?configgroup=<tenantid>__Mongoose&forcesso=1`
- All customer environments - WinStudio Click-Once installation:
`https://<farmid>ap.mongoose.awsdev.infor.io/ClientDeploy/Mongoose.application?configgroup=<tenantid>__Mongoose&forcesso=1`
- REST Web Service endpoint:
`https://<farmid>ws.mongoose.awsdev.infor.io/IDORequestService/MGRestService.svc`
- SOAP Web Service endpoint:
`https://farmidws.mongoose.awsdev.infor.io/IDORequestService/IDOWebService.asmx`
- Help:
`https://<farmid>ap.mongoose.awsdev.infor.io/Mongoose/Language/en-us/default.html`

Setting up replication of security BODs between Ming.le and Mongoose

These are the steps required to complete post-provisioning when setting up the replication of security BODs between Ming.le and Mongoose:

- 1 Open the Ming.le application, using the URL provided in the topic ""Your application's URLs" on page 9".
- 2 Click the Grid icon at the top-left to view the available applications in Ming.le.
- 3 Select the ION Desk Application.
- 4 At the top left, click the "hamburger" icon next to **Status Overview**.
This opens an accordian menu.
- 5 Activate the message listener:
 - a Expand **Model**, then **Connect**, and select **Message Listeners**.
 - b Select the Message Listener for Ming.le.
 - c Under **DocumentsSync**, **Process**, and **Confirm**, and then select **Save**.
Once saved, the **Activate** button is enabled.
 - d To activate the message listener, click **Activate**.
- 6 Configure the Ming.le connection point:
 - a Go back to the accordion menu, and under **Model > Connect**, select **Connection Points**.
 - b Select the Ming.le connection point.
 - c Under **Documents**, to bring up a list of the available documents, click , select the options for **Add**.
 - d Search for the term "Security".
 - e Select these options:
 - Process.SecurityPermissionMaster
 - Sync.SecurityPermissionMaster
 - Process.SecurityRoleMaster
 - Sync.SecurityRoleMaster
 - Process.SecurityUserMaster
 - Sync.SecurityUserMaster
 - f Click **OK**.

- g For each of the process documents select **Receive in Application**, select the, and for each of the sync documents, select **Send from Application**.
 - h Click the save icon.
- 7 Configure the Mongoose connection point:
- a Go back to **Connection Points**, and select the Mongoose connection point.
 - b Under **Documents**, to bring up a list of the available documents, click **Add**.
 - c Search for the term "Security".
 - d Select these options:
 - Process.SecurityPermissionMaster
 - Sync.SecurityPermissionMaster
 - Process.SecurityRoleMaster
 - Sync.SecurityRoleMaster
 - Process.SecurityUserMaster
 - Sync.SecurityUserMaster
 - e Click **OK**.
 - f For each of the process documents select **Send from Application**, and for each of the sync documents, select **Receive in Application**.
 - g Click the save icon.
- 8 Add a document flow from Ming.le to Mongoose:
- a Go back to the accordion menu, and under **Model > Connect**, select **Document Flows**.
 - b To add the document flow, click **Add**.
 - c Name the document flow **MingleToMongoose** and give it a description.
 - d On the right, drag an application icon onto the flow diagram, between **Start** and **End**.
 - e For that application's properties, name it **Mingle**.
 - f Within its properties, click **Add**, and then select **Ming.le** for the application.
 - g Click **OK**.
 - h In the flow diagram, next to **Mingle**, select the document icon.
 - i Below the **Documents** properties, click **ADD**, and then select the three security documents added earlier, using the Sync verb.
 - j Click **OK**.
 - k Drag another application icon onto the flow diagram, placing it after **Mingle** and before **End**.
 - l Name this application **Mongoose**, and then click **ADD**.
 - m Select **Mongoose** as the application, and then click **OK**.
 - n Click the Save icon.
- The Activate icon is now available.
- 9 To activate the document flow, click the Activate icon.
- 10 Create a document flow from Mongoose to Ming.le:
- a Go back to **Document Flows**, and click **Add** to add the document flow.

- b Name this flow **MongooseToMingle** and give it a description.
- c On the right, drag another application icon on to the flow diagram, between **Start** and **End**.
- d For this application's properties, name it **Mongoose**.
- e Within its properties, click **Add**, and then select **Mongoose** for the application.
- f Click **OK**.
- g In the flow diagram, next to **Mongoose**, select the document icon.
- h In the **Documents** properties below, click **ADD**, and then select the three security documents added earlier, using the Process verb.
- i Click **OK**.
- j Drag another application icon to the flow diagram, placing it after **Mongoose**, and before **End**.
- k Name this application **Mingle**, and then click **ADD**.
- l Select **Ming.le** as the application, and then click **OK**.

The Activate icon is now available.

11 To activate the document flow, click the Activate icon.

To verify that the flows are now active, navigate in the accordian menu to **Manage > Connect** and select **Active Document Flows**. You should see your newly created flows there.

