

# Chapter 2

# Assemblers

---



# Outline

---

- 2.1 Basic Assembler Functions
- 2.2 Machine-Dependent Assembler Features
- 2.3 Machine-Independent Assembler Features
- 2.4 Assembler Design Options
- 2.5 Implementation Examples

# Introduction to Assemblers

---

- Fundamental functions
  - Translate mnemonic operation codes to their *machine language* equivalents
  - Assign *machine addresses* to *symbolic labels* used by the programmer
- The feature and design of an assembler depend
  - *Source language* it translate
  - The *machine language* it produce

## 2.1 Basic Assembler Functions

---

### □ *Assembler*

- A program that accepts an *assembly language program* as input and produces its *machine language equivalent* along with *information for the loader*

## 2.1 Basic Assembler Functions (Cont.)

---

- Constructions of assembly language program

- *Instruction*

*Label mnemonic operand*

- Operand

- Direct addressing
      - E.g. LDA ZERO
    - Immediate addressing
      - E.g. LDA #0
    - Indexed addressing
      - E.g. STCH BUFFER, X
    - Indirect addressing
      - E.g J @RETADR

## 2.1 Basic Assembler Functions (Cont.)

---

- Constructions of assembly language program (Cont.)

- *Data*

- Label BYTE value

- Label WORD value

- Label RESB value

- Label RESW value

- Label: name of operand
      - value: integer, character
      - E.g. EOF BYTE C'EOF'
      - E.g. FIVE WORD 5

# Assembler Directives

---

## □ Pseudo-instructions

- Not translated into machine instructions
- Provide instructions to the assembler itself

## □ Basic assembler directives

- **START:** specify *name* and *starting address of the program*
- **END:** specify *end of program* and (option) *the first executable instruction in the program*
  - If not specified, use the address of the first executable instruction
- **BYTE:** direct the assembler to *generate constants*
- **WORD**
- **RESB:** : instruct the assembler to *reserve memory location* without generating data values
- **RESW**

# Example of a SIC Assembler Language Program

---

- Show the generated *object code* for each statement in Fig. 2.1
- *Loc* column shows the *machine address* for each part of the assembled program
  - Assume program starts at address 1000
  - All instructions, data, or reserved storage are *sequential arranged* according to their order in source program.
  - A *location counter* is used to keep track the address changing

# Example of a SIC Assembler Language Program (Fig 2.1,2.2)

<b>Line</b>	<b>Loc</b>	<b>Source statement</b>	<b>Object code</b>
5	1000	COPY	
10	1000	FIRST	141033
15	1003	CLOOP	482039
20	1006		001036
25	1009		281030
30	100C		301015
35	100F		482061
40	1012		3C1003
45	1015	ENDFIL	00102A
50	1018		0C1039
55	101B		00102D
60	101E		0C1036
65	1021		482061
70	1024		081033
75	1027		4C0000
80	102A	EOF	454F46
85	102D	THREE	000003
90	1030	ZERO	000000
95	1033	RETADR	
100	1036	LENGTH	
105	1039	BUFFER	4096

# Example of a SIC Assembler Language Program (Fig 2.1,2.2) (Cont.)

110		:			
115		:	SUBROUTINE TO READ RECORD INTO BUFFER		
120		:			
125	2039	RDREC	LDX	ZERO	041030
130	203C		LDA	ZERO	001030
135	203F	RLOOP	TD	INPUT	E0205D
140	2042		JEQ	RLOOP	30203F
145	2045		RD	INPUT	D8205D
150	2048		COMP	ZERO	281030
155	204B		JEQ	EXIT	302057
160	204E		STCH	BUFFER,X	549039
165	2051		TIX	MAXLEN	2C205E
170	2054		JLT	RLOOP	38203F
175	2057	EXIT	STX	LENGTH	101036
180	205A		RSUB		4C0000
185	205D	INPUT	BYTE	X'F1'	F1
190	205E	MAXLEN	WORD	4096	001000
195					

# Example of a SIC Assembler Language Program (Fig 2.1,2.2) (Cont.)

195	.				
200	.			SUBROUTINE TO WRITE RECORD FROM BUFFER	
205	.				
210	2061	WRREC	LDX	ZERO	041030
215	2064	WLOOP	TD	OUTPUT	E02079
220	2067		JEQ	WLOOP	302064
225	206A		LDCH	BUFFER,X	509039
230	206D		WD	OUTPUT	DC2079
235	2070		TIX	LENGTH	2C1036
240	2073		JLT	WLOOP	382064
245	2076		RSUB		4C0000
250	2079	OUTPUT	BYTE	X'05'	05
255			END	FIRST	

Figure 2.2 Program from Fig. 2.1 with object code.

# Functions of a Basic Assembler

---

- Convert *mnemonic operation codes* to their *machine language equivalents*
  - E.g. STL -> 14 (line 10)
- Convert *symbolic operands* to their equivalent *machine addresses*
  - E.g. RETADR -> 1033 (line 10)
- Build the machine instructions in the proper *format*
- Convert the *data constants* to *internal machine representations*
  - E.g. EOF -> 454F46 (line 80)
- Write the *object program* and the *assembly listing*

# Functions of a Basic Assembler (Cont.)

---

- All of above functions can be accomplished by *sequential processing* of the source program
  - *Except number 2 in processing symbolic operands*
- Example
  - **10 STL RETADR**
    - *RETADR* is not yet defined when we encounter *STL* instruction
    - Called *forward reference*

# Symbolic Operands (Renew)

---

- We're not likely to write *memory addresses* directly in our code.
  - Instead, we will define *variable names*.
- Other examples of symbolic operands
  - Labels (for jump instructions)
  - Subroutines
  - Constants

# Address Translation Problem

---

- *Forward reference*
  - A reference to a label that is defined later in the program
    - We will be unable to process this statement
- As a result, most assemblers make 2 passes over the source program
  - *1<sup>st</sup> pass*: scan *label definitions* and *assign addresses*
  - *2<sup>nd</sup> pass*: actual translation (object code)

# Functions of Two Pass Assembler

---

- **Pass 1 - define symbols (assign addresses)**
  - Assign addresses to all statements in the program
  - Save the values assigned to all labels for use in Pass 2
  - Process some assembler directives
- **Pass 2 - assemble instructions and generate object program**
  - Assemble instructions
  - Generate data values defined by BYTE, WORD, etc.
  - Process the assembler directives not done in Pass 1
  - Write the object program and the assembly listing

# Object Program

---

- Finally, assembler must write the generated object code to some output device
  - Called *object program*
  - Will be later loaded into memory for execution

# Object Program (Cont.)

---

- Contains 3 types of records:

- **Header record:**

Col. 1	H
Col. 2-7	Program name
Col. 8-13	Starting address (hex)
Col. 14-19	Length of object program in bytes (hex)

- **Text record**

Col.1	T
Col.2-7	Starting address in this record (hex)
Col. 8-9	Length of object code in this record in bytes (hex)
Col. 10-69	Object code (hex) (2 columns per byte)

- **End record**

Col.1	E
Col.2~7	Address of first executable instruction (hex) (END program_name)

# Object Program for Fig 2.2 (Fig 2.3)

Program name,Starting address (hex),Length  
of object program in bytes (hex)

```
HCOPY 00100000107A
T0010001E1410334820390010362810303010154820613C100300102A0C103900102D
T00101E150C10364820610810334C0000454F46000003000000
T0020391E041030001030E0205D30203FD8205D2810303020575490392C205E38203F
T0020571C1010364C0000F1001000041030E02079302064509039DC20792C1036
T002073073820644C000005
E001000
```

Address of first executable  
instruction (hex)

Q 3 Object program corresponds to

Starting address (hex),Length of object  
code in this record (hex),Object code (hex)

## 2.1.2 Assembler Algorithm and Data Structures

---

- Algorithm
  - Two-pass assembler
  
- Data Structures
  - Operation Code Table (OPTAB)
  - Symbol Table (SYMTAB)
  - Location Counter (LOCCTR)

# Internal Data Structures

---

## □ OPTAB (operation code table)

- Content
  - Menmonic machine code and its machine language equivalent
  - May also include instruction format, length etc.
- Usage
  - Pass 1: used to loop up and validate operation codes in the source program
  - Pass 2: used to translate the operation codes to machine language
- Characteristics
  - Static table, predefined when the assembler is written
- Implementation
  - Array or hash table with mnemonic operation code as the key (preferred)
- Ref. Appendix A

# Internal Data Structures (Cont.)

---

## □ SYMTAB (symbol table)

- Content
  - Label name and its value (address)
  - May also include flag (type, length) etc.
- Usage
  - Pass 1: labels are entered into SYMTAB with their address (from LOCCTR) as they are encountered in the source program
  - Pass 2: symbols used as operands are looked up in SYMTAB to obtain the address to be inserted in the assembled instruction
- Characteristic
  - Dynamic table (insert, delete, search)
- Implementation
  - Hash table for efficiency of *insertion* and *retrieval*



# Internal Data Structures (Cont.)

---

## □ Location Counter

- A variable used to help in *assignment of addresses*
- Initialized to the beginning address specified in the START statement
- Counted in bytes

## Algorithm for 2 Pass Assembler (Fig 2.4)

---

- Figure 2.4 (a): algorithm for pass 1 of assembler
  
- Figure 2.4 (b): algorithm for pass 2 of assembler


## Algorithm for 2 Pass Assembler (Fig 2.4)

---

- Both pass1 and pass 2 need to read the source program.
  - However, pass 2 needs more information
    - Location counter value, error flags
- **Intermediate file**
  - Contains each source statement with its assigned address, error indicators, etc
  - Used as the input to Pass 2

# Intermediate File

---



# Algorithm for Pass 1 of Assembler (Fig 2.4a)

Pass 1:

**begin**

    read first input line

**if** OPCODE = 'START' **then**

**begin**

            save #[OPERAND] as starting address

            initialize LOCCTR to starting address

            write line to intermediate file

            read next input line

**end** {if START}

**else**

        initialize LOCCTR to 0

```

while OPCODE ≠ 'END' do
  begin
    if this is not a comment line then
      begin
        if there is a symbol in the LABEL field then
          begin
            search SYMTAB for LABEL
            if found then
              set error flag (duplicate symbol)
            else
              insert (LABEL, LOCCTR) into SYMTAB
            end {if symbol}
          search OPTAB for OPCODE
          if found then
            add 3 {instruction length} to LOCCTR
          else if OPCODE = 'WORD' then
            add 3 to LOCCTR
          else if OPCODE = 'RESW' then
            add 3 * # [OPERAND] to LOCCTR
          else if OPCODE = 'RESB' then
            add # [OPERAND] to LOCCTR
          else if OPCODE = 'BYTE' then
            begin
              find length of constant in bytes
              add length to LOCCTR
            end {if BYTE}
          else
            set error flag (invalid operation code)
        end {if not a comment}
        write line to intermediate file
        read next input line
      end {while not END}
      write last line to intermediate file
      save (LOCCTR - starting address) as program length
    end {Pass 1}
  
```

**Figure 2.4(a)** Algorithm for Pass 1 of assembler.

# Algorithm for Pass 2 of Assembler (Fig 2.4b)

---

Pass 2:

```
begin
    read first input line {from intermediate file}
    if OPCODE = 'START' then
        begin
            write listing line
            read next input line
        end {if START}
        write Header record to object program
        initialize first Text record
        . . .
```

```

while OPCODE ≠ 'END' do
    begin
        if this is not a comment line then
            begin
                search OPTAB for OPCODE
                if found then
                    begin
                        if there is a symbol in OPERAND field then
                            begin
                                search SYMTAB for OPERAND
                                if found then
                                    store symbol value as operand address
                                else
                                    begin
                                        store 0 as operand address
                                        set error flag (undefined symbol)
                                    end
                            end {if symbol}
                        else
                            store 0 as operand address
                            assemble the object code instruction
                        end {if opcode found}
                    else if OPCODE = 'BYTE' or 'WORD' then
                        convert constant to object code
                    if object code will not fit into the current Text record then
                        begin
                            write Text record to object program
                            initialize new Text record
                        end
                    add object code to Text record
                    end {if not comment}
                write listing line
                read next input line
            end {while not END}
            write last Text record to object program
            write End record to object program
            write last listing line
    end {Pass 2}

```

**Figure 2.4(b)** Algorithm for Pass 2 of assembler.

# Assembler Design

---

- Machine Dependent Assembler Features
  - instruction formats and addressing modes
  - program relocation
- Machine Independent Assembler Features
  - literals
  - symbol-defining statements
  - expressions
  - program blocks
  - control sections and program linking
- Assembler design Options
  - one-pass assemblers
  - multi-pass assemblers

## 2.2 Machine Dependent Assembler Features

---

- Machine Dependent Assembler Features
  - SIC/XE
  - Instruction formats and addressing modes
  - Program relocation



# SIC/XE Assembler

---

- Previous, we know how to implement the 2-pass SIC assembler.
  
- What's new for SIC/XE?
  - More addressing modes.
  - Program Relocation.

# SIC/XE Assembler (Cont.)

---

- SIC/XE
  - Immediate addressing: op **#c**
  - Indirect addressing: op **@m**
  - PC-relative or Base-relative addressing:
    - The assembler directive **BASE** is used with base-relative addressing
    - If displacements are too large to fit into a 3-byte instruction, then 4-byte extended format is used
  - Extended format: +op m
  - Indexed addressing: op m, **x**
  - Register-to-register instructions
  - Large memory
    - Support multiprogramming and need *program reallocation* capability

## Example of a SIC/XE Program (Fig 2.5)

---

- Improve the execution speed
  - Register-to-register instructions
  - Immediate addressing: op #c
    - Operand is already present as part of the instruction
  - Indirect addressing: op @m
    - Often avoid the need of another instruction

# Example of a SIC/XE Program (Fig 2.5,2.6)

<b>Line</b>	<b>Loc</b>	<b>Source statement</b>			<b>Object code</b>
5	0000	COPY	START	0	
10	0000	FIRST	STL	RETADR	17202D
12	0003		LDB	#LENGTH	69202D
13			BASE	LENGTH	
15	0006	CLOOP	+JSUB	RDREC	4B101036
20	000A		LDA	LENGTH	032026
25	000D		COMP	#0	290000
30	0010		JEQ	ENDFIL	332007
35	0013		+JSUB	WRREC	4B10105D
40	0017		J	CLOOP	3F2FEC
45	001A	ENDFIL	LDA	EOF	032010
50	001D		STA	BUFFER	0F2016
55	0020		LDA	#3	010003
60	0023		STA	LENGTH	0F200D
65	0026		+JSUB	WRREC	4B10105D
70	002A		J	@RETADR	3E2003
80	002D	EOF	BYTE	C'EOF'	454F46
95	0030	RETADR	RESW	1	
100	0033	LENGTH	RESW	1	
105	0036	BUFFER	RESB	4096	

## Example of a SIC/XE Program (Fig 2.5,2.6) (Cont.)

110	.				
115	.		SUBROUTINE TO READ RECORD INTO BUFFER		
120	.				
125	1036	RDREC	CLEAR X		B410
130	1038		CLEAR A		B400
132	103A		CLEAR S		B440
133	103C		+LDT #4096		75101000
135	1040	RLOOP	TD INPUT		E32019
140	1043		JEQ RLOOP		332FFA
145	1046		RD INPUT		DB2013
150	1049		COMPR A, S		A004
155	104B		JEQ EXIT		332008
160	104E		STCH BUFFER, X		57C003
165	1051		TIXR T		B850
170	1053		JLT RLOOP		3B2FEA
175	1056	EXIT	STX LENGTH		134000
180	1059		RSUB		4F0000
185	105C	INPUT	BYTE X'F1'		F1
190					

## Example of a SIC/XE Program (Fig 2.5,2.6) (Cont.)

---

```
195          .
200          .           SUBROUTINE TO WRITE RECORD FROM BUFFER
205          .
210      105D    WRREC    CLEAR     X           B410
212      105F    LDT      LENGTH    774000
215      1062    WLOOP    TD        OUTPUT    E32011
220      1065    JEQ      WLOOP    332FFA
225      1068    LDCH     BUFFER,X  53C003
230      106B    WD       OUTPUT   DF2008
235      106E    TIXR     T         B850
240      1070    JLT      WLOOP   3B2FEF
245      1073    RSUB     4F0000
250      1076    OUTPUT   BYTE     X'05'   05
255          END      FIRST
```

**Figure 2.6** Program from Fig. 2.5 with object code.

## 2.2.1 Instruction Formats and Addressing Modes

---

- START now specifies a beginning program address of 0
  - Indicate a *relocatable program*
- Register translation
  - For example: *COMPR A, S => A004*
  - Must keep the register name (A, X, L, B, S, T, F, PC, SW) and their values (0,1, 2, 3, 4, 5, 6, 8, 9)
    - Keep in SYMTAB

# Address Translation

---

- Most register-to-memory instructions are assembled using *PC relative* or *base relative* addressing
  - Assembler must calculate a *displacement* as part of the object instruction
  - If displacement can be fit into 12-bit field, format 3 is used.
  - Format 3: 12-bit address field
    - Base-relative: 0~4095
    - PC-relative: -2048~2047
  - Assembler attempts to translate using PC-relative first, then base-relative
    - If displacement in PC-relative is out of range, then try base-relative

# Address Translation (Cont.)

---

- If displacement can not be fit into 12-bit field in the object instruction, format 4 must be used.
  - Format 4: 20-bit address field
  - No displacement need to be calculated.
    - 20-bit is large enough to contain the full memory address
  - Programmer must specify extended format: +op m
  - For example: *+JSUB RDREC => 4B101036*
    - $LOC(RDREC) = 1036$ , get it from SYMTAB

# PC-Relative Addressing Modes

□ *10 0000 FIRST STL RETADR 17202D*

- Displacement= RETADR – (PC) = 30-3 = 2D
- Opcode (6 bits) =  $14_{16} = 00010100_2$
- nixbpe=110010
  - n=1, i = 1: indicate neither *indirect* nor *immediate* addressing
  - p = 1: indicate *PC-relative* addressing




Object Code = 17202D

# PC-Relative Addressing Modes (Cont.)

□ 40 0017 J CLOOP 3F2FEC

- Displacement= CLOOP - (PC) = 6 - **1A** = -14 = FEC (2's complement for negative number)
- Opcode= $3C_{16}$  =  $00111100_2$
- nixbpe=110010



Object Code = 3F2FEC



# Base-Relative Addressing Modes

---

- Base register is under the control of the programmer
  - Programmer use assembler directive **BASE** to specify which value to be assigned to base register (B)
  - Assembler directive **NOBASE**: inform the assembler that the contents of base register no longer be used for addressing
  - **BASE** and **NOBASE** produce no executable code

# Base-Relative Addressing Modes (Cont.)

- 12                    *LDB #LENGTH*
- 13                    *BASE LENGTH*                    ;no object code
- 160 104E STCH    *BUFFER, X*                    57C003
  - Displacement= *BUFFER* – (B) = 0036 – 0033(=LOC(*LENGTH*)) = 3
  - Opcode=54=01010100
  - nixbpe=111100
    - n=1, i = 1: indicate neither *indirect* nor *immediate* addressing
    - x = 1: *indexed* addressing
    - b = 1: *base-relative* addressing

OPCODE	n	i	x	b	p	e	Address
0101 01	1	1	1	1	0	0	$(003)_{16}$

Object Code = 57C003

# Address Translation



---

- Assembler attempts to translate using *PC-relative* first, then *base-relative*
  - e.g. 175 1056 STX LENGTH 134000
    - Try PC-relative first
      - Displacement= LENGTH - (PC) = 0033 - 1056 = -1026 (hex)
    - Try base-relative next
      - displacement= LENGTH – (B) = 0033 – 0033 =0
      - Opcode=10
      - nixbpe=110100
        - n=1, i = 1: indicate neither *indirect* nor *immediate* addressing
        - b = 1: *base-relative* addressing

# Immediate Address Translation

---

- Convert the *immediate* operand to its internal representation and insert it into the instruction
- 55 0020                    LDA #3                    010003
  - Opcode=00
  - nixbpe=010000
    - i = 1: *immediate addressing*





Object Code = 010003

# Immediate Address Translation (Cont.)

□ 133 103C +LDT #4096 75101000

- Opcode=74=01110100
- nixbpe=010001
  - i = 1: *immediate addressing*
  - e = 1: *extended instruction format* since 4096 is too large to fit into the 12-bit displacement field



Object Code = 75101000

# Immediate Address Translation (Cont.)

□ 12 0003      LDB      #LENGTH      69202D

- The immediate operand is the symbol LENGTH
  - The address of LENGTH is loaded into register B
- Displacement=LENGTH – (PC) = 0033 – 0006 = 02D
- Opcode=68<sub>16</sub> = 01101000<sub>2</sub>
- nixbpe=010010
  - Combined *PC relative* (p=1) with *immediate addressing* (i=1)



# Indirect Address Translation


---

- Indirect addressing
  - The contents stored at the location represent the *address* of the operand, not the operand itself
  - Target addressing is computed as usual (PC-relative or BASE-relative)
  - $n$  bit is set to 1

# Indirect Address Translation (Cont.)

□ 70 002A J @RETADR 3E2003

- Displacement= RETADR- (PC) = 0030 – 002D =3
- Opcode= 3C=00111100
- nixbpe=100010
  - n = 1: *indirect addressing*
  - p = 1: *PC-relative addressing*





# Note

---

- Ref: *Appendix A*

## 2.2.2 Program Relocation


---

- The larger main memory of SIC/XE
  - Several programs can be loaded and run at the same time.
  - This kind of sharing of the machine between programs is called *multiprogramming*
- To take full advantage
  - Load programs into memory wherever there is room
  - Not specifying a fixed address at assembly time
  - Called *program relocation*

## 2.2.2 Program Relocation (Cont.)

### *Absolute program* (or *absolute assembly*)

- Program must be loaded at the address specified *at assembly time*.
- E.g. Fig. 2.1




- What if the program is loaded to 2000

e.g. 55      101B      LDA      THREE      00202D

- Each absolute address should be modified

# Example of Program Relocation (Fig 2.7)



**Figure 2.7** Examples of program relocation.

## 2.2.2 Program Relocation (Cont.)

- *Relocatable* program

```
COPY START 0 ←  
FIRST STL RETADR  
:  
:
```

program loading  
starting address is  
determined *at load  
time*

- An object program that contains the information necessary to perform address modification for relocation
- The assembler must identify for the loader those parts of object program that need modification.
- No instruction modification is needed for
  - Immediate addressing (not a memory address)
  - PC-relative, Base-relative addressing
- The only parts of the program that require modification at load time are those that specify *direct addresses*
  - In SIC/XE, only found in extended format instructions

# Instruction Format vs. Relocatable Loader

---

- In SIC/XE
  - Format 1, 2, 3
    - Not affect
  - Format 4
    - Should be modified
- In SIC
  - Format with address field
    - Should be modified
    - SIC does not support PC-relative and base-relative addressing

# Relocatable Program

---

- We use modification records that are added to the object files.

Pass the *address-modification* information to the relocatable loader

- *Modification record*

- Col 1 M
- Col 2-7 Starting location of the address field to be modified, relative to the beginning of the program (hex)
- Col 8-9 length of the address field to be modified, in half-bytes
- E.g M<sub>0</sub>000007<sub>0</sub>05

Beginning address of the program is to be added to a field that begins at addr ox000007 and is 2.5 bytes in length.

# Object Program for Fig 2.6 (Fig 2.8)

```
HCOPY 000000001077
T0000001D17202D69202D4B1010360320262900003320074B10105D3F2FEC032010
T00001D130F20160100030F200D4B10105D3E2003454F46
T0010361DB410B400B44075101000E32019332FFADB2013A00433200857C003B850
T0010531D3B2FEA1340004F0000F1B410774000E32011332FFA53C003DF2008B850
T001070073B2FEF4F000005
M00000705
M00001405
M00002705
E000000
```

**Figure 2.8** Object program corresponding to Fig. 2.6.

## 2.3 Machine-Independent Assembler Features

---

- Literals
- Symbol-Defining Statements
- Expressions
- Program Blocks
- Control Sections and Program Linking

## 2.3.1 Literals

---

### □ Design idea

- Let programmers to be able to write the value of a constant operand as a part of the instruction that uses it.
- This avoids having to define the constant elsewhere in the program and make up a label for it.
- Such an operand is called a ***literal*** because the value is stated “literally” in the instruction.
- A literal is identified with the prefix =

### □ Examples

- 45 001A ENDFILLDA =C'EOF' 032010
- 215 1062 WLOOPTD =X'05' E32011

# Original Program (Fig. 2.6)

5	0000	COPY	START	0	
10	0000	FIRST	STL	RETADR	17202D
12	0003		LDB	#LENGTH	69202D
13			BASE	LENGTH	
15	0006	CLOOP	+JSUB	RDREC	4B101036
20	000A		LDA	LENGTH	032026
25	000D		COMP	#0	290000
30	0010		JEQ	ENDFIL	332007
35	0013		+JSUB	WRREC	4B10105D
40	0017		J	CLOOP	3F2FEC
45	001A	ENDFIL	<u>LDA</u>	<u>EOF</u>	032010
50	001D		STA	BUFFER	0F2016
55	0020		LDA	#3	010003
60	0023		STA	LENGTH	0F200D
65	0026		+JSUB	WRREC	4B10105D
70	002A		J	@RETADR	3E2003
80	002D	<u>EOF</u>	BYTE	C'EOF'	454F46
95	0030	RETADR	RESW	1	
100	0033	LENGTH	RESW	1	
105	0036	BUFFER	RESB	4096	
110					

# Using Literal (Fig. 2.9)

5	COPY	START	0	COPY FILE FROM INPUT TO OUTPUT
10	FIRST	STL	RETADR	SAVE RETURN ADDRESS
13		LDB	#LENGTH	ESTABLISH BASE REGISTER
14		BASE	LENGTH	
15	CLOOP	+JSUB	RDREC	READ INPUT RECORD
20		LDA	LENGTH	TEST FOR EOF (LENGTH = 0)
25		COMP	#0	
30		JEQ	ENDFIL	EXIT IF EOF FOUND
35		+JSUB	WRREC	WRITE OUTPUT RECORD
40		J	CLOOP	LOOP
45	ENDFIL	<u>LDA</u>	=C'EOF'	INSERT END OF FILE MARKER
50		STA	BUFFER	
55		LDA	#3	SET LENGTH = 3
60		STA	LENGTH	
65		+JSUB	WRREC	WRITE EOF
70		J	@RETADR	RETURN TO CALLER
93		<u>LTORG</u>		
95	RETADR	RESW	1	
100	LENGTH	RESW	1	LENGTH OF RECORD
105	BUFFER	RESB	4096	4096-BYTE BUFFER AREA
106	BUFEND	EQU	*	
107	MAXLEN	EQU	BUFEND-BUFFER	MAXIMUM RECORD LENGTH

# Object Program Using Literal

5	0000	COPY	START	0	
10	0000	FIRST	STL	RETADR	17202D
13	0003		LDB	#LENGTH	69202D
14			BASE	LENGTH	
15	0006	CLOOP	+JSUB	RDREC	4B101036
20	000A		LDA	LENGTH	032026
25	000D		COMP	#0	290000
30	0010		JEQ	ENDFIL	332007
35	0013		+JSUB	WRREC	4B10105D
40	0017		J	CLOOP	3F2FEC
45	001A	ENDFIL	LDA	=C'EOF'	032010
50	001D		STA	BUFFER	0F2016
55	0020		LDA	#3	010003
60	0023		STA	LENGTH	0F200D
65	0026		+JSUB	WRREC	4B10105D
70	002A		J	@RETADR	3E2003
93	002D	*	LTORG		The same as before
			=C'EOF'		454F46
95	0030	RETADR	RESW	1	

# Original Program (Fig. 2.6)

---

205		.			
210	105D	WRREC	CLEAR	X	B410
212	105F		LDT	LENGTH	774000
215	1062	WLOOP	<u>TD</u>	<u>OUTPUT</u>	<u>E32011</u>
220	1065		JEQ	WLOOP	332FFA
225	1068		LDCH	BUFFER,X	53C003
230	106B		<u>WD</u>	<u>OUTPUT</u>	<u>DF2008</u>
235	106E		TIXR	T	B850
240	1070		JLT	WLOOP	3B2FEF
245	1073		RSUB		4F0000
250	1076	OUTPUT	BYTE	X'05'	05
255			END	FIRST	

# Using Literal (Fig. 2.9)

---

```
195      .
200      .          SUBROUTINE TO WRITE RECORD FROM BUFFER
205      .
210      WRREC    CLEAR    X                  CLEAR LOOP COUNTER
212          LDT      LENGTH
215      WLOOP    TD      =X'05'             TEST OUTPUT DEVICE
220          JEQ      WLOOP
225          LDCH     BUFFER,X            GET CHARACTER FROM BUFFER
230          WD      =X'05'             WRITE CHARACTER
235          TIXR     T                  LOOP UNTIL ALL CHARACTERS
240          JLT      WLOOP            HAVE BEEN WRITTEN
245          RSUB
255          END      FIRST
```

# Object Program Using Literal

210	105D	WRREC	CLEAR	X	B410
212	105F		LDT	LENGTH	774000
215	1062	WLOOP	TD	=X'05'	E32011
220	1065		JEQ	WLOOP	332FFA
225	1068		LDCH	BUFFER,X	53C003
230	106B		WD	=X'05'	DF2008
235	106E		TIXR	T	B850
240	1070		JLT	WLOOP	3B2FEF
245	1073		RSUB	The same as before	4F0000
255	1076	*	END	FIRST	05

# Object Program Using Literal (Fig 2.9 & 2.10)

<b>Line</b>	<b>Loc</b>	<b>Source statement</b>			<b>Object code</b>
5	0000	COPY	START	0	
10	0000	FIRST	STL	RETADR	17202D
13	0003		LDB	#LENGTH	69202D
14			BASE	LENGTH	
15	0006	CLOOP	+JSUB	RDREC	4B101036
20	000A		LDA	LENGTH	032026
25	000D		COMP	#0	290000
30	0010		JEQ	ENDFIL	332007
35	0013		+JSUB	WRREC	4B10105D
40	0017		J	CLOOP	3F2FEC
45	001A	ENDFIL	LDA	=C'EOF'	032010
50	001D		STA	BUFFER	0F2016
55	0020		LDA	#3	010003
60	0023		STA	LENGTH	0F200D
65	0026		+JSUB	WRREC	4B10105D
70	002A		J	@RETADR	3E2003
93	002D	*	LTORG		
			=C'EOF'		454F46
95	0030	RETADR	RESW	1	
100	0033	LENGTH	RESW	1	
105	0036	BUFFER	RESB	4096	
106	1036	BUFEND	EQU	*	
107	1000	MAXLEN	EQU	BUFEND-BUFFER	
110		.			

# Object Program Using Literal (Fig 2.9 & 2.10) (Cont.)

---

```
110      .
115      .          SUBROUTINE TO READ RECORD INTO BUFFER
120      .
125      1036    RDREC    CLEAR    X           B410
130      1038    .         CLEAR    A           B400
132      103A    .         CLEAR    S           B440
133      103C    .         +LDT     #MAXLEN   75101000
135      1040    RLOOP    TD       INPUT      E32019
140      1043    .         JEQ      RLOOP      332FFA
145      1046    .         RD       INPUT      DB2013
150      1049    .         COMPR    A,S        A004
155      104B    .         JEQ      EXIT       332008
160      104E    .         STCH     BUFFER,X  57C003
165      1051    .         TIXR     T          B850
170      1053    .         JLT      RLOOP      3B2FEA
175      1056    EXIT     STX      LENGTH    134000
180      1059    .         RSUB     .          4F0000
185      105C    INPUT    BYTE     X'F1'    F1
195
```

## Object Program Using Literal (Fig 2.9 & 2.10) (Cont.)

195	.				
200	.			SUBROUTINE TO WRITE RECORD FROM BUFFER	
205	.				
210	105D	WRREC	CLEAR	X	B410
212	105F		LDT	LENGTH	774000
215	1062	WLOOP	TD	=X'05'	E32011
220	1065		JEQ	WLOOP	332FFA
225	1068		LDCH	BUFFER,X	53C003
230	106B		WD	=X'05'	DF2008
235	106E		TIXR	T	B850
240	1070		JLT	WLOOP	3B2FEF
245	1073		RSUB		4F0000
255			END	FIRST	
	1076	*		=X'05'	05

**Figure 2.10** Program from Fig. 2.9 with object code.

# Literals vs. Immediate Operands

---

## □ Immediate Operands

- The operand value is assembled as *part of the machine instruction*
- e.g. 55 0020 LDA #3 010003

Similar to define  
constant

## □ Literals

- The assembler generates the specified value as a constant *at some other memory location*
- The effect of using a literal is exactly the same as if the programmer had *defined the constant* and used the *label* assigned to the constant as the instruction operand.
- e.g. 45 001A ENDFIL LDA =C'EOF' 032010 (Fig. 2.9)

## □ Compare (Fig. 2.6)

- e.g. 45 001A ENDFIL LDA EOF 032010  
80 002D EOF BYTE C'EOF' 454F46

# Literal - Implementation

---

## □ *Literal pools*

- All of the literal operands are gathered together into one or more *literal pools*
- Normally, literal are placed at the end of the object program, i.e., following the END statement by the *assembler*
- E.g., Fig. 2.10 (END statement)

255	END	FIRST
1076 *	=X'05'	05

# Literal – Implementation (Cont.)

---

- In some case, *programmer* would like to place literals into a pool at some other location in the object program
  - Using assembler directive **LTORG** (see Fig. 2.10)
  - Create a literal pool that contains all of the literal operands used since the previous LTORG

- e.g., 45 001A ENDFIL LDA =C'EOF' 032010 (Fig.2.10)

93

**LTORG**

002D \* =C'EOF' 454F46

- Reason: keep the literal operand close to the instruction referencing it
    - Allow *PC-relative addressing* possible

# Literal - Implementation (Cont.)

## □ Duplicate literals

- e.g. 215 1062      WLOOP                  TD            =X'05'
- e.g. 230 106B                                      WD            =X'05'
- The assemblers should recognize duplicate literals and store only one copy of the specified data value

### □ Compare the character strings defining them

- E.g., =X'05'
- Easier to implement, but has potential problem (see next)

Or compare the generated data value

- E.g. the literals =C'EOF' and =X'454F46' would specify identical operand value.
- Better, but will increase the complexity of the assembler

Same symbols,  
only one address is  
assigned

# Basic Data Structure for Assembler to Handle Literal Operands

---

- *Data Structure: literal table - LITTAB*
  - Content
    - Literal name
    - The operand value and length
    - Address assigned to the operand
  - Implementation
    - Organized as a hash table, using literal name or value as key.

# How the Assembler Handles Literals?

---

- Pass 1
  - Build LITTAB with literal name, operand value and length, (leaving the address unassigned).
  - Handle duplicate literals. (Ignore duplicate literals)
  - When encounter LTORG statement or end of the program, assign an address to each literal not yet assigned an address
    - Remember to update the PC value to assign each literal's address
- Pass 2
  - Search LITTAB for each literal operand encountered
  - Generate data values in the object program exactly as if they are generated by BYTE or WORD statements
  - Generate modification record for literals that represent an *address* in the program (e.g. a location counter value)

## 2.3.2 Symbol-Defining Statements

---

- **Labels** on instructions or data areas
  - The value of such a label is the *address* assigned to the statement on which it appears
- Defining symbols
  - All programmer to define symbols and specify their values
  - Format: symbol    **EQU**    value
    - Value can be *constant* or *expression involving constants and previously defined symbols*
  - Example
    - MAXLEN    EQU    4096
    - +LDT    #MAXLEN

## 2.3.2 Symbol-Defining Statements (Cont.)

---

- Usage:
  - Make the source program easier to understand
- How assembler handles it?
  - In pass 1: when the assembler encounters the EQU statement, it enters the symbol into SYMTAB for later reference.
  - In pass 2: assemble the instruction with the *value* of the symbol
    - Follow the previous approach

# Examples of Symbol-Defining Statements

---

- E.g. +LDT #4096 (Fig 2.5)
  - MAXLEN EQU 4096
  - +LDT #MAXLEN

- E.g. define mnemonic names for registers

- A EQU 0
- X EQU 1
- L EQU 2
- ...

- E.g. define names that reflect the logical function of the registers in the program

- BASE EQU R1
- COUNT EQU R2
- INDEX EQU R3

# Forward Reference

---

- All *symbol-defining directives* do **not** allow forward reference for 2-pass assembler

- e.g., EQU...
- All symbols used on the *right-hand side* of the statement must have been defined previously

E.g. (Cannot be assembled in 2-pass assm.)

ALPHA	EQU	BETA
BETA	EQU	DELTA
DELTA	RESW	1

## 2.3.3 Expressions

---

- Most assemblers allow the use of *expression* to replace symbol in the operand field.
  - Expression is evaluated by the assembler
  - Formed according to the rules using the operators  
+, -, \*, /
    - Division is usually defined to produce an integer result
    - Individual terms can be
      - Constants
      - User-defined symbols
      - Special terms: e.g., \* (= current value of location counter)

## 2.3.3 Expressions (Cont.)

---

### □ Review

- Values in the object program are
  - *relative* to the beginning of the program or
  - *absolute* (independent of program location)
- For example
  - Constants: absolute
  - Labels: relative

## 2.3.3 Expressions (Cont.)

---

- Expressions can also be classified as *absolute expressions* or *relative expressions*
  - E.g. (Fig 2.9)

107	MAXLEN	EQU BUFEND-BUFFER
-----	--------	-------------------

    - Both BUFEND and BUFFER are *relative terms*, representing addresses within the program
    - However the expression BUFEND-BUFFER represents an *absolute value: the difference between the two addresses*
  - When relative terms are paired with opposite signs
    - The dependency on the program starting address is canceled out
    - The result is an *absolute value*

## 2.3.3 Expressions (Cont.)

---

- Absolute expressions
  - An expression that contains only absolute terms
  - An expression that contain relative terms but *in pairs* and the terms in each such pair have *opposite* signs
- Relative expressions
  - All of the relative terms *except one* can be paired and the remaining *unpaired relative terms* must have a *positive sign*
- *No relative terms* can enter into a multiplication or division operation no matter in absolute or relative expression

## 2.3.3 Expressions (Cont.)

---

- Errors: (**represent neither absolute values nor locations within the program**)
  - BUFEND+BUFFER // not opposite terms
  - 100-BUFFER // not in pair
  - 3\*BUFFER // multiplication

## 2.3.3 Expressions (Cont.)

---

- Assemblers should determine the type of an expression
  - Keep track of the *types* of all symbols defined in the program in the symbol table.
  - Generate *Modification records* in the object program for relative values.

SYMTAB for Fig. 2.10

Symbol	Type	Value
RETADR	R	30
BUFFER	R	36
BUFEND	R	1036
MAXLEN	A	1000

## 2.3.4 Program Blocks

---

- Previously, main program, subroutines, and data area are treated as a unit and are assembled at the same time.
  - Although the source program logically contains subroutines, data area, etc, they were assembled into a **single block** of object code
  - To improve memory utilization, main program, subroutines, and data blocks may be allocated in separate areas.
- Two approaches to provide such a flexibility:
  - Program blocks
    - Segments of code that are **rearranged** within a single object program unit
  - Control sections
    - Segments of code that are translated into **independent object program units**

## 2.3.4 Program Blocks

---

### □ *Solution 1: Program blocks*

- Refer to segments of code that are rearranged within a single object program unit
- **Assembler directive:**    **USE**              **blockname**
  - Indicates which portions of the source program belong to which blocks.
- Codes or data with same block name will allocate together
- At the beginning, statements are assumed to be part of the unnamed (default) block
- If no USE statements are included, the entire program belongs to this single block.

## 2.3.4 Program Blocks (Cont.)

---

- E.g: Figure 2.11
  - Three blocks
    - First: unnamed, i.e., default block
      - Line 5 ~ Line 70 + Line 123 ~ Line 180 + Line 208 ~ Line 245
    - Second: CDATA
      - Line 92 ~ Line 100 + Line 183 ~ Line 185 + Line 252 ~ Line 255
    - Third: CBLKS
      - Line 103 ~ Line 107
  - Each program block may actually contain *several separate segments* of the source program.
  - The assembler will (logically) rearrange these segments to gather together the pieces of each block.

# Program with Multiple Program Blocks (Fig 2.11 & 2.12)

<b>Line</b>	<b>Loc/Block</b>		<b>Source statement</b>		<b>Object code</b>	
5	0000	0	COPY	START	0	
10	0000	0	FIRST	STL	RETADR	172063
15	0003	0	CLOOP	JSUB	RDREC	4B2021
20	0006	0		LDA	LENGTH	032060
25	0009	0		COMP	#0	290000
30	000C	0		JEQ	ENDFIL	332006
35	000F	0		JSUB	WRREC	4B203B
40	0012	0		J	CLOOP	3F2FEE
45	0015	0	ENDFIL	LDA	=C'EOF'	032055
50	0018	0		STA	BUFFER	0F2056
55	001B	0		LDA	#3	010003
60	001E	0		STA	LENGTH	0F2048
65	0021	0		JSUB	WRREC	4B2029
70	0024	0		J	@RETADR	3E203F
92	0000	1		USE	CDATA	
95	0000	1	RETADR	RESW	1	
100	0003	1	LENGTH	RESW	1	
103	0000	2		USE	CBLKS	
105	0000	2	BUFFER	RESB	4096	
106	1000	2	BUFEND	EQU	*	
107	1000		MAXLEN	EQU	BUFEND-BUFFER	
110						

# Program with Multiple Program Blocks (Fig 2.11 & 2.12) (Cont.)

110			:		
115			.	SUBROUTINE TO READ RECORD INTO BUFFER	
120			.		
123	0027	0		USE	
125	0027	0	RDREC	CLEAR X	B410
130	0029	0		CLEAR A	B400
132	002B	0		CLEAR S	B440
133	002D	0		+LDT #MAXLEN	75101000
135	0031	0	RLOOP	TD INPUT	E32038
140	0034	0		JEQ RLOOP	332FFA
145	0037	0		RD INPUT	DB2032
150	003A	0		COMPR A, S	A004
155	003C	0		JEQ EXIT	332008
160	003F	0		STCH BUFFER, X	57A02F
165	0042	0		TIXR T	B850
170	0044	0		JLT RLOOP	3B2FEA
175	0047	0	EXIT	STX LENGTH	13201F
180	004A	0		RSUB	4F0000
183	0006	1		USE CDATA	
185	0006	1	INPUT	BYTE X'F1'	F1
195					

# Program with Multiple Program Blocks (Fig 2.11 & 2.12)

195	:				
200	:				SUBROUTINE TO WRITE RECORD FROM BUFFER
205	:				
208	004D 0		USE		
210	004D 0	WRREC	CLEAR X		B410
212	004F 0		LDT LENGTH		772017
215	0052 0	WLOOP	TD =X'05'		E3201B
220	0055 0		JEQ WLOOP		332FFA
225	0058 0		LDCH BUFFER, X		53A016
230	005B 0		WD =X'05'		DF2012
235	005E 0		TIXR T		B850
240	0060 0		JLT WLOOP		3B2FEF
245	0063 0		RSUB		4F0000
252	0007 1		USE CDATA		
253			LTORG		
	0007 1	*	=C'EOF		454F46
	000A 1	*	=X'05'		05
255			END FIRST		

**Figure 2.12** Program from Fig. 2.11 with object code.

# Basic Data Structure for Assembler to Handle Program Blocks

---

- *Block name table*

- Block name, block number, address, length

Block name	Block number	Address	Length
(default)	0	0000	0066
CDATA	1	0066	000B
CBLKS	2	0071	1000

# How the Assembler Handles Program Blocks?

---

## □ Pass 1

- Maintaining separate location counter for each program block
- Each label is assigned an address that is relative to the start of the block that contains it
- When labels are entered into SYMTAB, the block name or number is stored along with the assigned relative addresses.
- At the end of Pass 1, the latest value of the location counter for each block indicates the length of that block
- The assembler can then assign to each block a starting address in the object program

# How the Assembler Handles Program Blocks? (Cont.)

---

- Pass 2
  - The address of each symbol can be computed by adding the assigned block starting address and the relative address of the symbol to the start of its block
    - The assembler needs the address for each symbol relative to the start of the object program, not the start of an individual program block

# Table for Program Blocks

---

- At the end of Pass 1 in Fig 2.11:

Block name	Block number	Address	Length
(default)	0	0000	0066
CDATA	1	0066	000B
CBLKS	2	0071	1000

# Example of Address Calculation

---

- Each source line is given a *relative address assigned* and a *block number*
  - **Loc/Block** Column in Fig. 2.11
- For an *absolute symbol* (whose value is not relative to the start of any program block), there is no block number
  - E.g. 107 1000 MAXLEN EQU BUFEND-BUFFER
- Example: calculation of address in Pass 2
  - 20 0006 0 LDA LENGTH 032060  
LENGTH = (block 1 starting address)+0003 = 0066+0003= 0069  
LOCCTR = (block 0 starting address)+0009 = 0009  
PC-relative: Displacement = 0069 - (LOCCTR) = 0069-0009=0060

## 2.3.4 Program Blocks (Cont.)

---

- Program blocks reduce addressing problem:
  - No needs for extended format instructions (lines 15, 35, 65)
    - The larger buffer is moved to the end of the object program
  - No needs for base relative addressing (line 13, 14)
    - The larger buffer is moved to the end of the object program
  - LTORG is used to make sure the literals are placed ahead of any large data areas (line 253)
    - Prevent literal definition from its usage too far

## 2.3.4 Program Blocks (Cont.)

---

- Object code
  - It is not necessary to physically rearrange the generated code in the object program to place the pieces of each program block together.
  - Loader will load the object code from each record at the *indicated addresses*.
- For example (Fig. 2.13)
  - The first two Text records are generated from line 5~70
  - When the USE statement is recognized
    - Assembler writes out the current Text record, even if there still room left in it
    - Begin a new Text record for the new program block

# Object Program Corresponding to Fig. 2.11 (Fig. 2.13)

---

```
HCOPY 000000001071
      ^          ^          ^
T0000001E1720634B20210320602900003320064B203B3F2FEE0320550F2056010003
      ^          ^          ^          ^          ^          ^          ^          ^
T00001E090F20484B20293E203F
      ^          ^          ^          ^
T0000271DB410B400B44075101000E32038332FFADB2032A00433200857A02FB850
      ^          ^          ^          ^          ^          ^          ^          ^
T000044093B2FEA13201F4F0000
      ^          ^          ^          ^
T00006C01F1
      ^          ^
T00004D19B410772017E3201B332FFA53A016DF2012B8503B2FEE4F0000
      ^          ^          ^          ^
T00006D04454F4605
      ^          ^
E000000
```

Figure 2.13 Object program corresponding to Fig. 2.11.

# Program blocks for the Assembly and Loading Processes (Fig. 2.14)




Figure 2.14 Program blocks from Fig. 2.11 traced through the assembly and loading processes.

## 2.3.5 Control Sections and Program Linking

---

- Control sections
  - A part of the program that maintains its *identity* after reassembly
    - Each control section can be loaded and relocated independently
    - Programmer can assemble, load, and manipulate each of these control sections separately
  - Often used for subroutines or other logical subdivisions of a program

## 2.3.5 Control Sections and Program Linking (Cont.)

---

- Instruction in one control section may need to refer to instructions or data located in another section
  - Called *external reference*
- However, assembler have no idea where any other control sections will be located at execution time
- The assembler has to generate information for such kind of references, called **external references**, that will allow the loader to perform the required linking.

# Program Blocks v.s. Control Sections

---

- Program blocks
  - Refer to segments of code that are rearranged with *a single object program unit*
  
- Control sections
  - Refer to segments that are translated into *independent object program units*

# Illustration of Control Sections and Program Linking (Fig 2.15 & 2.16)

First control section: COPY		Source statement		Object code	
Line	Loc				
5	0000	COPY	START	0	
6			EXTDEF	BUFFER, BUFEND, LENGTH	
7			EXTREF	RDREC, WRREC	
10	0000	FIRST	STL	RETADR	172027
15	0003	CLOOP	+JSUB	RDREC	4B100000
20	0007		LDA	LENGTH	032023
25	000A		COMP	#0	290000
30	000D		JEQ	ENDFIL	332007
35	0010		+JSUB	WRREC	4B100000
40	0014		J	CLOOP	3F2FEC
45	0017	ENDFIL	LDA	=C'EOF'	032016
50	001A		STA	BUFFER	0F2016
55	001D		LDA	#3	010003
60	0020		STA	LENGTH	0F200A
65	0023		+JSUB	WRREC	4B100000
70	0027		J	@RETADR	3E2000
95	002A	RETADR	RESW	1	
100	002D	LENGTH	RESW	1	
103			LTORG		
	0030	*	=C'EOF'		454F46
105	0033	BUFFER	RESB	4096	
106	1033	BUFEND	EQU	*	
107	1000	MAXLEN	EQU	BUFEND-BUFFER	

# Illustration of Control Sections and Program Linking (Fig 2.15 & 2.16) (Cont.)

Second control section: RDREC					
109	0000	RDREC	CSECT		
110		.			
115		.	SUBROUTINE TO READ RECORD INTO BUFFER		
120		.			
122			EXTREF	BUFFER, LENGTH, BUFEND	
125	0000		CLEAR	X	B410
130	0002		CLEAR	A	B400
132	0004	External reference	CLEAR	S	B440
133	0006		LDT	MAXLEN	77201F
135	0009	RLOOP	TD	INPUT	E3201B
140	000C		JEQ	RLOOP	332FFA
145	000F		RD	INPUT	DB2015
150	0012		COMPR	A, S	A004
155	0014		JEQ	EXIT	332009
160	0017		+STCH	BUFFER, X	57900000
165	001B		TIXR	T	B850
170	001D		JLT	RLOOP	3B2FE9
175	0020	EXIT	+STX	LENGTH	13100000
180	0024		RSUB		4F0000
185	0027	INPUT	BYTE	X'F1'	F1
190	0028	MAXLEN	WORD	BUFEND-BUFFER	000000

# Illustration of Control Sections and Program Linking (Fig 2.15 & 2.16) (Cont.)

193	0000	WRREC	CSECT	
195		.		
200		.	SUBROUTINE TO WRITE RECORD FROM BUFFER	
205		.		
207			EXTREF LENGTH,BUFFER	
210	0000		CLEAR X	B410
212	0002		+LDT LENGTH	77100000
215	0006	WLOOP	TD =X'05'	E32012
220	0009		JEQ WLOOP	332FFA
225	000C		+LDCH BUFFER,X	53900000
230	0010		WD =X'05'	DF2008
235	0013		TIXR T	B850
240	0015		JLT WLOOP	3B2FEE
245	0018		RSUB	4F0000
255			END FIRST	
	001B	*	=X'05'	05

Figure 2.16 Program from Fig. 2.15 with object code.

## 2.3.5 Control Sections and Program Linking (Cont.)

---

- Assembler directive: **secname CSECT**
  - Signal the start of a new control section
  - e.g. 109 RDREC CSECT
  - e.g. 193 WRREC CSECT
  - **START** also identifies the beginning of a section
- *External references*
  - References between control sections
  - The assembler generates information for each external reference that will allow the loader to perform the required linking.

# External Definition and References

---

- *External definition*
  - Assembler directives: **EXTDEF name [, name]**
  - EXTDEF names symbols, called *external symbols*, that are defined in this control section and may be used by other sections
  - Control section names do not need to be named in an EXTDEF statement (e.g., COPY, RDREC, and WRREC)
    - They are automatically considered to be external symbols
- *External reference*
  - Assembler directives: **EXTREF name [,name]**
  - EXTREF names symbols that are used in this control section and are defined elsewhere

## 2.3.5 Control Sections and Program Linking (Cont.)

---

- Any instruction whose operand involves an external reference
  - Insert an address of zero and pass information to the loader
    - Cause the proper address to be inserted *at load time*
  - *Relative addressing* is not possible
    - The address of external symbol have no predictable relationship to anything in this control section
    - An *extended format instruction* must be used to provide enough room for the actual address to be inserted

# Example of External Definition and References

---

## □ Example

- 15 0003 CLOOP +JSUB RDREC 4B100000
  
- 160 0017 +STCH BUFFER,X 57900000
  
- 190 0028 MAXLEN WORD BUFEND-BUFFER 000000

# How the Assembler Handles Control Sections?

---

- The assembler must include information in the object program that will cause the loader to insert proper values where they are required
- *Define record*: gives information about external symbols named by EXTDEF
  - Col. 1 D
  - Col. 2-7 Name of external symbol defined in this section
  - Col. 8-13 Relative address within this control section (hex)
  - Col.14-73 Repeat information in Col. 2-13 for other external symbols
- *Refer record*: lists symbols used as external references, i.e., symbols named by EXTREF
  - Col. 1 R
  - Col. 2-7 Name of external symbol referred to in this section
  - Col. 8-73 Name of other external reference symbols

# How the Assembler Handles Control Sections? (Cont.)

---

- *Modification record* (revised)
  - Col. 1 M
  - Col. 2-7 Starting address of the field to be modified (hex)
  - Col. 8-9 Length of the field to be modified, in half-bytes (hex)
  - Col. 10 Modification flag (+ or - )
  - Col.11-16 External symbol whose value is to be added to or subtracted from the indicated field.
- Control section name is automatically an external symbol, it is available for use in Modification records.
- Example (Figure 2.17)
  - M000004<sub>16</sub>05<sub>16</sub>+RDREC
  - M000011<sub>16</sub>05<sub>16</sub>+WRREC
  - M000024<sub>16</sub>05<sub>16</sub>+WRREC
  - M000028<sub>16</sub>06<sub>16</sub>+BUFEND //Line 190 BUFEND-BUFFER
  - M000028<sub>16</sub>06<sub>16</sub>-BUFFER

# Object Program Corresponding to Fig. 2.15 (Fig. 2.17)

```
HCOPY 000000001033
      ^   ^   ^
DBUFFER000033BUFEND001033LENGTH00002D
      ^   ^   ^   ^   ^   ^
      RRDREC WRREC
      ^   ^   ^
T0000001D1720274B1000000320232900003320074B1000003F2FEC0320160F2016
      ^   ^   ^   ^   ^   ^   ^   ^   ^
T00001D0D0100030F200A4B1000003E2000
      ^   ^   ^   ^
T00003003454F46
      ^   ^   ^
M00000405+RDREC
      ^   ^   ^
M00001105+WRREC
      ^   ^   ^
M00002405+WRREC
      ^   ^   ^
E000000
      ^
```

# Object Program Corresponding to Fig. 2.15 (Fig. 2.17) (Cont.)

HRDREC 00000000002B

RBUFFERLENGTHBUFEND

T0000001DB410B400B44077201FE3201B332FFADB2015A00433200957900000B850

T00001D0E3B2FE9131000004F0000F100000

M00001805+BUFFER

M00002105+LENGTH

M00002806+BUFEND

M00002806-BUFFER

E

# Object Program Corresponding to Fig. 2.15 (Fig. 2.17) (Cont.)

The diagram displays a memory dump with several fields highlighted by colored boxes and arrows:

- HWRREC 00000000001C**: A green dashed box highlights the first 16 bytes. An arrow points from the label to the byte '0'.
- RLENGTHBUFFER**: A blue dotted box highlights the next 4 bytes. An arrow points from the label to the byte 'R'.
- T0000001CB41077100000E32012332FFA53900000DF2008B8503B2FEE4F000005**: The main data area is shown with various bytes labeled with their memory addresses. An arrow points from the byte 'T' to the address 'M00000305+LENGTH'.
- M00000305+LENGTH**: A red dotted box highlights the offset 'M00000305'. An arrow points from the label to the byte 'M'.
- M00000D05+BUFFER**: A red dotted box highlights the offset 'M00000D05'. An arrow points from the label to the byte 'M'.
- E**: An arrow points from the letter 'E' to the byte 'E' at address 'M00000D05+BUFFER'.

**Figure 2.17** Object program corresponding to Fig. 2.15.



## 2.4 Assembler Design Options

---

- One-pass assemblers
- Multi-pass assemblers

## 2.4.1 One-Pass Assemblers

---

- Goal: avoid a second pass over the source program
- Main problem
  - Forward references to *data items* or *labels on instructions*
- Solution
  - Data items: require all such areas be defined before they are referenced
  - Label on instructions: cannot be eliminated
    - E.g. the logic of the program often requires a forward jump
    - It is too inconvenient if forward jumps are not permitted

# Two Types of One-Pass Assemblers:

---

- Load-and-go assembler
  - Produces object code directly in memory for immediate execution
  
- The other assembler
  - Produces usual kind of object code for later execution

# Load-and-Go Assembler

---

- No object program is written out, no loader is needed
- Useful for program development and testing
  - Avoids the overhead of writing the object program out and reading it back in
- Both one-pass and two-pass assemblers can be designed as load-and-go
  - However, one-pass also avoids the overhead of an additional pass over the source program
- For a load-and-go assembler, the actual address must be known at assembly time.

# Forward Reference Handling in One-pass Assembler

---

- When the assembler encounter an instruction operand that has not yet been defined:
  1. The assembler omits the translation of operand address
  2. Insert the symbol into SYMTAB, if not yet exist, and mark this symbol ***undefined***
  3. The address that refers to the undefined symbol is added to *a list of forward references* associated with the symbol table entry
  4. When the definition for a symbol is encountered
    1. The forward reference list for that symbol is scanned
    2. The proper address for the symbol is inserted into any instructions previous generated.

# Handling Forward Reference in One-pass Assembler (Cont.)

---

- At the end of the program
  - Any SYMTAB entries that are still marked with \* indicate *undefined symbols*
    - Be flagged by the assembler as errors
  - Search SYMTAB for the symbol named in the END statement and jump to this location to begin execution of the assembled program.

# Sample Program for a One-Pass Assembler (Fig. 2.18)

<b>Line</b>	<b>Loc</b>	<b>Source statement</b>			<b>Object code</b>
0	1000	COPY	START	1000	
1	1000	EOF	BYTE	C'EOF'	454F46
2	1003	THREE	WORD	3	000003
3	1006	ZERO	WORD	0	000000
4	1009	RETADR	RESW	1	
5	100C	LENGTH	RESW	1	
6	100F	BUFFER	RESB	4096	
9		.			
10	200F	FIRST	STL	RETADR	141009
15	2012	CLOOP	JSUB	RDREC	48203D
20	2015		LDA	LENGTH	00100C
25	2018		COMP	ZERO	281006
30	201B		JEQ	ENDFIL	302024
35	201E		JSUB	WRREC	482062
40	2021		J	CLOOP	302012
45	2024	ENDFIL	LDA	EOF	001000
50	2027		STA	BUFFER	0C100F
55	202A		LDA	THREE	001003
60	202D		STA	LENGTH	0C100C
65	2030		JSUB	WRREC	482062
70	2033		LDL	RETADR	081009
75	2036		RSUB		4C0000

# Sample Program for a One-Pass Assembler (Fig. 2.18) (Cont.)

---

```
110      .
115      :          SUBROUTINE TO READ RECORD INTO BUFFE
120      .
121      2039    INPUT    BYTE     X'F1'      F1
122      203A    MAXLEN   WORD     4096      001000
124      .
125      203D    RDREC    LDX      ZERO      041006
130      2040    .          LDA      ZERO      001006
135      2043    RLOOP    TD       INPUT      E02039
140      2046    .          JEQ      RLOOP      302043
145      2049    .          RD       INPUT      D82039
150      204C    .          COMP     ZERO      281006
155      204F    .          JEQ      EXIT      30205B
160      2052    .          STCH     BUFFER,X  54900F
165      2055    .          TIX      MAXLEN   2C203A
170      2058    .          JLT      RLOOP      382043
175      205B    EXIT     STX      LENGTH   10100C
180      205E    .          RSUB    .          4C0000
195      .
```

# Sample Program for a One-Pass Assembler (Fig. 2.18) (Cont.)

195	:				
200	:	SUBROUTINE TO WRITE RECORD FROM BUFFER			
205	:				
206	2061	OUTPUT	BYTE	X'05'	05
207	.				
210	2062	WRREC	LDX	ZERO	041006
215	2065	WLOOP	TD	OUTPUT	E02061
220	2068		JEQ	WLOOP	302065
225	206B		LDCH	BUFFER, X	50900F
230	206E		WD	OUTPUT	DC2061
235	2071		TIX	LENGTH	2C100C
240	2074		JLT	WLOOP	382065
245	2077		RSUB		4C0000
255			END	FIRST	

Figure 2.18 Sample program for a one-pass assembler.


# Example

---

- Fig. 2.19 (a)
  - Show the object code in memory and symbol table entries after scanning line 40
  - Line 15: forward reference (RDREC)
    - Object code is marked ----
    - Value in symbol table is marked as \* (undefined)
    - Insert *the address of operand* (2013) in a list associated with RDREC
  - Line 30 and Line 35: follow the same procedure

# Object Code in Memory and SYMTAB

After scanning line 40 (Fig.2.19(a))




# Example (Cont.)

---

- Fig. 2.19 (b)
  - Show the object code in memory and symbol table entries after scanning line 160
  - Line 45: ENDFIL was defined
    - Assembler place its value in the SYMTAB entry
    - Insert this value into the address (at 201C) as directed by the forward reference list
  - Line 125: RDREC was defined
    - Follow the same procedure
  - Line 65
    - A new forward reference (WRREC and EXIT)

# Object Code in Memory and SYMTAB

After scanning line 160



# One-Pass Assembler Producing Object Code

---

- Forward reference are entered into the symbol table's list as before
  - If the operand contains an undefined symbol, use 0 as the address and write the Text record to the object program.
- However, when definition of a symbol is encountered,
  - Assembler generate *another Text record* with the *correct operand address*.
- When the program is loaded, this address will be inserted into the instruction by *loader*.
- The object program records must be kept in their original order when they are presented to the loader

# Example

---

- In Fig. 2.20
  - Second Text record contains the object code generated from lines 10 through 40
    - The operand addressed for the instruction on line 15, 30, 35 have been generated as 0000
  - When the definition of ENDFIL is encountered
    - Generate the third Text record
      - Specify the value 2024 ( the address of ENDFIL) is to be loaded at location 201C ( the operand field of JEQ in line 30)
      - Thus, the value 2024 will replace the 0000 previously loaded

# Object Program from one-pass assembler for Fig 2.18 (Fig 2.20)

```
HCOPY 00100000107A          201C
      ^   ^   ^
T00100009454F46000003000000
      ^   ^   ^
T00200F1514100948000000100C2810063000004800003C2012
      ^   ^   ^
T00201C022024
      ^   ^
T002024190010000C100F0010030C100C480000810094C0000F1001000
      ^   ^   ^
T00201302203D
      ^   ^
T00203D1E041006001006E02039302043D8203928100630000054900F2C203A382043
      ^   ^   ^
T00205002205B
      ^   ^
T00205B0710100C4C000005
      ^   ^
T00201F022062
      ^   ^
T002031022062
      ^   ^
T00206218041006E0206130206550900FDC20612C100C3820654C0000
      ^   ^
E00200F
```

**Figure 2.20** Object program from one-pass assembler for program in Fig. 2.18.



## 2.4.2 Multi-Pass Assemblers

---

- Motivation: for a 2-pass assembler, any symbol used on the *right-hand side* should be defined previously.
  - No forward references since symbols' value can't be defined during the first pass
  - Reason: symbol definition must be completed in pass 1.
    - E.g. 

APLHA	EQU	BETA
BETA	EQU	DELTA
DELTA	RESW 1	

 Not allowed !

# Multi-Pass Assemblers (Cont.)

---

- Motivation for using a multi-pass assembler
  - DELTA can be defined in pass 1
  - BETA can be defined in pass 2
  - ALPHA can be defined in pass 3
- Multi-pass assemblers
  - Eliminate the restriction on EQU and ORG
  - Make as many passes as are needed to process the definitions of symbols.

# Implementation

---

- A symbol table is used
  - Store symbol definitions that *involve forward references*
  - Indicate which symbols are dependant on the values of others
  - Keep a linking list to keep track of whose symbols' value depend on an this entry

# Example of Multi-pass Assembler Operation (fig 2.21a)


---

```
HALFSZ EQU MAXLEN/2
MAXLEN EQU BUFEND-BUFFER
PREVBT EQU BUFFER-1
.
.
.
BUFFER RESB 4096
BUFEND EQU *
```

# Example of Multi-Pass Assembler Operation (Fig 2.21b)

&1: one symbol in the defining expression is undefined

```
HALFSZ EQU MAXLEN/2
MAXLEN EQU BUFEND-BUFFER
PREVBT EQU BUFFER-1
.
.
.
BUFFER RESB 4096
BUFEND EQU *
```




(b)

Figure 2.21 Example of multi-pass assembler operation.

# Example of Multi-Pass Assembler Operation (Fig 2.21c)

```
HALFSZ EQU MAXLEN/2
MAXLEN EQU BUFEND-BUFFER
PREVBT EQU BUFFER-1
.
.
.
BUFFER RESB 4096
BUFEND EQU *
```



# Example of Multi-pass Assembler Operation (fig 2.21d)

```
HALFSZ EQU MAXLEN/2
MAXLEN EQU BUFEND-BUFFER
PREVBT EQU BUFFER-1
.
.
.
BUFFER RESB 4096
BUFEND EQU *
```





Figure 2.21 (cont'd)

# Example of Multi-pass Assembler Operation (fig 2.21e)

```
HALFSZ EQU MAXLEN/2
MAXLEN EQU BUFEND-BUFFER
PREVBT EQU BUFFER-1
.
.
.
BUFFER RESB 4096
BUFEND EQU *
```



(e)

# Example of Multi-pass Assembler Operation (Fig 2.21f)

$$BUFEND=*(PC)=1034_{16}+4096_{10}=1034_{16}+1000_{16}=2034_{16}$$

```
HALFSZ EQU MAXLEN/2
MAXLEN EQU BUFEND-BUFFER
PREVBT EQU BUFFER-1
.
.
.
BUFFER RESB 4096
BUFEND EQU *
```

BUFEND	2034	0
HALFSZ	800	0
PREVBT	1033	0
MAXLEN	1000	0
BUFFER	1034	0

(f)

Figure 2.21 (con'd)