Package 'EDOIF'

November 14, 2019

Title Empirical Distribution Ordering Inference Framework (EDOIF)

Version 0.1.0

Maintainer Chainarong Amornbunchornvej < grandca@gmail.com>

Description A non-parametric framework based on Estimation Statistics principle. Its main purpose is to infer orders of empirical distributions from different categories base on a probability of finding a value in one distribution that greater than the expectation of another distribution. Given a set of ordered-pair of real-category values the framework is capable of 1) inferring orders of domination of categories and representing orders in the form of a graph; 2) estimating magnitude of difference between a pair of categories in forms of confidence intervals; and 3) visualizing domination orders and magnitudes of difference of categories.

License BSD_3_clause + file LICENSE

URL https://github.com/DarkEyes/EDOIF

BugReports https://github.com/DarkEyes/EDOIF/issues

Language en-US

Encoding UTF-8

LazyData true

Depends R (>= 3.5.0),

boot

Imports distr,

igraph,

ellipsis,

simpleboot,

ggplot2 (>= 3.0)

Suggests knitr, rmarkdown

VignetteBuilder knitr

RoxygenNote 6.1.1

R topics documented:

ootDiffmeanFunc		
neckSim3Res		
DOIF		
etADJNetDen	4	
etConfInv		

2 bootDiffmeanFunc

boot	DiffmeanFunc	bootD	iffme	ean	Fun	c fu	ınct	ioi	n												
Index																					14
	SimNonNormalDist			• •		• •	• •	•	•	 ٠	 •	•	 •	•	 •	•	•	 •	•	•	13
	SimManNarmalDist																				
	print.EDOIF																				
	plotMeanDiffCIs .																				
	plotMeanCIs																				
	plotGraph																				
	plot.EDOIF																				
	meanBoot																				
	getWilcoxDominantl																				
	getttestDominantRA																				
	getOrder																				
	getMegDiffConfInv																				
	getiGraphOBJ																				
	getiGraphNetDen .																				6
	getDominantRADJ																				5

Description

bootDiffmeanFunc is a support function for bootstrapping method. Its main task is to infer meandifference confidence intervals of distributions for all categories except the first category in idx (idx[2],idx[3],...) minus a target category (idx[1]).

Usage

bootDiffmeanFunc(Group, Values, idx, reps, ci, methodType)

Arguments

Group	is a vector of categories of each real number in Values
Values	is a vector of real-number values
idx	is an order list of categories; $idx[1]$ is a target category while others $(idx[2],idx[3],)$ are compared against $idx[1]$ in order to compute mean-difference confidence intervals.
reps	is a number of time of sampling with replacement in a bootstrapping method.
ci	is a level of confidence interval inferred.
methodType	is a type of method for inferring confidence intervals. It is a parameter of two.boot function of simpleboot package.

Value

This function returns a list of mean-difference confidence intervals of categories idx[2],idx[3],... minus category idx[1].

result a list of objects that contains mean-difference confidence intervals of pairs of distributions. It contains mean-difference confidence intervals of categories idx[2],idx[3],... minus category idx[1].

checkSim3Res 3

|--|

Description

checkSim3Res is a support function for checking whether an adjacency matrix of inferred a dominant-distribution network adjMat is corrected w.r.t. generator SimNonNormalDist().

Usage

```
checkSim3Res(adjMat, flag)
```

Arguments

adjMat is an adjacency matrix of inferred a dominant-distribution network.

flag is a flag of matrix. It should be set only to shift the low of matrix for comparison.

Value

This function returns precision, recall, and F1-score of inferred adjacency matrix.

EDOIF	Empirical Distribution Ordering Inference Framework (EDOIF)
ED 011	Empirical Distribution of acting Ingerence Transcriotic (ED off)

Description

EDOIF is a non-parametric framework based on Estimation Statistics principle. Its main purpose is to infer orders of empirical distributions from different categories base on a probability of finding a value in one distribution that greater than the expectation of another distribution.

Given a set of ordered-pair of real-category values the framework is capable of 1) inferring orders of domination of categories and representing orders in the form of a graph; 2) estimating magnitude of difference between a pair of categories in forms of confidence intervals; and 3) visualizing domination orders and magnitudes of difference of categories.

Usage

EDOIF(Values, Group, bootT, alpha, methodType)

Arguments

Values	is a vector of real-number values
Group	is a vector of categories of each real number in Values
bootT	is a number of times of sample with replacement for bootstrapping. The default is 1000. It must be above zero
alpha	is a significance level using in both confidence intervals and ordering inference it has the range $[0,1]$. The default is 0.05 .
methodType	is an option for bootstrapping methods:either "perc" or "bca". The "perc" is the default option.

4 getADJNetDen

Value

This class constructor returns an object of EDOIF class.

obj an object of EDOIF class that contains the results of ordering inference that can be print in text mode (print(obj)) or graphic mode (plot(obj)).

The obj consists of the following variables

Values, Group The main inputs of the framework. They are the double and character vectors respectively.

bootT, alpha, methodType

The number of bootstrapping, significance level, and bootstrapping method pa-

rameters.

sortedGroupList A list of names of categories ascendingly ordered by their means.

sortedmeanList A list of means of categories that are ascendingly ordered.

MegDiffList[[i]] Mean difference confidence intervals and related information of all categories

that have higher means than sortedGroupList[i] category.

confInvsList[i,] A mean confidence interval of sortedGroupList[i] category. confInvsList[i,1] is

a lower bound and confInvsList[i,2] is an upper bound.

adjMat[i,j] An element of adjacency matrix: one if sortedGroupList[j] category dominates

sortedGroupList[i] using Mann-Whitney test, otherwise zero.

pValMat[i,j] A p-value of Mann-Whitney test for adjMat[i,j].

adjDiffMat[i,j] A lower bound of confidence interval of mean difference for sortedGroupList[j]

minus sortedGroupList[i] using methodType bootstrap.

adjBootMat[i,j] One if adjDiffMat[i,j] is positive, otherwise, zero.

net Den A network density of dominant-distribution network derived from adjMat.

Author(s)

Chainarong Amornbunchornvej, <chai@ieee.org>

+ A D IN -+ D	A D INI AD
$\operatorname{get} \operatorname{ADJNet} \operatorname{Den}$	getADJNetDen function

Description

getADJNetDen is a support function for calculating a network density of a dominant-distribution network.

Usage

```
getADJNetDen(adjMat)
```

Arguments

adjMat is an adjacency matrix of a dominant-distribution network.

Value

This function returns a value of network density of of a dominant-distribution network for a given adjMat.

getConfInv 5

|--|

Description

getConfInv is a support function for bootstrapping method. Its main purpose is to compute a mean confidence intervals of all distributions.

Usage

```
getConfInv(Values, Group, GroupList, bootT, alpha, methodType)
```

Arguments

Values	is a vector of real-number values
Group	is a vector of categories of each real number in Values
$\operatorname{GroupList}$	is a list of names of categories ascendingly ordered by their means.
bootT	is a number of times of sample with replacement for bootstrapping. The default is 1000. It must be above zero
alpha	is a significance level using in both confidence intervals and ordering inference

it has the range [0,1]. The default is 0.05.

is an option for bootstrapping methods:either "perc" or "bca". The "perc" is the

default option.

Value

methodType

This function returns a list of mean confidence intervals.

confInvsList[i,] The mean confidence interval of sortedGroupList[i] category. confInvsList[i,1] is a lower bound and confInvsList[i,2] is an upper bound.

getDominantRADJ getDominantRADJ function

Description

getDominantRADJ is a support function for inferring a dominant-distribution network using mean-difference confidence intervals.

Usage

```
getDominantRADJ(MegDiffList, methodType)
```

Arguments

MegDiffList is a list of objects that contains mean-difference confidence intervals inferred by

getMegDiffConfInv function.

methodType is an option for bootstrapping methods:either "perc" or "bca".

6 getiGraphOBJ

Value

This function returns an adjacency matrix of a dominant-distribution network adjMat and the corresponding lower-bound of mean difference CIs adjDiffMat.

adjDiffMat[i,j] A lower bound of confidence interval of mean difference for j minus i using

methodType bootstrap.

adjMat[i,j] An element of adjacency matrix: One if adjDiffMat[i,j] is positive, otherwise,

zero.

getiGraphNetDen

getiGraphNetDen function

Description

getiGraphNetDen is a support function for calculating a network density of a dominant-distribution network.

Usage

```
getiGraphNetDen(g)
```

Arguments

g

is an object of iGraph class of a dominant-distribution network.

Value

This function returns a value of network density of of a dominant-distribution network for a given object g.

getiGraphOBJ

getiGraphOBJ function

Description

getiGraphOBJ is a support function for converting a dominant-distribution network adjacency matrix to an iGraph object.

Usage

```
getiGraphOBJ(adjMat, sortedGroupList)
```

Arguments

adjMat

is an adjacency matrix of a dominant-distribution network.

sortedGroupList is a list of names of categories ascendingly ordered by their means.

Value

This function returns an iGraph object of a dominant-distribution network for a given adjMat.

getMegDiffConfInv 7

|--|--|--|

Description

getMegDiffConfInv is a support function for bootstrapping method. Its main purpose is to compute a mean-difference confidence intervals between all pair of distributions.

Usage

getMegDiffConfInv(Values, Group, GroupList, bootT, alpha, methodType)

Arguments

Values is a vector of real-number values

Group is a vector of categories of each real number in Values

GroupList is a list of names of categories ascendingly ordered by their means.

bootT is a number of times of sample with replacement for bootstrapping. The default

is 1000. It must be above zero

alpha is a significance level using in both confidence intervals and ordering inference

it has the range [0,1]. The default is 0.05.

methodType is an option for bootstrapping methods:either "perc" or "bca". The "perc" is the

default option.

Value

This function returns a list of mean-difference confidence intervals.

MegDiffList a list of objects that contains mean-difference confidence intervals of all possible pairs of distributions. It contains MegDiffList[[1]],...,MegDiffList[[length(GroupList)]].

The MegDiffList consists of the following variables

MegDiffList[[i]] Mean-difference confidence intervals and related information of all categories

that have higher means than sortedGroupList[i] category.

$\operatorname{get} \operatorname{Order}$	getOrder function	
---	-------------------	--

Description

getOrder is a support function for inferring a linear order of categories ascendingly sorted by their means.

Usage

```
getOrder(Values, Group)
```

Arguments

Values is a vector of real-number values

Group is a vector of categories of each real number in Values

Value

This function returns an order list of categories.

sortedGroupList The list of names of categories ascendingly ordered by their means.

sortedmeanList The list of means of categories that are ascendingly ordered.

getttestDominantRADJ getttestDominantRADJ function

Description

getttestDominantRADJ is a support function for inferring a dominant-distribution network using Student's t-test.

Usage

getttestDominantRADJ(Values, Group, GroupList, alpha)

Arguments

Values is a vector of real-number values

Group is a vector of categories of each real number in Values

GroupList is a list of names of categories ascendingly ordered by their means.

alpha is a significance level using in both confidence intervals and ordering inference

it has the range [0,1].

Value

This function returns an adjacency matrix of a dominant-distribution network adjMat and the corresponding p-values of all category pairs.

adjMat[i,j] An element of adjacency matrix: one if GroupList[j] category dominates Grou-

pList[i] using Student's t-test, otherwise zero.

pValMat[i,j] A p-value of Student's t-test for adjMat[i,j].

get Wilcox Dominant RADJ

getWilcoxDominantRADJ function

Description

getWilcoxDominantRADJ is a support function for inferring a dominant-distribution network using Mann-Whitney (Wilcoxon) Test.

Usage

getWilcoxDominantRADJ(Values, Group, GroupList, alpha)

Arguments

Values is a vector of real-number values

Group is a vector of categories of each real number in Values

GroupList is a list of names of categories ascendingly ordered by their means.

alpha is a significance level using in both confidence intervals and ordering inference

it has the range [0,1].

Value

This function returns an adjacency matrix of a dominant-distribution network adjMat. and the corresponding p-values of all category pairs.

adjMat[i,j] An element of adjacency matrix: one if GroupList[j] category dominates Grou-

pList[i] using Mann-Whitney test, otherwise zero.

pValMat[i,j] A p-value of Mann-Whitney test for adjMat[i,j].

meanBoot meanBoot function

Description

meanBoot is a support function for bootstrapping method. Its main purpose is to compute a mean of a given samples from data selected by indices.

Usage

meanBoot(data, indices)

Arguments

data is a vector of real-number values

indices is a vector of TRUE/FALSE indices. It allows boot to select samples.

Value

This function returns a mean of values in data that have values TRUE within indices.

10 plotGraph

|--|

Description

plot.EDOIF is a support function for printing all plots of EDOIF framework: dominant-distribution network plot, mean CI plot, and mean-difference CI plot.

Usage

```
## S3 method for class 'EDOIF' plot(x, ..., NList, options, fontSize)
```

Arguments

x is an object of EDOIF class that contains the results of ordering inference.

... Signature for S3 generic function.

NList is a list of based categories users want to have in mean-difference CI plot.

options is an option of reporting EDOIF plot(s): 0 for reporting all plots, 1 for mean-

difference CI plot, 2 for mean CI plot, and 3 for dominant-distribution network

plot.

fontSize is a font size of text for all plots.

plotGraph plotGraph function

Description

plotGraph is a support function for plotting a dominant-distribution network from an adjacency matrix.

Usage

```
plotGraph(obj, rankFlag)
```

Arguments

obj is an object of EDOIF class that contains the results of ordering inference.

rankFlag is an option for including ranks of categories with in the plot: default is TRUE

for including ranks.

Value

This function returns an object of iGraph for a dominant-distribution network and its plot variable.

graphVar An object of iGraph for a dominant-distribution network

plotMeanCIs 11

${\rm plotMeanCIs}$	plotMeanCIs function	
---------------------	----------------------	--

Description

plotMeanCIs is a support function for plotting mean confidence intervals.

Usage

```
plotMeanCIs(obj, fontSize, rankFlag)
```

Arguments

obj is an object of EDOIF class that contains the results of ordering inference.

fontSize is a font size of text for all plots.

rankFlag is an option for including ranks of categories with in the plot: default is TRUE

for including ranks.

Value

This function returns an object of ggplot class.

pMeanCI An object of ggplot class containing the plot of mean confidence intervals

plotMeanDiffCIs plotMeanDiffCIs function

Description

plotMeanDiffCIs is a support function for plotting difference-mean confidence intervals.

Usage

```
plotMeanDiffCIs(obj, NList, fontSize, rankFlag)
```

Arguments

obj is an object of EDOIF class that contains the results of ordering inference.

NList is a list of based categories users want to have in mean-difference CI plot.

fontSize is a font size of text for all plots.

rankFlag is an option for including ranks of categories with in the plot: default is TRUE

for including ranks.

Value

This function returns an object of ggplot class.

pDiffCI An object of ggplot class containing the plot of difference-mean confidence in-

tervals

12 SimMixDist

print.EDOIF print.EDOIF function

Description

print.EDOIF is a support function for printing results of ordering inference in text.

Usage

```
## S3 method for class 'EDOIF' print(x, ...)
```

Arguments

x is an object of EDOIF class that contains the results of ordering inference.

... Signature for S3 generic function.

SimMixDist function	$\operatorname{SimMixDist}$
---------------------	-----------------------------

Description

SimMixDist is a support function for generating samples from mixture distribution. The main purpose of this function is to generate samples from non-normal distribution.

Usage

```
SimMixDist(nInv, mean, std, p1, p2)
```

Arguments

nInv	is a number of samples the function will generate.
mean	is a mean of a normal distribution part of mixture distribution.
std	is a standard deviation of a normal distribution part of mixture distribution.
p1	is a ratio of a normal distribution within a mixture distribution.
p2	is a ratio of a Cauchy distribution within a mixture distribution.

Value

This function returns a vector of samples V generated by a mixture distribution.

SimNonNormalDist 13

st function

Description

SimNonNormalDist is a support function for generating samples from mixture distribution. There are five categories. Each categories has nInv samples. Categories C1,C2,C3, and C4 are dominated by C5 but none of them dominate each other.

Usage

SimNonNormalDist(nInv, noisePer)

Arguments

nInv is a number of samples the function will generate for each category.

noisePer is ratio of uniform distribution within a mixture distribution. It is considered

as a uniform noise that make an approach to hardly distinguish whether one

distribution dominates another.

Details

The main purpose of this function is to generate samples that contains domination relation among categories.

Value

This function returns a vector of samples Values and their category Group generated by a mixture distribution.

Values A vector of samples generated by a mixture distribution.

Group A list of categories associated with Values. V1,...,V5 Vectors of samples separated by categories.

Index

```
{\bf bootDiffmeanFunc, 2}
checkSim3Res, 3
EDOIF, 3
getADJNetDen, 4
getConfInv, 5
getDominantRADJ, 5
{\it getiGraphNetDen}, {\it 6}
getiGraphOBJ, 6
getMegDiffConfInv, 7
getOrder, 7
{\it getttestDominantRADJ}, {\it 8}
{\tt getWilcoxDominantRADJ, 9}
{\rm meanBoot}, {\color{red} 9}
{\rm plot.EDOIF,}\, {\color{red}10}
plotGraph,\, {\color{red}10}
plotMeanCIs, 11
plotMeanDiffCIs, 11
print.EDOIF, 12
SimMixDist, 12
SimNonNormalDist, 13
```