0 Contents

```
      1 Move Semantics
      1

      1.1 Copy
      1

      1.2 Move
      1

      1.3 Copy Assignment
      1

      1.4 Move Assignment
      1

      1.5 Rvalue and Lvalue
      1

      1.5.1 Convert Ivalue to rvalue
      1

      1.6 Other value types
      2

      1.6.1 Temporary Materialization
      2

      1.7 I and rvalue references
      2

      1.8 Binds
      3

      1.9 Destructor
      3

      1.10 Default Constructors and user defined Constructors
      3
```

1 Move Semantics

1.1 Copy

By default cpp will always create copies, this is good for memory safety etc, as you will not be returning null values, but it can be a runtime hit! (There are some special types that can't be copied like mutexes etc)

```
// Copy contructor
class something {
  something(const something &other) {
    // copy values from other
  }
}
```

1.2 Move

Move constructor will NOT copy values, instead, it will move these values into the new object, this is better for performance, but it requires more management from the programmer!

Make sure to free the memory at the old object, otherwise you might be dealing with nullpointers!

In short, the move constructor makes a lot of sense when you have *Heap data*, aka if you have something like an array or a vector, then you will want to make sure to always use the move constructor if you can do so.

The default move constructor is as follows:

```
struct S {
   S(S && s) : member{std::move(s.member)}
   {...}
   M member;
};
```

1.3 Copy Assignment

Default copy assignment constructor:

```
struct S {
  auto operator=(S const& s) -> S& {
    member = s.member;
    return *this;
  }
  M member;
};
```

1.4 Move Assignment

Default move assignment constructor:

```
struct S {
  auto operator=(S&& s) -> S& {
    member = std::move(s.member);
    return *this;
  }
  M member;
};
```

1.5 Rvalue and Lvalue

Ivalue T&: variable with some location in ram, either on the stack or on the heap.

rvalue T&&: temporary value that has no variable and no location in memory, it only exists in code.

```
int a = 5;
// 5 is an r value, it has no memory location
// a is an lvalue -> some address is set to 5

int b = 10;

int c = a + b;
// a + b is an rvalue -> value is 15, but no memory location for this calculation
// c is an lvalue -> some address is set to 5
```

1.5.1 Convert Ivalue to rvalue


By default you can't just use an Ivalue as an rvalue, however, you can use std::move to explicitly convert an Ivalue to an rvalue. Note that in this case, you can't use the old variable anymore, as the data has been moved! -> see rust

```
auto consume(Food&& food) -> void;
auto fryBurger() -> Food;
auto fastFood() -> void {
  Food fries{"salty and greasy"};
  consume(fryBurger()); //call with rvalue
```

```
consume(fries); //cannot pass lvalue to rvalue reference
consume(std::move(fries)); //explicit conversion lvalue to xvalue
Food&& burger = fryBurger(); //life-extension of temporary
```

1.6 Other value types

has identity?	can be moved from?	Value Category	
Yes	No	Ivalue	
Yes	Yes	xvalue (expiring value)	
No	No (Since C++17)	prvalue (pure rvalue)	
No	Yes (Since C++17)	- (doesn't exist anymore)	



Ivalue

- address can be taken
- Can be on the left-hand side of an assignment if modifiable
- Can be used to initialize Ivalue references
- Examples: variables, function calls that return reference, increment and decrement operators, array index access if array is Ivalue
- all string literals
- prvalue
 - address can't be taken -> doesn't exist
 - cannot be on the left hand side of assignment
 - temporary "materialization" to xvalue
 - Examples: literals, false, nullptr, function call with non reference return type, postincrement and postdecrement!!
- xvalue
 - address cannot be taken
 - Cannot be used as left-hand operator of built-in assignment
 - Conversion from prvalue through temporary materialization
 - Examples: function calls with rvalue reference return type -> std::move, access of non-references members of an rvalue object, arra index access when array is rvalue

1.6.1 Temporary Materialization

Getting from something imaginary to something you can point to....

When this happens:

- binding a reference to a prvalue
- when accessing a member of prvalue
- when accessing an element of a prvalue array
- when converting a prvalue array to a pointer
- when initializing an std::initializer_list<T> from a braced-init-list
- Type needs to be complete and needs to have a destructor


```
struct Ghost {
   auto haunt() const -> void {
      std::cout << "boocoo!\n";
   }
   //~Ghost() = delete;
};
auto evoke() -> Ghost {
   return Ghost{};
}
auto main() -> int {
   Ghost&& sam = evoke(); // bind reference to a prvalue
   Ghost{}.haunt(); // access member of prvalue
}
```

1.7 I and rvalue references

- Ivalue reference made only of Ivalues!!
 - type: T&
 - alias for a variable
 - can be used as function member type, local member/variable, return type
 - be aware of dangling references when returning!
- rvalue reference made of rvalues, prvalues or xvalues!
- Type: T&&
- when assigned to a name (for example inside of a function), then it is actually an Ivalue!!
- Argument is either a literal or a temporary object

```
std::string createGlass() -> std::string;
void fancyNameForFunction() {
  std::string mug{"cup of coffee"};
  std::string&& glass_ref = createGlass(); //life-extension of temporary
  std::string&& mug_ref = std::move(mug); //explicit conversion lvalue to rvalue
  int&&
  i_ref = 5;
  //binding rvalue reference to prvalue
}
```

1.8 Binds



Ivalue Reference	• const Ivalue Reference	• rvalue Reference ■ binds	
 ■ binds	binds		
olvalue value prvalue	givalue value prolue	expr (hyalue ryalue prollue)	
<pre>auto f(Type&) -> void; Type t{}; f(t);</pre>	<pre>auto f(Type const&) -> void; Type t{}; f(t); f(std::move(t)); f(Type{});</pre>	<pre>auto f(Type&&) -> void; Type t{}; f(Type{}); f(std::move(t));</pre>	

	f(S)	f(S &)	f(S const &)	f(S &&)
S s{}; f(s);	√	√ (preferred over const &)	✓	×
<pre>S const s{}; f(s);</pre>	✓	×	✓	×
f(S{});	✓	×	✓	√ (preferred over const &)
<pre>S s{}; f(std::move(s));</pre>	√	×	✓	√ (preferred over const &)

		S::m()	S::m() const	S::m() &	S::m() const &	S::m() &&	
	S s{}; s.m();	✓	√	(preferred over const &)	✓	×	
	<pre>S const s{}; s.m();</pre>	×	✓	×	✓	×	
	S{}.m();	√	✓	×	✓	(preferred over const &)	
	<pre>S s{}; std::move(s).m();</pre>	√	√	×	√	(preferred over const &)	

1.9 Destructor

Whenever you need to write an explicit destructor, please make sure that you will not throw exeptions here. This can cause memory to not be freed, which... well you guess what heppens In general you should make sure that ANY form of memory management doesn't throw exceptions!!!

1.10 Default Constructors and user defined Constructors

2023_02_28_02_42_32.png

The ! means that it is a standard library bug, don't use those defaulted ones!!! Note that deleting a constructor will be the same as "user declared"!!