0.1 total mass of a uniform parcel

$$M = n \left[\text{mole} \right] N_a \left[\frac{\text{molecule}}{\text{mole}} \right] m \left[\frac{\text{kg}}{\text{molecule}} \right]$$
 (1)

where the Avogadro's constant, $N_a = 6.022 \times 10^{23}$, is found by taking 12 grams of C^{12} and divide by the weight of a single C^{12} . It can also be found by taking 1 gram of H^1 and divide by the weight of a single H^1 . We can thus define the molar mass for C^{12} , $\mu = 12 \left[\frac{g}{\text{mole}}\right] = N_a m$, and the molecular mass of C^{12} , $m = \frac{\mu}{N_a}$ [kg].

0.2 temperature

Definition. Temperature is heat generated by the mean kinetic energy (MKE) of molecules

$$\frac{2}{3}k_BT = <\frac{1}{2}mu^2 > + <\frac{1}{2}mv^2 > + <\frac{1}{2}mw^2 >, \tag{2}$$

divide by the Boltzmann constant $k_B = 1.381 \times 10^{-23} J K^{-1}$. The one-to-one relationship between temperature and MKE implies that the average (time average over a single molecule, or over an ensemble of molecules) KE is always the same under the same macroscopic state.

0.3 pressure

Definition. The statistical force of molecules over an area divide by the area.

Derivation. Given the number density $\tilde{n} = \frac{nN_a}{V}$ (number of molecules per unit volume) of a gas with x-velocity u. All molecules have varying velocity, hence we define the number density \tilde{n}_u indexed by a specific velocity u. The relationship between \tilde{n} and \tilde{n}_u is

$$\tilde{n} = \frac{nN_a}{V}$$

$$= \frac{\sum_{i}^{\infty} n_{u_i} N_a}{V}$$

$$= \frac{\int n_u du N_a}{V}$$

$$= \int \tilde{n}_u du.$$
(3)

The force exerted by molecules with velocity u at the x-direction walls recieving only u is

$$F_u = \tilde{n}_u u \delta t A \frac{2mu}{\delta t} = 2m\tilde{n}_u u^2 A. \tag{4}$$

Integrating over all velocities and divide by the area, the pressure on the wall becomes

$$p = \int 2m\tilde{n}_u u^2 du = 2\tilde{n} < mu^2 > . \tag{5}$$

Since this is the pressure exerted in x-direction on both wall added, so for a single wall we divide by 2 and become

$$p = \tilde{n} < mu^2 > . (6)$$

From the temperature definition we know that $\langle mu^2 \rangle = k_BT$, hence

$$p = \frac{N}{V}k_BT. (7)$$

0.4 ideal gas (equation of state)

Definition. The ideal gas law

$$pV = n(N_a k_B)T = nR^*T (8)$$

where $R^* = 8.314 \text{ J mol}^{-1}\text{K}^{-1}$. Dividing both sides by the mass $M = nN_a m$,

$$\frac{p}{\rho} = \frac{R^*}{N_a m} T = RT,\tag{9}$$

gives the specific gas constant R (R^* per unit molar mass). Set $M = M_d$, $m = m_d$, $p = p_d$ for the dry air, then

$$p_d = \rho_d R_d T, \tag{10}$$

where $R_d = 287 \text{ J kg}^{-1} \text{ K}^{-1}$. This also applies to water vapor

$$e = \rho_v R_v T. \tag{11}$$




Figure 1: left to right: Boyle's Law, Gay-Lussac's Law and Charles's Law.

0.5 state function

Definition. f(p, V, T) = 0. A function that describes the *equilibrium* state of a system (e.g., energy, internal energy, enthalpy, entropy, pressure, temperature, volume, chemical composition, density, etc) irrespective of how the system arrived in the state.

0.6 process function

Definition. Values that depend on the path (e.g., time) of two equilibrium states (e.g., work, and heat).

0.7 internal energy

Definition. $I(S, V, \{N_i\})$, composed of kinetic and potential energy of the molecules and atoms, where chemical potential transfers to kinetic and temperature is proportional to kinetic energy. The change depends only on the initial and final states of the system. Can not be directly measured, but can be prepared by taking partial derivative of entropy, volume, and its mole number.

During a isothermal process with no change in volume (no work involved), then the change in internal energy must be from heat exchange. If the system is adiabatic (no heat involved), then the internal energy change must be from expansion/compression.

0.8 internal energy (dry ideal gas)

Definition. $dI = c_v dT$, the internal energy soley depends on temperature, not volume/density/pressure.

Joule's experiment:

In a free expansion $(p_iV_i = p_fV_f)$, pressure change is completely balanced by volume change), dW = 0, dQ = 0 hence dI = 0, and from the ideal gas equation the temperature stays constant (since the molecules rarely meet even before the expansion, so the kinetic energy, which is affected solely by temperature for ideal gas, remains constant). We can therefore conclude that internal energy is solely governed by temperature. We can imagine this conclusion by using two Joule's experiment by using the same volume compartment beginning with two different temperatures, which gives two internal energies in the end of expansion.

0.9 heat

Definition. Heat is energy "transferred" between two objects or systems in thermal contact, not a state to a single system. Do not confuse heating rate as a time derivative of a function of state.

0.10 heat (dry ideal gas)

Derivation. From first law of thermodynamics for a unit mass of dry ideal gas

$$dQ = dI + dW$$

$$= c_v dT + p d\alpha$$

$$= c_v dT + d(p\alpha) - \alpha dp$$

$$= d(c_v T + p\alpha) - \alpha dp.$$
(12)

Original equation states that the heat change is due to internal energy change and work done by the sytem/dry gas. The final equation first term is heat change due to change in **enthalpy**, $h = I + p\alpha$, at constant pressure. Where change in internal energy/temperature and volume take effect. The second term is heat change at constant temperature due to pressure change (heat increase causes initial molecular momentum to increase/pressure increase, but if temperature stays constant the volume must expand $(pV = Nk_BT)$, thus final pressure decreases). Further derivation

$$dQ = (c_v + R)dT - \alpha dp = c_p dT - \alpha dp$$
(13)

shows that the heat capacity under constant pressure and constant volume could be associated by

$$\left(\frac{\mathrm{d}q}{\mathrm{d}T}\right)_p = \frac{\mathrm{d}h}{\mathrm{d}T} = c_p = c_v + R. \tag{14}$$

0.11 potential temperature (dry ideal gas)

Definition. $\theta = \left(\frac{p_0}{p}\right)^{\kappa}$, this is obtained by setting dQ = 0 and integrate (13).

0.12 (saturation) equivalent potential temperature

Definition. θ_e , the temperature obtained by condensing out all the vapor.

Derivation. From first law,

$$dQ = c_p dT - \alpha dp$$

$$= c_p dT - RT d \ln p$$

$$= c_p (dT - \frac{RT}{c_p} d \ln p)$$

$$= c_p (dT + T d \ln(\frac{p_0}{p})^{\kappa})$$
(15)

when substituting $dQ = -Ldq_s$ (the negative means evaporative cooling of the parcel when q_s increases, otherwise condensative heating) and divide by c_pT this becomes,

$$\frac{-L}{c_p T} dq_s = d \ln T + d \ln \left(\frac{p_0}{p}\right)^{\kappa}
= \ln \left(T \left(\frac{p_0}{p}\right)^{\kappa}\right) = d \ln \theta.$$
(16)

Integrate from saturation to all moisture condensed out $(q_s = 0)$ results in the equivalent potential temperature

$$\theta_e = \theta \exp\left(\int_0^{q_s} \frac{L}{c_p T} dq_s\right) \approx \theta \exp\left(\frac{L}{c_p T} q_s\right).$$
(17)

Where the approximation is due to saturated vapor mixing ratio decreasing much faster than temperature with height (see Wallace and Hobbs p107).

0.13 liquid water potential temperature

Derivation. Replace the lhs of (16) with liquid water which just reverses the process/sign

$$\theta_L \approx \theta \exp(-\frac{L}{c_p T} q_L)$$
(18)

This can be further approximated by the first-order/linear power series of exponential ([1], [2])

$$\theta_L = \theta(1 - \frac{L}{c_p T} q_L). \tag{19}$$

0.14 continuity of water

Derivation. The water vapor for example has

$$\frac{Dq_v}{Dt} = \frac{D}{Dt} \left(\frac{\rho_v}{\rho_d}\right)
= \frac{-\rho_v}{\rho_d^2} \frac{D\rho_d}{Dt} + \frac{1}{\rho_d} \frac{D\rho_v}{Dt}
= \frac{\rho_v}{\rho_d^2} (\rho_d \nabla \cdot v) - \frac{1}{\rho_d} (\rho_v \nabla \cdot v)
= 0,$$
(20)

where the second equality uses mass continuity $(\frac{D\rho}{Dt} = -\rho \nabla \cdot v)$. Thus, with sources and sinks (\dot{S}) becomes

$$\frac{Dq_v}{Dt} = \dot{S}. (21)$$

The n species of water can be expressed as

$$\frac{Dq_i}{Dt} = \dot{S}_i, \ i = 1, \dots, n$$
(22)

0.15 thermodynamic equation

For general non-ideal gas, by combining continuity equation and

$$\frac{DI}{Dt} + p\frac{D\alpha}{Dt} = \dot{Q},\tag{23}$$

results in the internal energy equation

$$\boxed{\frac{DI}{Dt} + p\alpha\nabla \cdot v = \dot{Q}}.$$
(24)

and the pressure term (also missing the dynamics in the momentum equation) could be obtained diagnostically as

$$p = -\frac{\partial I}{\partial \alpha},\tag{25}$$

where α dynamics is from continuity equation.

As for ideal gas,

$$c_v \frac{DT}{Dt} + p \frac{D\alpha}{Dt} = \dot{Q}, \text{ or } c_p \frac{DT}{Dt} + \alpha \frac{Dp}{Dt} = \dot{Q},$$
 (26)

one would obtain a thermodynamic equation for T and solve for p by $p = \rho RT$. Which is by combining the continuity equation with

$$\frac{DI}{Dt} - \frac{RT}{\rho} \frac{D\rho}{Dt} = \dot{Q},\tag{27}$$

and result in the temperature equation

$$c_v \frac{DT}{Dt} + RT\nabla \cdot v = \dot{Q}. \tag{28}$$

If further large scale *hydrostatic balance* $\alpha dp = -g dz$ is assumed, then the thermodynamic equation pertains to the dry static energy $dQ = d(c_v T + gz) = ds$,

$$\boxed{\frac{Ds}{Dt} = \dot{Q}}. (29)$$

According to (22), if the rhs tendency comes from water vapor (see [3] for more details)

$$\boxed{\frac{Ds}{Dt} = -L_v \frac{Dq_v}{Dt}} \tag{30}$$

then there must be sources/sinks of vapor evaporative cooling/condensative heating. The negative sign is explained by supposing there is positive (negative) dq_v , which is increasing (decreasing) the vapor in the parcel, this means that the there must be evaporative cooling (condensative heating) to the parcel.

0.16 reversible process

In thermodynamics term, a process "taken place" is defined as transition from intial to final state. A reversible process is if this process can be reversed without additional work, and causes no change to the system or surrounding environment.

0.17 entropy

A measure of "difference" between adiabats (no heat exchange processes), and a measure of "work loss" in transferring heat (irreversible process).

In a closed system, when heat is added at a constant temperature (volume expands and pressure decreases), the amount of disorder increases which increases the potential temperature (the actual temperature is higher when forced back to original pressure). For a irreversible process, suppose a heat reservoir at T_2 transfers heat Q to a cooler reservoir at T_0 . By Carnot's engine, we know that the maximum available energy the heat transferred into work is

 $W_2 = (1 - \frac{T_0}{T_2})Q. (31)$

For a irreversible process (state variables (e.g., p, V, T) cannot go back to original values without additional work), where heat is first transferred to a middle reservoir at the state $T_1 < T_2$, and then transfers the same amount of heat Q to the cold reservoir at T_0 . Notice since $T_1 < T_2$, therefore the entropy is higher to transfer the same amount of Q. Therefore the maximum available work from the middle reservoir is

$$W_1 = (1 - \frac{T_0}{T_1})Q, (32)$$

which is less than W_2 . Hence, the work loss from irreversible process is

$$W_2 - W_1 = Q(T_0/T_1 - T_0/T_2) = T_0(S_1 - S_2) = T_0 dS,$$
(33)

in a form of heat loss, where the increase in dS becomes a measure of work loss. There is a net gain in entropy in the irreversible process. i.e., the more entropy gain/more disorderness contributes to more work loss, which becomes a less efficient process.

0.18 specific volume

Definition. $v = 1/\rho$, volume occupied by 1kg of mass.

0.19 mixing ratio

Definition. $\frac{m_i}{m_{\text{tot}}-m_i}$.

0.20 vapor mixing ratio

Definition. $q = \frac{m_v}{m_d}$, actual mass mixing ratio between vapor and dry air.

0.21 saturation mixing ratio

Definition. $q_s = \frac{m_{vs}}{m_d}$, maximum amount of water vapor allowed in the dry air.

Derivation.

$$q_s = \frac{m_{vs}}{m_d}$$

$$= \frac{e_s/(R_v T)}{(p - e_s)/(R_d T)}$$

$$= 0.622 \frac{e_s}{p - e_s}$$

$$\approx 0.622 \frac{e_s}{n}$$
(34)

where $p >> e_s$ in the atmosphere.

0.22 latent heat

Definition. Q [kJ], energy released/absorbed by a body during a constant temperature process (phase transition).

0.23 specific latent heat

Definition. L [kJ/kg]= Q/M, amount of heat required to complete phase change of a unit mass of substance.

0.24 Clausius-Claperon Relation

Definition. $\frac{\Delta P}{\Delta T} = \frac{L}{T\Delta v}$, P-T coexistence curve slope relation. Under typical atmoshperic conditions,

$$\frac{de_s}{dT} = \frac{L_v(T)e_s}{R_vT^2},\tag{35}$$

where: L_v is latent heat for evaporation varying with T, R_v is the water vapor gas constant.

0.25 saturation vapor pressure

August-Roche-Magnus formula (approximation from Clausius-Claperon Relation):

$$e_s(T) = 6.1094 \exp\left(\frac{17.625T}{T + 243.04}\right).$$
 (36)

(water-holding capacity of the atmosphere increases by about 7% for every 1°C heated)

0.26 unsaturated vapor pressure

Definition. $e = \frac{(n_{\text{air}} + n_{\text{water}})}{V} RT$,

0.27 relative humidity

Definition. $RH = \frac{e}{e_s}(T)$.

0.28 virtual temperature

Definition. $T_v(p,\rho)$, temperature at which a dry parcel would have at p and ρ of a moist parcel.

Derivation. Suppose a moist parcel has density ρ and pressure p. Dalton's law of partial pressure gives $p = e + p_d$, combined with (??) and (??) give

$$\rho = \frac{m_d + m_v}{V} = \rho_d + \rho_v = \frac{p - e}{R_d T} + \frac{e}{R_v T},\tag{37}$$

where ρ_d and ρ_v are the partial densities. Solving this gives

$$\mathbf{p} = \mathbf{\rho} R_d \frac{T}{1 - \frac{e}{n} (1 - \frac{R_d}{R_v})} = \rho R_d \mathbf{T}_v, \tag{38}$$

where, $\frac{R_d}{R_v} \approx 0.622$ in the atmosphere.

This can be written as a function of specific humidity

$$T_v = T(1 + 0.61q). (39)$$

The gas constant for moist air (a mix of pure water vapor and dry air) depends strongly on the amount of water vapor, so it is convenient to use a fictitious temperature with the dry-air equation of state to represent how "heavy" a moist parcel is (i.e., the more water vapor means a dry air needs to heat more to reach same pressure and density to become "light").

0.29 virtual potential temperature

Definition. $\theta_v = T_v(\frac{p_0}{p})^{\kappa}$, and $\theta_v = \theta(1 + 0.61q)$, by using dry air constant, the virtual potential temperature is just the potential temperature using $T = T_v$,

0.30 lifting condensation level (LCL)

Definition. z_l , height at which an unsaturated parcel reaches saturation, RH = 100%, dry adiabatically, then starts following moist adiabatic lapse rate upward.




Figure 2

0.31 level of free convection (LFC)

Definition. z_f , height at which a moist parcel temperature is equal to the environment, and temperature increases faster than the environment.

Example. The unsaturated parcel in Figure 2 is lifted dry adiabatically from A to B to saturation, and further lifted moist adiabatically to C until surpassing the environmental temperature.

0.32 equilibrium level (EL)

Definition. z_e , height at which the moist parcel lapse rate is greater than environment.

0.33 dew point/condensate temperature

Definition. T_d , temperature at LCL when a parcel reaches RH = 100% by expansion cooling.

0.34 wet bulb temperature

Definition. T_w , the temperature when saturation is reached in a bulb of moist ambient air and a wet cloth through evaporative cooling, i.e., air cooled by cloth warming (measure taken from the air).

 T_w is reached by evaporative cooling, whereas T_d is reached by expansion cooling (constant pressure). $T_d \leq T_w$ since when a parcel saturates by evaporation, the dew point inside increases which is higher than the original dew point T_d .

0.35 convective inhibition (CIN)

Definition. CIN = $\int_{z_0}^{z_f} g \frac{T_{v,\text{parcel}} - T_{v,\text{env}}}{T_{v,\text{env}}} dz$, a negative energy value measuring how much a parcel is prevented to rise to LFC from the surface.

The term $\frac{T_{v,\text{parcel}}}{T_{v,\text{env}}} - 1$ shows when the parcel is moister (larger $T_{v,\text{parcel}}$, more buoyant), CIN is less negative.

0.36 convective available potential energy (CAPE)

Definition. CAPE = $\int_{z_f}^{z_e} g \frac{T_{v,\text{parcel}} - T_{v,\text{env}}}{T_{v,\text{env}}} dz$, differs from CIN in just the levels of integration.

References

- [1] A. Betts, "Non-precipitating cumulus convection and its parameterization," Quart. J. Roy. Meteor. Soc, vol. 99, no. 419, pp. 178–196, 1973.
- [2] H. Grenier and C. S. Bretherton, "A moist pbl parameterization for large-scale models and its application to subtropical cloud-topped marine boundary layers," *Monthly weather review*, vol. 129, no. 3, pp. 357–377, 2001.
- [3] M. F. Khairoutdinov and D. A. Randall, "Cloud resolving modeling of the arm summer 1997 iop: Model formulation, results, uncertainties, and sensitivities," *Journal of the Atmospheric Sciences*, vol. 60, no. 4, pp. 607–625, 2003.