API Reference

Pod Annotation

Specifying the profile a container will run with:

- **key**: container.apparmor.security.beta.kubernetes.io/<container_name>
 Where <container_name> matches the name of a container in the Pod. A separate profile can be specified for each container in the Pod.
- value: a profile reference, described below

Profile Reference

- runtime/default: Refers to the default runtime profile.
 - Equivalent to not specifying a profile (without a PodSecurityPolicy default), except it still requires AppArmor to be enabled.
 - For Docker, this resolves to the docker-default profile for non-privileged containers, and unconfined (no profile) for privileged containers.
- localhost/<profile_name> : Refers to a profile loaded on the node (localhost) by
 name.
 - The possible profile names are detailed in the <u>core policy reference</u>.
- unconfined: This effectively disables AppArmor on the container.

Any other profile reference format is invalid.

PodSecurityPolicy Annotations

Specifying the default profile to apply to containers when none is provided:

- **key**: apparmor.security.beta.kubernetes.io/defaultProfileName
- value: a profile reference, described above

API Reference 1

Specifying the list of profiles Pod containers is allowed to specify:

- **key**: apparmor.security.beta.kubernetes.io/allowedProfileNames
- value: a comma-separated list of profile references (described above)
 - Although an escaped comma is a legal character in a profile name, it cannot be explicitly allowed here.

API Reference 2