NAME

prt – print file

SYNOPSIS

prt [-**B**] [-**b** bin] [-**c** copies] [-**d** dest] [-**f** form] [-**h**] [-**j** jobname] [-**K** "KEYWORD value"] [-**l** language] [-**m**] [-**o** "filter filter_options"] [-**p** printmode] [-**q**] [-**s** sides] [-**u** userid] [-**z**] [-] [filename...]

DESCRIPTION

prt submits the named files and associated information (collectively called a request) to be printed. If no filenames appear or - is specified, prt reads standard input. prt queues a request to be printed when facilities become available. The named files may be reused immediately without affecting the output. User defaults for all options can be set up in a .prt file; otherwise, system defaults are used.

prt associates a unique ID with each request and prints it to standard output. This request ID can be used later to cancel or find the status of the request (see prtc(1) and prtstat(1)).

For additional information about devices, destinations, defaults, languages, etc., see prtinfo(1).

The following options may appear in any order preceding the file names:

-B Input data is binary - suppress the WARNING message that indicates the input data contains non-printable characters. Note: such a WARNING message is displayed whenever *prt* detects that there are more than 25 non-printable characters in the input.

−**b** string Forward output to string where string can be one of the following:

bin Put the output in bin number bin (1 to 10 characters). By default, the bin number is taken from the user's .prt file. If it is not set, the bin is taken from the password file.

"#IDNO"

Hold output in secure area, to be released to person bearing badge with *IDNO*, normally a payroll account number or social security number. The # symbol must be the first character in string.

"%address"

 $-\mathbf{d} \ dest$

Send the output to bin **MAIL** for delivery via company mail. Use *address* as a string to specify the name and company mail address of the recipient to appear on the banner page. The % must be the first character in the address. Semicolons can be used to split the address string so that a multi-line address (maximum 7 lines) is displayed on the banner page. The **-d** option can be used to speed mail delivery by printing the job at a site near the recipient where it will enter the company mail for final delivery.

Note that *prt* does NOT get the bin from the environment variable \$BIN.

 $-\mathbf{c} n$ Make *n* copies of the output. The default is 1. The maximum number of copies is 99.

Print the output at destination *dest. dest* has two parts; both parts can be given together, or either part can be given alone. When specifying both parts, the *dest* argument should appear in the form *location/device. location* can be a network node name, a site code, or *fax. device* can be a specific printer name, a generic device type, or a fax phone number. The two parts are separated by a slash (/).

When specifying *location* alone, the slash is required. When specifying *device* alone, the slash is not necessary. The default for *location* is the network node name of the current system. Examples of *dest* are: ho2g4, imagen1, i300, post, x9700, aps, prism, hou2a/, ihuxj/, ho/, wh/, /i300, mh/i300, ih/im1, and fax/2019491234. The *device* must be 8 characters or less.

Note that *prt* does NOT get the dest from the environment variable \$DEST.

-f form Print on form form (1 to 8 characters). Examples of form names are:

vg viewgraph or transparency

holepaper with holesnoholepaper with no holeslegal8 1/2 x 14 inch paperledger11 x 17 inch paperlibrary14 x 17 inch paper

Note: Forms are not usually set up for local printers, as Imagen or PostScript printers. All forms may not be available for all printers.

−**h** Print full help message.

 $-\mathbf{j}$ jobname Use jobname (1 to 14 characters) instead of the default requested on the banner page of the

printout.

-K "KEYWORD value"

Specify a *keyword* and *value* for device- dependent options. The *keyword* should be specified in upper- case. Multiple - K options can be specified. For more information on valid keywords, refer to the specific device type manual page, such as *devi300(5)*, *devpost(5)*, *devx9700(5)*. Examples include: - K"JOBHDR n", and - K"FILTEROPTS x9700 - s xr18".

-l language

Identify the type of file by specifying *language* (1 to 14 characters). If no language is specified, the input is assumed to contain ASCII text and should be printed as if on a generic line printer. The standard input languages valid across most device types, are:

printer indicates the input contains ASCII text;

input should be printed as if on a generic line printer

troff indicates the input contains output from the troff formatter **nroff** indicates the input contains output from the nroff formatter

troffin indicates the input contains troff input statements **nroffin** indicates the input contains nroff input statements

meta indicates the input is a DI3000 metafile

nje indicates the input was submitted from MVS via NJE
gr indicates the input contains gr input statements
raw indicates the input requires no translation;

the input contains statements the device understands

Additional examples include dimpress, postscript, pepostscript, tektronix and daisy.

The language **pcpostscript** should be used for **PostScript** files generated by MS- DOS[®] PC applications.

 Send a reply via electronic mail to report job completion. The default is that no mail is sent. Error messages will always be mailed.

−o "filter filter options"

Specify a filter and device dependent options. Examples of filters are: **dimpress** and **x9700**. For more information on valid *filter_options*, see the specific filter man page. Multiple **-o** options can be specified. A pipeline of filter commands will be created in the order the **-o** options are specified.

This option will be phased out in a future release. See the - K option to specify device-dependent options. If desired, you can specify the filter and filter_options by using **-K"FILTEROPTS** *filter filter options"*.

- **p** printmode Print in the mode printmode. Examples of printmodes are

portrait 8.5 x 11 inches, letter orientation

landscape 11 x 8.5 inches

2 logical pages on 1 physical side

-q Quiet. Suppress the one-line message which contains the submitted request ID and/or job

name.

-s sides Print on sides sides of a sheet of paper. Examples are -s1 and -s2 Note: Two-sided output

is only available at sites that have devices that support the duplexing feature.

−**u** userid Print userid (1 to 14 characters) on the banner page.

−z Write the request to standard output instead of submitting it. A request header showing the

defaults will be listed along with the user's data. This option is used primarily for debug-

ging.

EXAMPLES

To print a file (using all the default settings):

prt filename

To print a file at another location, for example, *IH*:

prt - d ih/ filename

To print a file on a specific printer named imagen1 at another location, MH,

prt - d mh/imagen1filename

To print a file with line numbers:

pr - **n**filename | **prt**

To expand input tabs to character positions 10, 19, 28, 37 ... and print the file:

pr - e9filename | prt

To print a file containing PostScript language on printer called *qms-a*,

prt - d qms- a - l postscrip@lename

To print 3 copies of a file without the banner page to device *brains*,

prt - c3 - K"JOBHDR n" - d brainslename

To print a file on the Xerox 9700 in portrait mode, using font style XR18:

prt - d x9700 - p port - K "FILTEROPTS x9700 - s xr18filename

See also .prt(4) for setting your own printing defaults.

FILES

\$HOME/.prt \$UNISONTABLES/.prtsys

\$UNISON/*

/etc/passwd

SEE ALSO

prtfmt(1), prtinfo(1), prtstat(1), prtc(1), .prt(4), .prtsys(4), devi300(5), devpost(5), devprism(5), devstare(5), devx9700(5), dev3203(5), devhp(5).