

PromptMeGood Whisperer Fix Brief

CORE OBJECTIVE

The Prompt Whisperer scrolling placeholder text (the typewriter animation) is missing from the live site. The text is generating correctly in the DOM, but it is visually hidden behind the input field.

This brief provides the exact root cause and the targeted CSS fix to restore the typewriter animation.

BUG: MISSING WHISPERER TYPEWRITER TEXT

The Problem:

The `pmg-spark-panel.js` script is running perfectly. It correctly injects the cycling questions into the `#whisperer-typewriter` element.

However, the CSS layering is broken. The `.whisperer-input` field is designed to sit over the typewriter text so the user can click into it. To make the typewriter text visible underneath, the input field's background must be transparent.

Currently, the `.whisperer-input` has a computed background color of `rgb(14, 58, 54)` (a solid dark green) instead of `transparent`. Because the input has a solid background and a higher `z-index` (2) than the typewriter text (1), the typewriter text is completely blocked from view.

The Fix:

Force the `.whisperer-input` background to be transparent so the typewriter text underneath is visible.

1. In `pmg-spark-panel.css` (or wherever the whisperer input is styled):

Update the `.whisperer-input` class to ensure the background is strictly transparent.

CSS

```
.whisperer-input {
  background: transparent !important; /* Force transparency so the typewriter s
  /* Keep existing styles */
  width: 100%;
  border: none;
  border-bottom: 1px solid rgba(0, 200, 150, 0.3);
  color: #fff;
  font-size: 15px;
  padding: 6px 4px;
  outline: none;
```

```
font-family: inherit;  
transition: border-color 0.2s;  
border-radius: 0;  
position: relative;  
z-index: 2;  
}
```

IMPLEMENTATION STEPS

1. Locate the CSS rule for `.whisperer-input` .
2. Add `background: transparent !important;` to ensure no other global input styles are overriding it with a solid color.