9/20/23, 12:54 PM TestOut LabSim

## 8.8.3 Quota Facts

This lesson covers the following topics:

- Disk quota overview
- Implement disk quotas
- Disk quota commands

## **Disk Quota Overview**

Disk quotas prevent a user or group from using a disproportionate amount of disk space on a volume. You can configure quotas to:

- Limit the number of files and directories a user or group can create.
- Limit the amount of disk space a user or group can use.

Quota types include the following:

- A soft limit, which allows a user to temporarily exceed a quota limit.
- A hard limit, which is a fixed limit that a user cannot exceed.

## **Implement Disk Quotas**

The following table lists the general steps to implement disk quotas:

Step	Procedure
Install the quota package	Use <b>yum</b> , <b>zypper</b> , or <b>apt-get</b> to install the quota package on the system where you want to set the quota limits.
Edit the mount options in <b>/etc/fstab</b>	Edit the /etc/fstab file to add the mount options for the file system and enable quotas.  • usrquota enables quotas for users.  • grpquota enables quotas for groups.
Create the quota files	Create the <b>aquota.user</b> and <b>aquota.group</b> files in the directory where the partition is mounted.
Enable the quotas and view a quota report	<ul> <li>Enable disk quotas and then generate a disk usage and quota report. The report shows:</li> <li>How much space to allocate to each user.</li> <li>How much space is currently consumed by each user.</li> </ul>

9/20/23, 12:54 PM TestOut LabSim

What has a second upon a second secon
Whether some users are using a significant amount of disk space.
Edit a quota for the specified user or group. Be aware of the following when editing quotas:
<ul> <li>Set the soft and hard quotas for blocks. This limits the total amount of disk space per user or group.</li> <li>Set the hard and soft quotas for inodes. This limits the total number of files and directories per user or group.</li> <li>Users may exceed soft quotas for the number of days specified in the grace period (seven by default). When the grace period expires, users can't create additional files.</li> <li>Users cannot exceed hard quotas.</li> <li>When setting block quotas, 1,000 blocks is about 1 MB, and 1,000,000 blocks is about 1 GB.</li> <li>Setting the quota limits to 0 removes all quotas.</li> </ul>

## **Disk Quota Commands**

The table below describes common commands for working with quotas.

Command	Function	Examples
quotacheck - mavug	Creates the aquota.user and aquota.group files in the file system (after placing the quota entries in /etc/fstab). Consider the common options below.  • -m updates the quota database even if other processes are running on the file system.  • -a updates the quota database.  • -v runs the command in Verbose Mode.  • -u and -g run the database updates for users and groups, respectively.	quotacheck -mavug /home creates the aquota.user and aquota.group files in the root (/) directory.
quotaon	Enables quotas for the mounted file system. Consider the common options below.  • -a enables all mounted file systems listed in /etc/mtab.  • -v runs the command in Verbose Mode.	<b>quotaon -av /</b> enables quotas for the root (/) directory.
quotaoff	Disables quotas for the mounted file system.	<b>quotaoff /home</b> disables quotas for the /home directory.

9/20/23, 12:54 PM TestOut LabSim

repquota	Displays a summary of the disc usage and quotas for the specified file systems, including the specific number of files and space by user. Consider the common options below.  • -v reports all quotas, even if there is no usage.  • -n does not resolve user and group names to speed printing time.  • -u and -g give reports for users and groups, respectively.  • -a gives information for all file systems listed in /etc/mtab.	<b>repquota /home -uv</b> creates a user quota report for the /home directory.
edquota	Opens and edits a user's quota, a group's quota, or changes the grace period. Consider the common options below.  • -u changes a user's quota. • -g changes a group's quota. • -t changes the grace period.	edquota -u mtomm opens the quota file for the mtomm user account.
quota	Displays the current user's or group's quota.  Consider the common options below.  • -u shows the current user's quota. • -g shows the current group's quota. • -v shows current usage (the hard and soft quota for blocks and inodes).	quota displays the quota report for the current user account only. quota -u dhanson displays the quota report for the dhanson user account only.

Copyright © 2023 TestOut Corp. Copyright © The Computing Technology Industry Association, Inc. All rights reserved.