WMS Task 004 — Corrected Handover Report

> **Project:** MP Transport Warehouse Management System
> **Environment:** https://nnuk.wms.mp-transport.co.uk
> **Branch:** feature/catalogue-and-mapping
> **Latest commit:** b601fdd
> **Date:** 6 November 2026
> **Addresses:** Paul's six review points from Task 004 provisional acceptance — all resolved

1. Test Results — 52 Tests, 52 Passed

```
Database engine: SQLite :memory: | PHP 8.3.35 | Pest 4.7.8
{"tool":"pest","result":"passed","tests":52,"passed":52,"assertions":104}
```

File	Tests	Result
FoundationTest.php	4	✅ **ALL PASS**
CatalogueTest.php	13	✅ **ALL PASS**
Task004Test.php (incl. 4 new HTTP cross-client tests)	35	✅ **ALL PASS**
Total	**52**	✅ **52 PASSED**

2. Deployment Environment

Item	Detail
URL tested	https://nnuk.wms.mp-transport.co.uk
Server	MP Transport cPanel / AlmaLinux 8 / PHP 8.3
Branch deployed	feature/catalogue-and-mapping
Merged to main?	No — awaiting Paul and Craig sign-off
Real warehouse data?	No — test data only (DemoSeeder)

3. Cross-Client Security (HTTP Level)

Four HTTP-level tests added (commit aee3d86) proving URL-direct cross-client access returns 404:

- Admin from Client A requesting Client B warehouse URL → **404**
- Admin from Client A requesting Client B locations URL → **404**
- Unauthenticated warehouse URLs → **302 redirect to /login**
- Unauthenticated user management URLs → **302 redirect to /login**

Enforcement mechanism: Eloquent FulfilmentClientScope global scope filters route model binding — independent of middleware.

4. SMTP — Configured and Tested

Setting	Value
Provider	cPanel Exim — cloud.mp-transport.co.uk
Host	mail.mp-transport.co.uk
Port	465 (SMTPS)
Username	no-reply@mp-transport.co.uk
Authentication	235 Authentication succeeded ✅
Test email delivered	✅ Confirmed
Password reset end-to-end	✅ Email delivered, link clicked, new password set, login confirmed

5. Browser Verification Summary

Verification	Status
Warehouse creation	✅ **CONFIRMED**
Barcode auto-generation	✅ **CONFIRMED**
Duplicate barcode prevention	✅ **CONFIRMED**
Deactivated location visible under All filter	✅ **CONFIRMED**
Zone colour coding	✅ **CONFIRMED**
Admin user management	✅ **CONFIRMED**
Operator — no Administration group	✅ **CONFIRMED**
Supervisor — no Administration group	✅ **CONFIRMED**
Create user via UI form	✅ **CONFIRMED**
Password reset email sent and delivered	✅ **CONFIRMED**
Password reset link works end-to-end	✅ **CONFIRMED**
Merge to main / production release	⏳ **PENDING sign-off**

6. Screenshots — All Taken from Live Site 6 November 2026

Screenshot 1 — Warehouse list


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
+ New Warehouse
Active

Warehouses

Physical warehouse locations for NeoNail UK

Search warehouses...

WAREHOUSE	ADDRESS	LOCATIONS	STATUS	
MP Transport — Main Warehouse	—	4 locations	Active	Edit

Shows MP Transport Main Warehouse (Active, 4 locations). Sidebar displays Warehouses & Locations and User Management — confirming admin navigation.

Screenshot 2 — New Location form (empty)


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
Save Location
Cancel

New Location

Add a bin, shelf or zone location.

LOCATION IDENTITY

Zone * A — Ambient Storage

Location Type * Bin

Section / Rack 01

Shelf Level 02

Bin / Position 03

Barcode / Reference * (auto-generated or enter manually) e.g. A01-S02-B03

Must be unique within this warehouse. This is what the scanner reads.

Display Name * e.g. Ambient Rack 1 Shelf 2 Bin 3

CAPACITY & NOTES

Maximum Capacity (units) Leave blank if unconfigured

Optional. Used by the system to warn when a bin is full.

Notes Any notes about this location

☑ Active

Shows the New Location form with zone/section/shelf/bin fields. The barcode placeholder shows the expected format.

Screenshot 3 — Barcode auto-generation


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
Save Location
Cancel

New Location

Add a bin, shelf or zone location.

LOCATION IDENTITY

Zone * A — Ambient Storage

Location Type * Bin

Section / Rack 01

Shelf Level 01

Bin / Position 01

Barcode / Reference * (auto-generated or enter manually) A01-S01-B01

Must be unique within this warehouse. This is what the scanner reads.

Display Name * Ambient Rack 1 Shelf 1 Bin 1

CAPACITY & NOTES

Maximum Capacity (units) Leave blank if unconfigured

Optional. Used by the system to warn when a bin is full.

Notes Any notes about this location

☑ Active

Zone=A, Section=01, Shelf=01, Bin=01 typed in. Barcode field has auto-populated A01-S01-B01. Display Name also auto-filled. ✅ Auto-generation confirmed.

Screenshot 4 — Duplicate barcode prevention


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
Save Location
Cancel

New Location

Add a bin, shelf or zone location.

LOCATION IDENTITY

Zone * A — Ambient Storage

Location Type * Bin

Section / Rack 01

Shelf Level 01

Bin / Position 01

Barcode / Reference * (auto-generated or enter manually) A01-S01-B01

The barcode has already been taken.

Must be unique within this warehouse. This is what the scanner reads.

Display Name * Ambient Rack 1 Shelf 1 Bin 1

CAPACITY & NOTES

Maximum Capacity (units) Leave blank if unconfigured

Optional. Used by the system to warn when a bin is full.

Notes Any notes about this location

☑ Active

Attempting to save a second location with barcode A01-S01-B01. Red error: 'The barcode has already been taken.' Form cannot be submitted. ✅ Duplicate prevention confirmed.

Screenshot 5 — Location list (All filter)


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
+ New Location
All zones
All

MP Transport — Main Warehouse — Locations

Manage bin, shelf and zone locations.

Search barcode or name...

BARCODE / REFERENCE	NAME	ZONE	TYPE	CAPACITY	STATUS	
A01-S01-B01	Ambient Rack 1 Shelf 1 Bin 1	A — Ambient Storage	Bin	—	Active	Edit
A01-S01-B02	Ambient Rack 1 Shelf 1 Bin 2	A — Ambient Storage	Bin	—	Inactive	Edit
I01	Inbound Area	I — Inbound Holding	Zone	—	Active	Edit
Q01	Quarantine Area	Q — Quarantine	Zone	—	Active	Edit

4 locations shown: A01-S01-B01 (Active, green Ambient badge), A01-S01-B02 (Inactive, grey badge), I01 (Inbound Holding, amber), Q01 (Quarantine, amber). ✅ Deactivation and zone colour coding confirmed.

Screenshot 6 — User Management (admin view)


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
+ New User
All roles
Active

Users

Manage warehouse staff accounts and permissions.

Search name or email...

NAME	EMAIL	ROLE	STATUS	
Admin (you)	admin@mp-transport.co.uk	Admin	Active	
Admin User	admin@neonail.test	Admin	Active	Edit
Test Operator	operator2@neonail.test	Operator	Active	Edit
Warehouse Operator	operator@neonail.test	Operator	Active	Edit

User list with 4 users: Admin (you), Admin User, Test Operator, Warehouse Operator. Role badges visible. No Edit button on own row. ✅ Admin user management confirmed.

Screenshot 7 — Operator view: no Administration group


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
TO
Test Operator

Logged in as Test Operator (TO initials bottom-left). Sidebar: Platform, Catalogue, Warehouse — Administration group absent. ✅ Operator restriction confirmed.

Screenshot 8 — Create User form


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
Create User
Cancel

New User

Create a new warehouse staff account.

ACCOUNT DETAILS

Full Name * Test Supervisor

Email Address * supervisor@neonail.test

Role * Supervisor — approve exceptions, view r

Initial Password * ••••••••••

New User form: Test Supervisor, supervisor@neonail.test, Supervisor role selected, password obscured. ✅ User creation via UI form confirmed.

Screenshot 9 — User created successfully


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
+ New User
All roles
Active

Users

Manage warehouse staff accounts and permissions.

User Test Supervisor created.

Search name or email...

NAME	EMAIL	ROLE	STATUS	
Admin (you)	admin@mp-transport.co.uk	Admin	Active	
Admin User	admin@neonail.test	Admin	Active	Edit
Test Operator	operator2@neonail.test	Operator	Active	Edit
Test Supervisor	supervisor@neonail.test	Supervisor	Active	Edit
Warehouse Operator	operator@neonail.test	Operator	Active	Edit

Green banner: 'User Test Supervisor created.' Test Supervisor appears in list with amber Supervisor badge. ✅ End-to-end user creation confirmed.

Screenshot 10 — Supervisor view: no Administration group


NeoNailWMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
TS
Test Supervisor

Logged in as Test Supervisor (TS initials bottom-left). Same sidebar restriction as Operator — no Administration group. ✅ Supervisor restriction confirmed.

Screenshot 11 — Password reset sent


MP WMS
Platform
Dashboard
Catalogue
Products
Variant Mappings
Warehouse
Warehouses & Locations
Administration
User Management
System
Foundation
A
Admin
Send Password Reset Email
Save Changes
Cancel

Edit User

Update account details and permissions.

ACCOUNT DETAILS

Full Name * Test Supervisor

Email Address * mpt-portal@mp-trans

Role * Supervisor — approve exceptions, view r

New Password (leave blank to keep current) Leave blank to keep unchanged

☑ Account active

Inactive accounts cannot log in. The account history is preserved.

PASSWORD RESET

Send a password reset link to the user's email address. They will receive a secure link to set a new password. No password is revealed.

✓ Password reset link sent to mpt-portal@mp-transport.co.uk.

Edit User form for Test Supervisor. After clicking Send Password Reset Email: green confirmation 'Password reset link sent to mpt-portal@mp-transport.co.uk.' App name shows MP WMS. Email delivered, reset link worked, new password confirmed in private browser. ✅ Password reset end-to-end confirmed.

7. Outstanding Items

Item	Status
Location reclassification guard (before live stock)	⏳ **To implement before Phase 3**
Label printing (Zebra ZD421t)	⏳ **Phase 3**
Business decisions BD-01 through BD-11	⏳ **Paul/Craig to confirm**
Merge to main and production release	⏳ **Requires Paul and Craig sign-off**

> *Latest commit: b601fdd | Branch: feature/catalogue-and-mapping*
> *52 automated tests, 52 passing | SQLite :memory: | PHP 8.3.35*
> *Produced 6 November 2026 — MP Transport WMS Project*