# Lab3实验报告

191300087 左之睿 1710670843@qq.com

## 一、实验进度

完成了所有非选做部分

## 二、实验结果

如下图所示,每隔一段时间会进行打印

```
Pather Process: Ping 1, 7;
Child Process: Ping 2, 7;
Father Process: Ping 1, 6;
Child Process: Pong 2, 6;
Father Process: Ping 1, 5;
Child Process: Pong 2, 5;
```

```
QEMU - Press Ctrl-Alt to exit mouse grab

Father Process: Ping 1, 7;

Child Process: Pong 2, 6;

Father Process: Ping 1, 5;

Child Process: Pong 2, 5;

Father Process: Ping 1, 4;

Child Process: Ping 1, 4;

Child Process: Ping 1, 3;

Child Process: Ping 1, 3;

Child Process: Ping 1, 3;

Child Process: Ping 2, 3;

Father Process: Ping 1, 2;

Child Process: Pong 2, 2;

Father Process: Ping 1, 1;

Child Process: Ping 2, 2;

Father Process: Ping 2, 1;
```

#### 三、实验修改的代码位置

首先,按照指导pdf的要求,先去完善syscall.c中的库函数,这一部分非常简单,代码如下

```
pid_t fork() {
          return syscall(SYS_FORK, 0, 0, 0, 0, 0);
}

int sleep(uint32_t time) {
          return syscall(SYS_SLEEP,time,0,0,0,0);
}

int exit() {
          return syscall(SYS_EXIT,0,0,0,0,0);
}
```

接下来实现timerhandle函数,这个根据实验指导的描述,实现起来也比较容易

```
void timerHandle(struct StackFrame *sf){
        uint32_t tmpStackTop;
        int i;
        for (i = 0; i < MAX PCB NUM; ++i)
                if (pcb[i].state == STATE_BLOCKED){
                        if (pcb[i].sleepTime == 1)
                               pcb[i].state = STATE RUNNABLE;
                       else
                               pcb[i].sleepTime-=1;
                }//对应时钟中断功能1
        pcb[current].timeCount++;
        if (pcb[current].timeCount >= MAX TIME COUNT) {
                pcb[current].state = STATE_RUNNABLE;
                pcb[current].timeCount = 0;
                for (i = (current + 1) % MAX PCB NUM; i != current; i = (i + 1) % MAX PCB NUM)
                        if (pcb[i].state == STATE_RUNNABLE){
                                ...切换进程
                       }
        }//时钟中断功能2
}
```

最后实现syscallFork,syscallSleep,syscallExit,在此先说较为简单的sleep和rxit,这两个都是先修改当前进程的状态,然后遍历寻找下一个等待中的进程,最后用lab3的pdf中给出的相应代码进行进程切换即可,在此给出syscallSleep的部分代码

较为困难的是syscallFork,首先需要找一个空闲进程被Fork

然后将父进程的内容拷贝到子进程,需要注意的是stackTop和prevStackTop以及cs, gs, ds, fs, ss, es并不是通过复制而来,并且cs是USEL(1+2i),而其他的为USEL(2+2i),最终再设置子进程号即可

```
for (j = 0; j < 0x100000; j++) {
        *(uint8 t *)(j + (i+1)*0x100000) = *(uint8 t *)(j + (current+1)*0x100000);
}
disableInterrupt();
pcb[i].stackTop = (uint32_t)&(pcb[i].regs);
pcb[i].prevStackTop = (uint32_t)&(pcb[i].stackTop);
pcb[i].state = STATE RUNNABLE;
pcb[i].timeCount = 0;
pcb[i].sleepTime = 0;
pcb[i].pid = i;
pcb[i].regs.ss = USEL(2+2*i);
pcb[i].regs.cs = USEL(1+2*i);
pcb[i].regs.ds = USEL(2+2*i);
pcb[i].regs.es = USEL(2+2*i);
pcb[i].regs.fs = USEL(2+2*i);
pcb[i].regs.gs = USEL(2+2*i);
pcb[i].regs.eflags = pcb[current].regs.eflags;
pcb[i].regs.edx = pcb[current].regs.edx;
pcb[i].regs.ecx = pcb[current].regs.ecx;
pcb[i].regs.ebx = pcb[current].regs.ebx;
pcb[i].regs.esp = pcb[current].regs.esp;
pcb[i].regs.ebp = pcb[current].regs.ebp;
pcb[i].regs.edi = pcb[current].regs.edi;
pcb[i].regs.esi = pcb[current].regs.esi;
pcb[i].regs.eip = pcb[current].regs.eip;
pcb[i].regs.eax = 0;//子进程号
pcb[current].regs.eax = i;
```

#### 四、实验感想

本次实验相对来说较为简单,让我对于系统内部的进程管理加深了理解