Install MongoDB > Install MongoDB Enterprise > Install MongoDB Enterprise on Linux > Install MongoDB Enterprise on Ubuntu

# Install MongoDB Enterprise on Ubuntu¶

### On this page

- Overview
- Install MongoDB Enterprise
- Install MongoDB Enterprise From Tarball
- Run MongoDB Enterprise
- Uninstall MongoDB

### Overview

Use this tutorial to install MongoDB Enterprise 

on LTS Ubuntu Linux systems from .deb packages.

□ on LTS Ubuntu Linux systems from .deb packages.

#### PLATFORM SUPPORT:

MongoDB only provides packages for 64-bit LTS (long-term support) Ubuntu releases. For example, 12.04 LTS (precise), 14.04 LTS (trusty), 16.04 LTS (xenial), and so on. These packages may work with other Ubuntu releases, however, they are not supported.

#### PACKAGE UPDATES REQUIRED ON UBUNTU 16.04 FOR IBM POWER SYSTEMS:

Due to a lock elision bug present in older versions of the glibc package on Ubuntu 16.04 for POWER, you must upgrade the glibc package to at least glibc 2.23-0ubuntu5 before running MongoDB. Systems with older versions of the glibc package will experience database server crashes and misbehavior due to random memory corruption, and are unsuitable for production deployments of MongoDB

MongoDB provides officially supported Enterprise packages in their own repository. This repository contains the following packages:

Package Name

**Description** 

mongodb-enterprise	A metapackage that will automatically install the four component packages listed below.
mongodb-enterprise- server	Contains the mongod daemon and associated configuration and init scripts.
mongodb-enterprise- mongos	Contains the mongos daemon.
mongodb-enterprise- shell	Contains the mongo shell.
mongodb-enterprise- tools	Contains the following MongoDB tools: mongoimport bsondump, mongodump, mongoexport, mongofiles, mongooplog, mongoperf, mongorestore, mongostat, and mongotop.

# Install MongoDB Enterprise

#### NOTE:

1

To install a different version of MongoDB, please refer to that version's documentation. For example, see version 3.2 .

MongoDB only provides packages for 64-bit LTS (long-term support) Ubuntu releases. For example, 12.04 LTS (precise), 14.04 LTS (trusty), 16.04 LTS (xenial), and so on. These packages may work with other Ubuntu releases, however, they are not supported.

Use the provided distribution packages as described in this page if possible. These packages will automatically install all of MongoDB's dependencies, and are the recommended installation method.

### Import the public key used by the package management system.

The Ubuntu package management tools (i.e. dpkg and apt) ensure package consistency and authenticity by requiring that distributors sign packages with GPG keys. Issue the following command to import the MongoDB public GPG Key ::

sudo apt-key adv --keyserver hkp://keyserver.ubuntu.com:80 --recv 0C49F3730359A145

### 2 Create a /etc/apt/sources.list.d/mongodb-enterprise.list file for MongoDB.

Create the list file using the command appropriate for your version of Ubuntu:

Ubuntu 12.04

```
echo "deb [ arch=amd64 ] http://repo.mongodb.com/apt/ubuntu precise/mongodb-enterp
```

Ubuntu 14.04

```
echo "deb [ arch=amd64 ] http://repo.mongodb.com/apt/ubuntu trusty/mongodb-enterpr
```

Ubuntu 16.04

```
echo "deb [ arch=amd64,arm64,ppc64el,s390x ] http://repo.mongodb.com/apt/ubuntu xe
```

If you'd like to install MongoDB Enterprise packages from a particular release series, such as 2.4 or 2.6, you can specify the release series in the repository configuration. For example, to restrict your system to the 2.6 release series, add the following repository:

```
echo "deb http://repo.mongodb.com/apt/ubuntu "$(lsb_release -sc)"/mongodb-enterpri
```

3

### Reload local package database.

Issue the following command to reload the local package database:

sudo apt-get update

### 4 Install the MongoDB Enterprise packages.

Install the latest stable version of MongoDB Enterprise.

Issue the following command:

sudo apt-get install -y mongodb-enterprise

Versions of the MongoDB packages before 2.6 use a different repository location. Refer to the version of the documentation appropriate for your MongoDB version.

## Install MongoDB Enterprise From Tarball

While you should use the .deb packages as previously described, you may also manually install MongoDB using the tarballs. See Install MongoDB Enterprise From Tarball for details.

# Run MongoDB Enterprise

The MongoDB instance stores its data files in /var/lib/mongodb and its log files in /var/log/mongodb by default, and runs using the mongodb user account. You can specify alternate log and data file directories in /etc/mongod.conf. See systemLog.path and storage.dbPath for additional information.

If you change the user that runs the MongoDB process, you **must** modify the access control rights to the /var/lib/mongodb and /var/log/mongodb directories to give this user access to these directories.

Most Unix-like operating systems limit the system resources that a session may use. These limits may negatively impact MongoDB operation. See UNIX ulimit Settings for more information.

### 1 Start MongoDB.

Issue the following command to start mongod:

sudo service mongod start

### 2 Verify that MongoDB has started successfully

Verify that the mongod process has started successfully by checking the contents of the log file at /var/log/mongodb/mongod.log for a line reading

[initandlisten] waiting for connections on port <port>

where <port> is the port configured in /etc/mongod.conf, 27017 by default.

### 3 Stop MongoDB.

As needed, you can stop the mongod process by issuing the following command:

sudo service mongod stop

Restart MongoDB.

Issue the following command to restart mongod:

sudo service mongod restart

### 5 Begin using MongoDB.

To help you start using MongoDB, MongoDB provides Getting Started Guides in various driver editions. See Getting Started for the available editions.

Before deploying MongoDB in a production environment, consider the Production Notes document.

Later, to stop MongoDB, press Control+C in the terminal where the mongod instance is running.

# Uninstall MongoDB

To completely remove MongoDB from a system, you must remove the MongoDB applications themselves, the configuration files, and any directories containing data and logs. The following section guides you through the necessary steps.

#### **WARNING:**

This process will *completely* remove MongoDB, its configuration, and *all* databases. This process is not reversible, so ensure that all of your configuration and data is backed up before proceeding.

### 1 Stop MongoDB.

Stop the mongod process by issuing the following command:

sudo service mongod stop

2

### Remove Packages.

Remove any MongoDB packages that you had previously installed.

sudo apt-get purge mongodb-enterprise\*

#### 3 Remove Data Directories.

Remove MongoDB databases and log files.

sudo rm -r /var/log/mongodb
sudo rm -r /var/lib/mongodb