RIP Next Generation (RIPng)

Sample Chapter is provided courtesy of Cisco Press.
Date: May 27, 2016.

Chapter Information

Contents

From the Book

Verifying and Troubleshooting RIPng

CAUTION

Using the **debug** command may severely affect router performance and might even cause the router to reboot. Always exercise caution when using the **debug** command. Do not leave **debug** on. Use it long enough to gather needed information, and then disable debugging with the **undebug all** command.

TIP

Send your **debug** output to a syslog server to ensure you have a copy of it in case your router is overloaded and needs to reboot.

`Router#clear ipv6 rip`	Deletes routes from the IPv6 RIP routing table and, if installed, routes in the IPv6 routing table.
`Router#clear ipv6 route *`	Deletes all routes from the IPv6 routing table. **NOTE** Clearing all routes from the routing table causes high CPU utilization rates as the routing table is rebuilt.
`Router#clear ipv6 route 2001:db8:c18:3::/64`	Clears this specific route from the IPv6 routing table.
`Router#clear ipv6 traffic`	Resets IPv6 traffic counters.
`Router#debug ipv6 packet`	Displays debug messages for IPv6 packets.
`Router#debug ipv6 rip`	Displays debug messages for IPv6 RIP routing transactions.
`Router#debug ipv6 routing`	Displays debug messages for IPv6 routing table updates and route cache updates.
`Router#show ipv6 interface`	Displays the status of interfaces configured for IPv6.

`Router#show ipv6 interface brief`	Displays a summarized status of all interfaces along with assigned IPv6 addresses.
`Router#show ipv6 neighbors`	Displays IPv6 neighbor discovery cache information.
`Router#show ipv6 protocols`	Displays the parameters and the current state of the active IPv6 routing protocol processes.
`Router#show ipv6 rip`	Displays information about the current IPv6 RIPng process.
`Router#show ipv6 rip database`	Displays the RIPng process database. If more than one RIPng process is running, all are displayed with this command.
`Router#show ipv6 rip next-hops`	Displays RIPng processes and, under each process, all next-hop addresses.
`Router#show ipv6 route`	Displays the current IPv6 routing table.
`Router#show ipv6 route rip`	Displays the current RIPng routes in the IPv6 routing table
`Router#show ipv6 route summary`	Displays a summarized form of the current IPv6 routing table.
`Router#show ipv6 routers`	Displays IPv6 router advertisement information received from other routers.
`Router#show ipv6 traffic`	Displays statistics about IPv6 traffic.

Previous Section 3. Configuration Example: RIPng | Next Section