

Actividad Práctica 6

Angel Emanuel Rodriguez Corado - 20240856


1. Topología Completa.



2. IP de PC-Inferior



3. IP de PC-Superior



4. HSRP de R1

```
R1-Activo>enable
R1-Activo#show standby
GigabitEthernet0/0 - Group 1
  State is Active
    6 state changes, last state change 00:00:37
  Virtual IP address is 192.168.10.1
  Active virtual MAC address is 0000.0C07.AC01
    Local virtual MAC address is 0000.0C07.AC01 (v1 default)
  Hello time 3 sec, hold time 10 sec
    Next hello sent in 2.375 secs
  Preemption enabled
  Active router is local
  Standby router is 192.168.10.3
  Priority 120 (configured 120)
  Group name is hsrp-Gig0/0-1 (default)
```

5. HSRP de R2


```
R2-Standby>enable
R2-Standby#show standby
GigabitEthernet0/0 - Group 1
  State is Standby
    11 state changes, last state change 01:02:34
  Virtual IP address is 192.168.10.1
  Active virtual MAC address is 0000.0C07.AC01
    Local virtual MAC address is 0000.0C07.AC01 (v1 default)
  Hello time 3 sec, hold time 10 sec
    Next hello sent in 1.482 secs
  Preemption enabled
  Active router is 192.168.10.2
  Standby router is local
  Priority 100 (default 100)
  Group name is hsrp-Gig0/0-1 (default)
```


6. Estado inicial HSRP

```
R1-Activo#show standby brief
                     P indicates configured to preempt.
                     |
Interface   Grp  Pri P State    Active          Standby         Virtual IP
Gig0/0      1    120 P Active   local           192.168.10.3    192.168.10.1
```

```
R2-Standby#show standby brief
                     P indicates configured to preempt.
                     |
Interface   Grp  Pri P State    Active          Standby         Virtual IP
Gig0/0      1    100 P Standby  192.168.10.2    local           192.168.10.1
```

7. Simulacion con el ping continuo






```
Ping statistics for 192.168.20.10:
    Packets: Sent = 27, Received = 23, Lost = 4 (15% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 6ms, Average = 0ms
```

8. Configuraciones utilizadas

1. Configuración de R1-Activo

```
enable
configure terminal
hostname R1-Activo

interface gigabitEthernet 0/0
ip address 192.168.10.2 255.255.255.0
no shutdown
exit

interface gigabitEthernet 0/1
ip address 10.0.1.1 255.255.255.252
no shutdown
exit
```

```
interface gigabitEthernet 0/0
standby 1 ip 192.168.10.1
standby 1 priority 120
standby 1 preempt
exit

ip route 192.168.20.0 255.255.255.0 10.0.1.2

end
copy running-config startup-config
```

2. Configuración de R2-Standby

```
enable
configure terminal
hostname R2-Standby

interface gigabitEthernet 0/0
ip address 192.168.10.3 255.255.255.0
no shutdown
exit

interface gigabitEthernet 0/1
ip address 10.0.2.1 255.255.255.252
no shutdown
exit

interface gigabitEthernet 0/0
standby 1 ip 192.168.10.1
standby 1 priority 100
standby 1 preempt
exit

ip route 192.168.20.0 255.255.255.0 10.0.2.2

end
copy running-config startup-config
```

3. Configuración de R3-Superior

```
enable
configure terminal
hostname R3-Superior
```

```
interface gigabitEthernet 0/0
ip address 10.0.1.2 255.255.255.252
no shutdown
exit

interface gigabitEthernet 0/1
ip address 10.0.2.2 255.255.255.252
no shutdown
exit

interface gigabitEthernet 0/2
ip address 192.168.20.1 255.255.255.0
no shutdown
exit

ip route 192.168.10.0 255.255.255.0 10.0.1.1
ip route 192.168.10.0 255.255.255.0 10.0.2.1 10

end
copy running-config startup-config
```