DEPLOYMENT & ONBOARDING GUIDE

Nexus ERP Quickstart & Branch Setup Guide

A complete technical deployment walkthrough covering initial tenant provisioning, multi-branch scoping, dual-location inventory bins, and role-based security governance.

CLASSIFICATION	Deployment Architecture	RELEASE VERSION	v2.4.0 (Enterprise)
AUTHOR / TEAM	Nexus Systems Engineering	EFFECTIVE DATE	October 2026
TARGET AUDIENCE	IT Administrators, Operations Directors, Store Managers	STATUS	Official Production Ready

1. System Architecture Overview

Nexus ERP operates on a high-availability cloud architecture designed specifically for multi-branch retail, wholesale distribution, and manufacturing enterprises. All system nodes maintain synchronized stock positions while permitting granular data isolation per operational branch.

When your company workspace is provisioned via the Nexus Customer Portal, your root administrator account is granted global authority across all commercial entities, warehouse facilities, and cashier registers.

Root Tenant Isolation Notice

Each provisioned company operates within an isolated tenant partition with dedicated encryption keys. Ensure all initial store setups are completed under the primary administrator profile before delegating credentials to branch supervisors.

2. Initial Company Profile & Branding Configuration

Before launching retail POS terminals or importing supplier goods, configure your legal entity branding to ensure tax invoices, thermal customer receipts, and financial ledgers carry valid commercial credentials:

Step 1: Navigate to **Settings** → **Company Profile** in the Nexus ERP main sidebar.

Step 2: Enter your registered legal business name, National Identity Card (NIC) or Business Registration (BR) number, and registered operational address.

Step 3: Configure default currency settings to **LKR (Sri Lankan Rupee)**, set standard decimal precision (2 decimal places), and configure tax numbers (VAT/SVAT if registered).

Step 4: Upload high-resolution monochrome receipt logos and specify customer footer disclaimers (e.g., return policies, warranty clauses).

3. Multi-Branch & Store Hierarchy Setup

Nexus ERP structures your organization into hierarchical entities: **Company** → **Branches** → **Locations (Warehouses / Showrooms)** → **POS Registers**. This structure guarantees that cashiers cannot access or alter data belonging to other branches.

Branch Code	Branch Name	Location Type	Default Scope	Cashier Registers
HO-01	Colombo Head Office & Showroom	Showroom + Main Store	Primary Central Hub	3 Terminals
BR-02	Kandy Retail Showroom	Retail Showroom Only	Restricted Branch	2 Terminals
WH-01	Peliyagoda Central Logistics	Bulk Central Warehouse	Logistics & GRN Only	0 (Admin only)
BR-03	Galle Highway Outlet	Retail Showroom Only	Restricted Branch	1 Terminal

4. Dual-Location Inventory Architecture (Showroom vs. Storeroom)

A hallmark capability of Nexus ERP is native dual-location stock segregation within each physical branch. Every retail store is automatically equipped with two distinct inventory buckets:

Front-of-House Showroom: The active retail sales floor inventory available for immediate POS cashier billing.

Back-of-House Storeroom: Secure bulk stock held off the retail floor to safeguard against retail shrinkage and unauthorized removal.

Internal Inter-Bin Transfers: Moving inventory from the storeroom to the retail floor requires an internal transfer voucher (`ITV`), maintaining an unalterable audit ledger of who authorized and received the stock.

> **Preventing Stock Theft with Dual Locations**
>
> By enforcing dual-location stock controls, end-of-day shelf physical stocktakes can be reconciled within minutes without having to recount bulk backroom cartons.

5. Role-Based Access Control (RBAC) & Governance

User permissions must adhere strictly to the principle of least privilege. Nexus ERP enforces predefined operational roles:

User Role	Accessible Interfaces	POS Billing	Price Overrides	Financial Reports
`Super Admin`	All Branches, Settings, Ledgers	Full Access	Full Authority	Unrestricted
`Store Manager`	Assigned Branch & Stock Bins	Full Access	PIN Approval Required	Branch P&L; Only
`POS Cashier`	Assigned Register Terminal Only	Billing Only	Blocked (Manager PIN)	Shift Summary Only
`Inventory Officer`	Goods Receiving & Stock Counts	No Billing	No Pricing Access	Stock Ledger Only
`Auditor`	Read-Only Across All Modules	No Billing	View Only	Complete Ledger Audit

6. Pre-Flight Go-Live Checklist

Prior to initiating commercial trading on your Nexus ERP workspace, verify that all items in the deployment checklist below have been validated:

- [✓] Company legal credentials, BR number, and contact numbers configured in Settings.
- [✓] Operational branches and dual-location stock bins assigned to relevant teams.
- [✓] Cashier staff user accounts created with unique login credentials.
- [✓] Thermal receipt printer and barcode scanner paired and verified with test bills.
- [✓] Opening stock imported via CSV migration or confirmed with physical inventory count.
- [✓] Initial cash drawer float recorded during cashier shift start.