CSE 120 Principles of Operating Systems

Fall 2014

Lecture 5: Synchronization

Geoffrey M. Voelker

Synchronization

- Threads cooperate in multithreaded programs
 - To share resources, access shared data structures
 - » Threads accessing a memory cache in a Web server
 - To coordinate their execution
 - » One thread executes relative to another (recall ping-pong)
- For correctness, we need to control this cooperation
 - Threads interleave executions arbitrarily and at different rates
 - Scheduling is not under program control
- We control cooperation using synchronization
 - Synchronization enables us to restrict the possible interleavings of thread executions
- Discuss in terms of threads, also applies to processes

Shared Resources

We initially focus on coordinating access to shared resources

- Basic problem
 - If two concurrent threads (processes) are accessing a shared variable, and that variable is read/modified/written by those threads, then access to the variable must be controlled to avoid erroneous behavior
- Over the next couple of lectures, we will look at
 - Mechanisms to control access to shared resources
 - » Locks, mutexes, semaphores, monitors, condition variables, etc.
 - Patterns for coordinating accesses to shared resources
 - » Bounded buffer, producer-consumer, etc.

Classic Example

 Suppose we have to implement a function to handle withdrawals from a bank account:

```
withdraw (account, amount) {
    balance = get_balance(account);
    balance = balance - amount;
    put_balance(account, balance);
    return balance;
}
```

- Now suppose that you and your significant other share a bank account with a balance of \$1000.
- Then you each go to separate ATM machines and simultaneously withdraw \$100 from the account.

Example Continued

- We'll represent the situation by creating a separate thread for each person to do the withdrawals
- These threads run on the same bank machine:

```
withdraw (account, amount) {
  balance = get_balance(account);
  balance = balance - amount;
  put_balance(account, balance);
  return balance;
}
```

```
withdraw (account, amount) {
   balance = get_balance(account);
   balance = balance - amount;
   put_balance(account, balance);
   return balance;
}
```

- What's the problem with this implementation?
 - Think about potential schedules of these two threads

Interleaved Schedules

 The problem is that the execution of the two threads can be interleaved:

balance = get_balance(account);
balance = balance - amount;

balance = get_balance(account);
balance = get_balance(account);
balance = balance - amount;
balance = balance - amount;
put_balance(account, balance);

put_balance(account, balance);

- What is the balance of the account now?
- Is the bank happy with our implementation?

Shared Resources

- The problem is that two concurrent threads (or processes) accessed a shared resource (account) without any synchronization
 - Known as a race condition (memorize this buzzword)
- We need mechanisms to control access to these shared resources in the face of concurrency
 - So we can reason about how the program will operate
- Our example was updating a shared bank account
- Also necessary for synchronizing access to any shared data structure
 - Buffers, queues, lists, hash tables, etc.

When Are Resources Stack (T1) Thread 1 Stack (T2) Stack (T2) Stack (T3) Thread 3 Thread 3 Thread 2 Stack (T2) Stack (T3) Thread 3 Thread 3 Thread 3 Thread 2 Stack (T2) Stack (T3) Thread 3 Stack (T3) Thread 3 Thread 3

- Each thread has its own stack
- Never pass/share/store a pointer to a local variable on the stack for thread T1 to another thread T2
- Global variables and static objects are shared
 - Stored in the static data segment, accessible by any thread
- Dynamic objects and other heap objects are shared
 - Allocated from heap with malloc/free or new/delete

PC (T1)

How Interleaved Can It Get?

How contorted can the interleavings be?

- We'll assume that the only atomic operations are instructions (e.g., reads and writes of words)
 - Some architectures don't even give you that!
- We'll assume that a context switch can occur at any time
- We'll assume that you can delay a thread as long as you like as long as it's not delayed forever

```
balance = get_balance(account);

balance = get_balance(account);

balance = balance - amount;

balance = balance - amount;

put_balance(account, balance);

put_balance(account, balance);
```

Mutual Exclusion

- We want to use mutual exclusion to synchronize access to shared resources
 - This allows us to have larger atomic blocks
- Code that uses mutual exclusion to synchronize its execution is called a critical section
 - Only one thread at a time can execute in the critical section
 - All other threads are forced to wait on entry
 - When a thread leaves a critical section, another can enter
 - Example: sharing your bathroom with housemates
- What requirements would you place on a critical section?

Critical Section Requirements

Critical sections have the following requirements:

- 1) Mutual exclusion (mutex)
 - If one thread is in the critical section, then no other is
- 2) Progress
 - If some thread T is not in the critical section, then T cannot prevent some other thread S from entering the critical section
 - A thread in the critical section will eventually leave the critical section
- 3) Bounded waiting (no starvation)
 - If some thread T is waiting on the critical section, then T will eventually enter the critical section
- 4) Performance
 - The overhead of entering and exiting the critical section is small with respect to the work being done within it

About Requirements

There are three kinds of requirements that we'll use

- Safety property: nothing bad happens
 - Mutex
- Liveness property: something good happens
 - Progress, Bounded Waiting
- Performance requirement
 - Performance
- Properties hold for each run, while performance depends on all the runs
 - Rule of thumb: When designing a concurrent algorithm, worry about safety first (but don't forget liveness!).

Mechanisms For Building Critical Sections

- Atomic read/write
 - Can it be done?
- Locks
 - Primitive, minimal semantics, used to build others
- Semaphores
 - Basic, easy to get the hang of, but hard to program with
- Monitors
 - High-level, requires language support, operations implicit
- Messages
 - Simple model of communication and synchronization based on atomic transfer of data across a channel
 - Direct application to distributed systems
 - Messages for synchronization are straightforward (once we see how the others work)

Mutual Exclusion with Atomic Read/Writes: First Try

```
int turn = 1;
```

```
while (true) {
   while (turn != 1);
   critical section
   turn = 2;
   outside of critical section
}
```

```
while (true) {
   while (turn != 2);
   critical section
   turn = 1;
   outside of critical section
}
```

This is called alternation

It satisfies mutex:

- If blue is in the critical section, then turn == 1 and if yellow is in the critical section then turn == 2 (why?)
- $(turn == 1) \equiv (turn != 2)$

It violates progress: the thread could go into an infinite loop outside of the critical section, which will prevent the yellow one from entering.

Mutex with Atomic R/W: Peterson's Algorithm

```
int turn = 1;
bool try1 = false, try2 = false;
```

```
while (true) {
   try1 = true;
   turn = 2;
   while (try2 && turn != 1);
   critical section
   try1 = false;
   outside of critical section
}
```

```
while (true) {
   try2 = true;
   turn = 1;
   while (try1 && turn != 2);
   critical section
   try2 = false;
   outside of critical section
}
```

- This satisfies all the requirements
- Here's why...

Mutex with Atomic R/W: Peterson's Algorithm

```
int turn = 1;
bool try1 = false, try2 = false;
```

```
(blue at 4) \land try1 \land (turn == 1 \lor \neg try2 \lor (try2 \land (yellow at 6 or at 7)) \land (yellow at 8) \land try2 \land (turn == 2 \lor \neg try1 \lor (try1 \land (blur at 2 or at 3)) \dots \Rightarrow (turn == 1 \land turn == 2)
```

Locks

- A lock is an object in memory providing two operations
 - acquire(): to enter a critical section
 - release(): to leave a critical section
- Threads pair calls to acquire() and release()
 - Between acquire()/release(), the thread holds the lock
 - acquire() does not return until any previous holder releases
 - What can happen if the calls are not paired?
- Locks can spin (a spinlock) or block (a mutex)
 - Can break apart Peterson's to implement a spinlock.

Using Locks

```
withdraw (account, amount) {
  acquire(lock);
  balance = get_balance(account);
                                       Critical
  balance = balance - amount:
                                       Section
  put_balance(account, balance);
  release(lock);
  return balance;
```

```
acquire(lock);
balance = get_balance(account);
balance = balance - amount;
```

```
acquire(lock);
```

```
put_balance(account, balance);
release(lock);
```

```
balance = get_balance(account);
balance = balance - amount;
put_balance(account, balance);
release(lock);
```

- What happens when blue tries to acquire the lock?
- Why is the "return" outside the critical section? Is this ok?
- What happens when a third thread calls acquire?

Implementing Locks (1)

How do we implement locks? Here is one attempt:

```
struct lock {
   int held = 0;
}

void acquire (lock) {
   while (lock->held);
   lock->held = 1;
}

void release (lock) {
   lock->held = 0;
}
```

- This is called a spinlock because a thread spins waiting for the lock to be released
- Does this work?

Implementing Locks (2)

 No. Two independent threads may both notice that a lock has been released and thereby acquire it.

```
struct lock {
   int held = 0;
}

void acquire (lock) {
   while (lock->held);
   lock->held = 1;
}

void release (lock) {
   lock->held = 0;
}
```

Implementing Locks (3)

- The problem is that the implementation of locks has critical sections, too
- How do we stop the recursion?
- The implementation of acquire/release must be atomic
 - An atomic operation is one which executes as though it could not be interrupted
 - Code that executes "all or nothing"
- How do we make them atomic?
- Need help from hardware
 - Atomic instructions (e.g., test-and-set)
 - Disable/enable interrupts (prevents context switches)

Atomic Instructions: Test-And-Set

- The semantics of test-and-set are:
 - Record the old value
 - Set the value to indicate available
 - Return the old value
- Hardware executes it atomically!

```
bool test_and_set (bool *flag) {
   bool old = *flag;
   *flag = True;
   return old;
}
```

- When executing test-and-set on "flag"
 - What is value of flag afterwards if it was initially False? True?
 - What is the return result if flag was initially False? True?

Using Test-And-Set

Here is our lock implementation with test-and-set:

```
struct lock {
  int held = 0;
}
void acquire (lock) {
  while (test-and-set(&lock->held));
}
void release (lock) {
  lock->held = 0;
}
```

- When will the while return? What is the value of held?
- What about multiprocessors?

Problems with Spinlocks

- The problem with spinlocks is that they are wasteful
 - If a thread is spinning on a lock, then the thread holding the lock cannot make progress (on a uniprocessor)
- How did the lock holder give up the CPU in the first place?
 - Lock holder calls yield or sleep
 - Involuntary context switch
- Only want to use spinlocks as primitives to build higher-level synchronization constructs

Disabling Interrupts

 Another implementation of acquire/release is to disable interrupts:

```
struct lock {
}
void acquire (lock) {
    disable interrupts;
}
void release (lock) {
    enable interrupts;
}
```

- Note that there is no state associated with the lock
- Can two threads disable interrupts simultaneously?

On Disabling Interrupts


- Disabling interrupts blocks notification of external events that could trigger a context switch (e.g., timer)
 - This is what Nachos uses as its primitive
- In a "real" system, this is only available to the kernel
 - Why?
 - What could user-level programs use instead?
- Disabling interrupts is insufficient on a multiprocessor
 - Back to atomic instructions
- Like spinlocks, only want to disable interrupts to implement higher-level synchronization primitives
 - Don't want interrupts disabled between acquire and release

Summarize Where We Are

- Goal: Use mutual exclusion to protect critical sections of code that access shared resources
- Method: Use locks (spinlocks or disable interrupts)
- Problem: Critical sections can be long

Spinlocks:

- Threads waiting to acquire lock spin in test-and-set loop
- Wastes CPU cycles
- Longer the CS, the longer the spin
- Greater the chance for lock holder to be interrupted



Disabling Interrupts:

- Should not disable interrupts for long periods of time
- Can miss or delay important events (e.g., timer, I/O)

Higher-Level Synchronization

- Spinlocks and disabling interrupts are useful only for very short and simple critical sections
 - Wasteful otherwise
 - These primitives are "primitive" don't do anything besides mutual exclusion
- Need higher-level synchronization primitives that:
 - Block waiters
 - Leave interrupts enabled within the critical section
- All synchronization requires atomicity
- So we'll use our "atomic" locks as primitives to implement them

Implementing Locks (4)

Block waiters, interrupts enabled in critical sections

```
struct lock {
  int held = 0;
  queue Q;
void acquire (lock) {
  Disable interrupts:
  while (lock->held) {
      put current thread on lock Q;
      block current thread:
  lock->held=1:
  Enable interrupts;
```

```
void release (lock) {
    Disable interrupts;
    if (Q) remove waiting thread;
    unblock waiting thread;
    lock->held = 0;
    Enable interrupts;
}
```

```
acquire(lock)

...

Critical section

...

release(lock)

Interrupts Disabled

Interrupts Disabled
```

Next time...

Read Chapter 5.4 − 5.6