CSC/CPE 138

COMPUTER NETWORK FUNDAMENTALS

SACRAMENTO STATE

Lecture 3_2: Transport Layer

California State University, Sacramento
Fall 2024

Slide Courtesy: Computer Networking: A Top-Down Approach, Kurose Ross, 8th Edition

Lecture 3_2: Transport Layer Continued

SACRAMENTO STATE

- TCP Round trip time
- TCP Retransmissions
- TCP Flow Control
- TCP Connection Management
- TCP Congestion Control

TCP segment structure



TCP sequence numbers, ACKs



simple telnet scenario

TCP round trip time, timeout

Q: how to set TCP timeout value?

- longer than RTT, but RTT varies!
- *too short:* premature timeout, unnecessary retransmissions
- *too long:* slow reaction to segment loss

Q: how to estimate RTT?

- `SampleRTT`: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- `SampleRTT` will vary, want estimated RTT "smoother"
  - average several *recent* measurements, not just current `SampleRTT`

TCP round trip time, timeout

```
EstimatedRTT = (1- α)*EstimatedRTT + α*SampleRTT
```

- exponential weighted moving average (EWMA)
- influence of past sample decreases exponentially fast
- typical value: α = 0.125



Sample RTT and Estimated RTT

TCP round trip time, timeout

- timeout interval: **`EstimatedRTT`** plus “safety margin”
  - large variation in **`EstimatedRTT`**: want a larger safety margin

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

estimated RTT (`EstimatedRTT`) “safety margin” (`4*DevRTT`)

- **`DevRTT`**: EWMA of **`SampleRTT`** deviation from **`EstimatedRTT`**:

```
DevRTT = (1-β)*DevRTT + β*|SampleRTT-EstimatedRTT|
```

(typically, β = 0.25)

Sample Question

- Given
  - Estimated RTT = 380msec
  - Deviation RTT = 30 msec
  - Next measured RTT is 350 msec
  - α = 0.125
  - β = 0.25



RTT EXAMPLE DIAGRAM

- Compute
  - Estimated RTT
  - Deviation RTT
  - TCP Timeout

Sample Question- Solution

```
EstimatedRTT    = (1- α)*EstimatedRTT + α*SampleRTT
                =(1 - 0.125)*380+0.125*350 = 376.25

DevRTT          = (1-β)*DevRTT + β*|SampleRTT-EstimatedRTT|
                = (1-0.25)*30 + 0.25* |350-380| = 30

Timeout Interval = EstimatedRTT + 4*DevRTT
                 = 376.25 + 4* 30 = 496.25
```

TCP Sender (simplified)

event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unACKed segment
  - expiration interval: **`TimeOutInterval`**

event: timeout

- retransmit segment that caused timeout
- restart timer

event: ACK received

- if ACK acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are still unACKed segments

TCP: retransmission scenarios



lost ACK scenario



premature timeout

TCP: retransmission scenarios



cumulative ACK covers
for earlier lost ACK

TCP fast retransmit

TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

- likely that unACKed segment lost, so don't wait for timeout



Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?





receiver protocol stack

TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

Application removing data from TCP socket buffers



receiver protocol stack

TCP flow control

- TCP receiver "advertises" free buffer space in **`rwnd`** field in TCP header
  - **`RcvBuffer`** size set via socket options (typical default is 4096 bytes)
  - many operating systems auto-adjust **`RcvBuffer`**
- sender limits amount of unACKed ("in-flight") data to received **`rwnd`**
- guarantees receive buffer will not overflow



TCP receiver-side buffering

TCP flow control

- TCP receiver "advertises" free buffer space in **`rwnd`** field in TCP header
  - **`RcvBuffer`** size set via socket options (typical default is 4096 bytes)
  - many operating systems auto-adjust **`RcvBuffer`**
- sender limits amount of unACKed ("in-flight") data to received **`rwnd`**
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept



TCP segment format

TCP connection management

before exchanging data, sender/receiver "handshake":
- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)




```
Socket clientSocket =
  newSocket("hostname","port number");
```




```
Socket connectionSocket =
  welcomeSocket.accept();
```

Agreeing to establish a connection

2-way handshake:





Q: will 2-way handshake always work in network?

- variable delays
- retransmitted messages (e.g. req_conn(x)) due to message loss
- message reordering
- can't "see" other side

2-way handshake scenarios

SACRAMENTO STATE



No problem!



Problem: half open connection! (no client)



Problem: dup data accepted!

TCP 3-way handshake

Server state

```
serverSocket = socket(AF_INET,SOCK_STREAM)
serverSocket.bind((‘’,serverPort))
serverSocket.listen(1)
connectionSocket, addr = serverSocket.accept()
```

Client state

```
clientSocket = socket(AF_INET, SOCK_STREAM)
```



A human 3-way handshake protocol

Closing a TCP connection

- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Question

- You are developing a reliable transport control protocol and the protocol requires you to establish a connection between a client and a server before they can start communicating. You plan to send a connection request and wait for an acknowledgment to build a connection. Discuss the potential problems you observe in to 2-way connection transport control protocol. Provide diagrams to prove your claim.

- Answer :
  - Problem of half open connection
  - Problem of duplicate data being accepted

Principles of Congestion Control

Congestion:

- informally: "too many sources sending too much data too fast for *network* to handle"
- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!

congestion control: too many senders, sending too fast

flow control: one sender too fast for one receiver

Causes/costs of congestion: scenario 1

Simplest scenario:

- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed



Q: What happens as arrival rate λ_{in} approaches R/2?



maximum per-connection throughput: R/2



large delays as arrival rate λιν approaches capacity

Causes/costs of congestion: scenario 2

- one router, *finite* buffers
- sender retransmits lost, timed-out packet
  - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes *retransmissions* : $\lambda'_{in} \geq \lambda_{in}$



Causes/costs of congestion: scenario 2

Idealization: perfect knowledge

- sender sends only when router buffers available





Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost



Causes/costs of congestion: scenario 2

Idealization: *some* perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet *known* to be lost





Causes/costs of congestion: scenario 2

Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending *two* copies, *both* of which are delivered





Causes/costs of congestion: scenario 2

Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending *two* copies, *both* of which are delivered



"costs" of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
  - decreasing maximum achievable throughput

Causes/costs of congestion: scenario 3

- *four* senders
- *multi-hop* paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in}' increase ?

A: as red λ_{in}' increases, all arriving blue pkts at upper queue are dropped, blue throughput → 0



Causes/costs of congestion: scenario 3





another "cost" of congestion:

- when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!

SACRAMENTO STATE

Causes/costs of congestion: insights

- throughput can never exceed capacity



- delay increases as capacity approached



- loss/retransmission decreases effective throughput



- un-needed duplicates further decreases effective throughput



- upstream transmission capacity / buffering wasted for packets lost downstream



Approaches towards congestion control

End-end congestion control:

- no explicit feedback from network
- congestion *inferred* from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide *direct* feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



TCP congestion control: AIMD

- *approach:* senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase

increase sending rate by 1 maximum segment size every RTT until loss detected

Multiplicative Decrease

cut sending rate in half at each loss event



AIMD sawtooth behavior: *probing* for bandwidth

TCP AIMD: more

Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD – a distributed, asynchronous algorithm – has been shown to:
  - optimize congested flow rates network wide!
  - have desirable stability properties

TCP congestion control: details



TCP sending behavior:

- *roughly:* send `cwnd` bytes, wait RTT for ACKS, then send more bytes

$$\text{TCP rate} \approx \frac{\texttt{cwnd}}{\text{RTT}} \text{ bytes/sec}$$

- TCP sender limits transmission: **`LastByteSent- LastByteAcked ≤ cwnd`**
- `cwnd` is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
  - initially **`cwnd`** = 1 MSS
  - double **`cwnd`** every RTT
  - done by incrementing **`cwnd`** for every ACK received
- *summary:* initial rate is slow, but ramps up exponentially fast



TCP: from slow start to congestion avoidance

SACRAMENTO STATE

Q: when should the exponential increase switch to linear?

A: when **`cwnd`** gets to 1/2 of its value before timeout.

Implementation:

- variable **`ssthresh`**
- on loss event, **`ssthresh`** is set to 1/2 of **`cwnd`** just before loss event



TCP and the congested “bottleneck link”

- TCP increase TCP’s sending rate until packet loss occurs at some router’s output: the *bottleneck link*



TCP and the congested “bottleneck link”

- TCP increase TCP’s sending rate until packet loss occurs at some router’s output: the *bottleneck link*
- understanding congestion: useful to focus on congested bottleneck link

insight: increasing TCP sending rate will *not* increase end-end throughout with congested bottleneck



insight: increasing TCP sending rate *will* increase measured RTT

Goal: *“keep the end-end pipe just full, but not fuller”*

Delay-based TCP congestion control

Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



$$\text{measured throughput} = \frac{\text{\# bytes sent in last RTT interval}}{RTT_{measured}}$$

Delay-based approach:

- RTT_{min} - minimum observed RTT (uncongested path)
- uncongested throughput with congestion window `cwnd` is cwnd/RTT_{min}

```
if measured throughput "very close" to uncongested throughput
    increase cwnd linearly          /* since path not congested */
else if measured throughput "far below" uncongested throughout
    decrease cwnd linearly          /* since path is congested */
```

Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full… ") while keeping delay low ("…but not fuller")
- a number of deployed TCPs take a delay-based approach
  - BBR deployed on Google's (internal) backbone network

Explicit congestion notification (ECN)

TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked *by network router* to indicate congestion
  - *policy* to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



Lecture 3-2 Summary

- TCP Round trip time
- TCP Retransmissions
- TCP Flow Control
- TCP Connection Management
- TCP Congestion Control

End of Lecture 3_2