Transport Layer:

- TCP, UDP
- SOCKETS Library
- UDP implements the minimal requirement
 - Support unique port# multiple channels for communication
- TCP reliable connection-oriented transport layer
 - Reliability (sliding window protocols)
 - Flow control send data at the rate suitable for the receiver.
 - Connection management
 - Internet supports datagram, best effort transmission
 - Table based end-to-end connection scenario
 - 3-way handshaking for connection establishment
 - Termination of half-connection (two-way handshake)
 - Congestion Management


- Congestion Management
 - What are the principles of congestion Management
 - How does TCP implement it.

- Transport Layer (TCP and UDP) is implemented at the end nodes only
 - Network layer (routers) is not involved

Principles of congestion control


congestion:

- informally: "too many sources sending too much data too fast for *network* to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- ACK takes longer time to arrive onset of congestion
- Eventually ACK times out Congestion!




Transport Layer 3-5


- one router, finite buffers
- sender retransmission of timed-out packet
 - application-layer input = application-layer output: λ_{in} = λ_{out}
 - transport-layer input includes retransmissions : $\lambda_{in} \ge \lambda_{in}$



idealization: perfect knowledge

sender sends only when router buffers available






Idealization: known loss


packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost



Idealization: known loss packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost






Realistic: duplicates


- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered




"costs" of congestion:


- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput


- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in} increase?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput $\rightarrow 0$







another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

- Congestion Control Mechanism (end-nodes only)
- Congestion occurs when send-rates is too high and packets overflow at the router.
- Sender Receiver (acknowledgements ACKs)
- IF ACK does not come what are the reasons?
 - Packet lost because
 - Router buffer overflows (congestion, too much traffic)
 - Misrouted. (routing protocol error)
 - (yash) packet corrupted because of noise. Checksum does not match – receiver doesnot send ACK
- Assume that loss is MAINLY because of congestion and mostly not because of error/misrouting
- NO ACK → CONGESTION
- CONGESTION → SLOW DOWN


- Congestion -> slow down -> underutilization
- If we receive ACK, we assume that network has spare capacity → speed up.

- ACK arrive → increase rate
- ACK loss → decrease rate
- -----
- Controlling the rate by controlling the window size.
- W inc → send rate inc.


TCP congestion control: additive increase multiplicative decrease

- approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by I MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth



TCP Congestion Control: details



sender limits transmission:

$$\begin{array}{ccc} \text{LastByteSent-} & \leq & \text{cwnd} \\ \text{LastByteAcked} & & \end{array}$$

 cwnd is dynamic, function of perceived network congestion


TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast



TCP: detecting, reacting to loss


- loss indicated by timeout:
 - cwnd set to I MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)

TCP: switching from slow start to CA

14.

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.




Implementation:

- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/


Summary: TCP Congestion Control



TCP throughput

- avg. TCP thruput as function of window size, RTT?
 - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is 3/4 W
 - avg. thruput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



TCP Futures: TCP over "long, fat pipes"


- example: I500 byte segments, I00ms RTT, wantI0 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L = $2 \cdot 10^{-10}$ a very small loss rate!
- new versions of TCP for high-speed

TCP Fairness


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

two competing sessions:

- additive increase gives slope of I, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for I TCP, gets rate R/I0
 - new app asks for 11 TCPs, gets R/2

Explicit Congestion Notification (ECN)

network-assisted congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
- congestion indication carried to receiving host
- receiver (seeing congestion indication in IP datagram)) sets ECE bit on receiver-to-sender ACK segment to notify sender of congestion

