INSTRUCTOR'S DISCUSSION GUIDE

Topic 7: Internet Protocol (IP) Addressing and Subnet Basics

Understand IPv4 address structure, decimal octets, classes, private ranges, subnet boundaries, and IPv6 fundamentals.

Curriculum: Networking 1 **Excluded:** Title (Slide 1), Objectives (Slide 2), and Summary (Final Slide) **Total Discussion Units:** 15 Slides

Slide 3 of 18

What Is an Internet Protocol Address?

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

An Internet Protocol (IP) address is a unique logical Layer 3 numerical identifier assigned to every device on a network. While a physical Media Access Control (MAC) address identifies hardware on a single local cable, an IP address is hierarchical and location-based, enabling routers to direct data packets across interconnected local, enterprise, and global networks.

- Logical identity: Assigned by network configuration, unlike a permanent physical Media Access Control (MAC) address.
- Hierarchical routing: Routers use the network portion to direct traffic across interconnected networks.
- Octet ranges: Each of the four decimal octets ranges from 0 to 255 (representing 8 binary bits each).

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Logical identity: Assigned by network configuration, unlike a permanent physical MAC address.
- Hierarchical routing: Routers use the network portion to direct traffic across interconnected networks.
- Octet ranges: Each of the four decimal octets ranges from 0 to 255 (representing 8 binary bits each).

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of what is an internet protocol address?.

Key Takeaway: An Internet Protocol (IP) address is a unique logical Layer 3 numerical identifier assigned to every device on a network. While a physical Media Access Control (MAC) address identifies hardware on a single local cable, an IP address is hierarchical and location-based, enabling routers to direct data packets across interconnected local, enterprise, and global networks.

Slide 4 of 18

Two Parts of an IP Address: Network and Host

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

Every Internet Protocol (IP) address is divided into two parts: the network portion identifies the network, and the host portion identifies the specific device.

- Network portion: Identifies the specific network or subnet.
- Host portion: Identifies the individual device on that network.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Network portion: Identifies the specific network or subnet.
- Host portion: Identifies the individual device on that network.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of two parts of an ip address: network and host.

Key Takeaway: Every Internet Protocol (IP) address is divided into two parts: the network portion identifies the network, and the host portion identifies the specific device.

Slide 5 of 18

What Is a Subnet and Why Do We Subnet?

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

A subnet is a smaller, organized group of computers within a network, such as separating Students, Staff, and Guest Wi-Fi.

- Organization: Divides a large network into manageable, logical departments.
- Traffic control: Keeps broadcast messages inside one group so they do not slow down other computers.
- Security boundaries: Devices in different subnets cannot talk directly; they must pass through a router or firewall where security rules apply.
- Address efficiency: Allows network administrators to assign addresses without wasting large blocks.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌞 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Organization: Divides a large network into manageable, logical departments.
- Traffic control: Keeps broadcast messages inside one group so they do not slow down other computers.
- Security boundaries: Devices in different subnets cannot talk directly; they must pass through a router or firewall where security rules apply.
- Address efficiency: Allows network administrators to assign addresses without wasting large blocks.
- Subnetting is a logical division created by the Subnet Mask; it does not require buying new physical switches.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of what is a subnet and why do we subnet?.

Key Takeaway: A subnet is a smaller, organized group of computers within a network, such as separating Students, Staff, and Guest Wi-Fi.

Slide 6 of 18

The Subnet Mask: The Dividing Boundary

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

A subnet mask is a 32-bit filter that marks the boundary between network bits and host bits using consecutive ones and zeros.

- Network boundary: Consecutive binary 1s identify the network portion; consecutive binary 0s identify the host portion.
- Dotted-decimal format: A mask with 24 ones is written as 255.255.255.0.
- Classless Inter-Domain Routing (CIDR) prefix notation: Counting the 24 network ones is written shorthand as /24 (pronounced 'slash twenty-four').
- Universal /24 standard: The most common mask in small offices, schools, and homes, providing up to 254 usable computers.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Network boundary: Consecutive binary 1s identify the network portion; consecutive binary 0s identify the host portion.
- Dotted-decimal format: A mask with 24 ones is written as 255.255.255.0.
- CIDR prefix notation: Counting the 24 network ones is written shorthand as /24 (pronounced 'slash twenty-four').
- Universal /24 standard: The most common mask in small offices, schools, and homes, providing up to 254 usable computers.
- A subnet mask must always have contiguous 1s followed by contiguous 0s.
- A mask like 255.255.0.255 is invalid.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of the subnet mask: the dividing boundary.

Key Takeaway: A subnet mask is a 32-bit filter that marks the boundary between network bits and host bits using consecutive ones and zeros.

Slide 7 of 18

How an Address and Mask Identify the Network

SIMULATION

📖 WHAT TO READ & DISPLAY ON SCREEN

A bitwise AND combines address bits with subnet-mask bits to obtain the network address. Mask ones preserve network bits, while mask zeros clear the host portion.

Interactive Demonstration: `bitwiseDemo` — Use on-screen controls to step through or demonstrate the concept visually.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

Understand IPv4 address structure, decimal octets, classes, private ranges, subnet boundaries, and IPv6 fundamentals.

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Display address bits, mask bits, and the actual bitwise network result.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of how an address and mask identify the network.

Key Takeaway: A bitwise AND combines address bits with subnet-mask bits to obtain the network address. Mask ones preserve network bits, while mask zeros clear the host portion.

Slide 8 of 18

Interpreting an IPv4 Host Configuration

WALKTHROUGH

📖 WHAT TO READ & DISPLAY ON SCREEN

A host configuration combines an address, network boundary, and optional service or routing settings. Understanding each field prevents confusing name resolution with local or remote delivery.

- In 192.168.10.25/24, the prefix marks 24 network bits and eight host bits. The mask is 255.255.255.0.
- The gateway 192.168.10.1 is another usable address on that local subnet and handles destinations without a more specific route.
- A Domain Name System (DNS) resolver maps names to records. It may equal the gateway when that gateway forwards DNS, but this is not required.
- An octet uses weights 128, 64, 32, 16, 8, 4, 2, 1; adding enabled weights converts eight bits into a decimal value.
- Private addresses are not globally routed; loopback, link-local, shared carrier, documentation, multicast, and reserved ranges also need separate treatment.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- In 192.168.10.25/24, the prefix marks 24 network bits and eight host bits.
- The mask is 255.255.255.0.
- The gateway 192.168.10.1 is another usable address on that local subnet and handles destinations without a more specific route.
- A DNS resolver maps names to records.
- It may equal the gateway when that gateway forwards DNS, but this is not required.
- An octet uses weights 128, 64, 32, 16, 8, 4, 2, 1; adding enabled weights converts eight bits into a decimal value.
- Private addresses are not globally routed; loopback, link-local, shared carrier, documentation, multicast, and reserved ranges also need separate treatment.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of interpreting an ipv4 host configuration.

Key Takeaway: A host configuration combines an address, network boundary, and optional service or routing settings. Understanding each field prevents confusing name resolution with local or remote delivery.

Slide 9 of 18

Inside Every Subnet: Network, Broadcast, and Host IPs

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

Every subnet is simply an Internet Protocol (IP) address group with a starting address, an ending address, and usable host addresses in between.

- Network ID (The First Internet Protocol (IP)): The very first address (e.g., 192.168.1.0). It names the entire subnet and cannot be assigned to a computer.
- Broadcast Internet Protocol (IP) (The Last IP): The very last address (e.g., 192.168.1.255). It sends messages to every device in the subnet at once.
- Usable Host IPs (The Middle Numbers): All addresses between the first and last (e.g., 192.168.1.1 through 192.168.1.254). Assigned to PCs, phones, and printers.
- Total Minus 2 Rule: Because the first (Network ID) and last (Broadcast Internet Protocol (IP)) are reserved, usable host count is always Total IPs − 2.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌞 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Network ID (The First IP): The very first address (e.g., 192.168.1.0).
- It names the entire subnet and cannot be assigned to a computer.
- Broadcast IP (The Last IP): The very last address (e.g., 192.168.1.255).
- It sends messages to every device in the subnet at once.
- Usable Host IPs (The Middle Numbers): All addresses between the first and last (e.g., 192.168.1.1 through 192.168.1.254).
- Assigned to PCs, phones, and printers.
- Total Minus 2 Rule: Because the first (Network ID) and last (Broadcast IP) are reserved, usable host count is always Total IPs − 2.
- In a /24 subnet with 256 total addresses, subtracting 2 gives exactly 254 usable host addresses.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of inside every subnet: network, broadcast, and host ips.

Key Takeaway: Every subnet is simply an Internet Protocol (IP) address group with a starting address, an ending address, and usable host addresses in between.

Slide 10 of 18

Subnet Calculator Demo

SIMULATION

📖 WHAT TO READ & DISPLAY ON SCREEN

The address and prefix determine a subnet's mask, boundary, and address count. Network, broadcast, and usable-host conventions must then be applied appropriately.

Interactive Demonstration: subnet — Use on-screen controls to step through or demonstrate the concept visually.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Real calculation • any valid IPv4 address and prefix, binary boundary, guided steps, and explained calculations.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of subnet calculator demo.

Key Takeaway: The address and prefix determine a subnet's mask, boundary, and address count. Network, broadcast, and usable-host conventions must then be applied appropriately.

Slide 11 of 18

CIDR Prefix Notation (/24 Shortcut)

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

Classless Inter-Domain Routing (CIDR) prefix notation states the number of consecutive network ones in the mask using a slash (such as /24), replacing cumbersome dotted-decimal masks.

- /24 means 24 ones in the mask: 11111111.11111111.11111111.00000000, which is 255.255.255.0.
- /16 means 16 ones (255.255.0.0), while /8 means 8 ones (255.0.0.0).
- Remaining host bits: subtracting the prefix from 32 gives the host bits (for /24, 32 − 24 = 8 bits, or 254 usable hosts).

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- /24 means 24 ones in the mask: 11111111.11111111.11111111.00000000, which is 255.255.255.0.
- /16 means 16 ones (255.255.0.0), while /8 means 8 ones (255.0.0.0).
- Remaining host bits: subtracting the prefix from 32 gives the host bits (for /24, 32 − 24 = 8 bits, or 254 usable hosts).

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of cidr prefix notation (/24 shortcut).

Key Takeaway: Classless Inter-Domain Routing (CIDR) prefix notation states the number of consecutive network ones in the mask using a slash (such as /24), replacing cumbersome dotted-decimal masks.

Slide 12 of 18

Example: read one classroom address

EXAMPLE

📖 WHAT TO READ & DISPLAY ON SCREEN

An address and prefix place a host within a logical subnet. The same configuration also identifies a gateway for appropriate remote destinations.

- The /24 prefix places this host in 192.168.10.0/24. Ordinary usable host addresses run from .1 through .254.
- A peer at 192.168.10.40 is local; a destination outside this subnet needs an appropriate route, often through the configured gateway.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌞 REAL-WORLD ANALOGY / INTUITION

> *Understand IPv4 address structure, decimal octets, classes, private ranges, subnet boundaries, and IPv6 fundamentals.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- The /24 prefix places this host in 192.168.10.0/24.
- Ordinary usable host addresses run from .1 through .254.
- A peer at 192.168.10.40 is local; a destination outside this subnet needs an appropriate route, often through the configured gateway.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of example: read one classroom address.

Key Takeaway: An address and prefix place a host within a logical subnet. The same configuration also identifies a gateway for appropriate remote destinations.

Slide 13 of 18

Classful History vs Modern Subnetting

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

Modern Classless Inter-Domain Routing (CIDR) eliminates rigid historical classes, allowing any Internet Protocol (IP) block to use any prefix size to fit the exact needs of a network.

- Classful legacy (1981): 10.0.0.0 was locked into Class A (/8), allocating 16 million hosts to one network with severe waste.
- Modern CIDR (1993): Classless Inter-Domain Routing allows any prefix to be used with any Internet Protocol (IP) address.
- 10.0.0.0/24 is normal: an administrator can carve 10.0.0.0 into small /24 subnets (254 hosts per classroom) with a 255.255.255.0 mask.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Classful legacy (1981): 10.0.0.0 was locked into Class A (/8), allocating 16 million hosts to one network with severe waste.
- Modern CIDR (1993): Classless Inter-Domain Routing allows any prefix to be used with any IP address.
- 10.0.0.0/24 is normal: an administrator can carve 10.0.0.0 into small /24 subnets (254 hosts per classroom) with a 255.255.255.0 mask.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of classful history vs modern subnetting.

Key Takeaway: Modern Classless Inter-Domain Routing (CIDR) eliminates rigid historical classes, allowing any Internet Protocol (IP) block to use any prefix size to fit the exact needs of a network.

Slide 14 of 18

Three Private IPv4 Address Ranges

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

Request for Comments (RFC) 1918 reserves three private address blocks for local networks: 10.0.0.0/8, 172.16.0.0/12, and 192.168.0.0/16. These addresses are free to use on local LANs and are not routed on the public Internet.

- 10.0.0.0/8: 10.0.0.0 through 10.255.255.255.
- 172.16.0.0/12: 172.16.0.0 through 172.31.255.255.
- 192.168.0.0/16: 192.168.0.0 through 192.168.255.255.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- 10.0.0.0/8: 10.0.0.0 through 10.255.255.255.
- 172.16.0.0/12: 172.16.0.0 through 172.31.255.255.
- 192.168.0.0/16: 192.168.0.0 through 192.168.255.255.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of three private ipv4 address ranges.

Key Takeaway: Request for Comments (RFC) 1918 reserves three private address blocks for local networks: 10.0.0.0/8, 172.16.0.0/12, and 192.168.0.0/16. These addresses are free to use on local LANs and are not routed on the public Internet.

Slide 15 of 18

Eight Special-Purpose IPv4 Ranges

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

Several address ranges have special uses such as loopback (127.0.0.1), link-local APIPA (169.254.0.0/16), and documentation. An address outside the private ranges is not automatically a globally reachable host address.

- 127.0.0.0/8: loopback.
- 169.254.0.0/16: Internet Protocol version 4 (IPv4) link-local.
- 100.64.0.0/10: shared carrier-grade Network Address Translation (NAT) space.
- 192.0.2.0/24: documentation.
- 198.51.100.0/24: documentation.
- 203.0.113.0/24: documentation.
- 224.0.0.0/4: multicast.
- 240.0.0.0/4: reserved space, including limited broadcast at 255.255.255.255.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- 127.0.0.0/8: loopback.
- 169.254.0.0/16: IPv4 link-local.
- 100.64.0.0/10: shared carrier-grade NAT space.
- 192.0.2.0/24: documentation.
- 198.51.100.0/24: documentation.
- 203.0.113.0/24: documentation.
- 224.0.0.0/4: multicast.
- 240.0.0.0/4: reserved space, including limited broadcast at 255.255.255.255.
- This is not an exhaustive registry.
- A non-private address is not automatically ordinary globally routable unicast.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of eight special-purpose ipv4 ranges.

Key Takeaway: Several address ranges have special uses such as loopback (127.0.0.1), link-local APIPA (169.254.0.0/16), and documentation. An address outside the private ranges is not automatically a globally reachable host address.

Slide 16 of 18

Introduction to IPv6 Basics

CONCEPT

📖 WHAT TO READ & DISPLAY ON SCREEN

Internet Protocol version 6 (IPv6) solves Internet Protocol version 4 (IPv4) address exhaustion by providing 128-bit addresses, offering practically unlimited addresses for modern global devices.

- Why Internet Protocol version 6 (IPv6) is needed: Internet Protocol version 4 (IPv4) provides only 4.3 billion addresses, which are now completely exhausted by billions of smartphones, computers, and cloud servers.
- 128-Bit Structure: Internet Protocol version 6 (IPv6) uses 128 binary bits written as eight groups of four hexadecimal digits separated by colons (e.g., 2001:0db8:85a3:0000:0000:8a2e:0370:7334).
- Zero Compression Rule (::): Consecutive groups of zeros can be abbreviated with a double colon (::) once in an address (e.g., 2001:db8::1).
- Address Types Without Broadcast: Internet Protocol version 6 (IPv6) uses Unicast (one-to-one), Multicast (one-to-many), and Anycast (one-to-nearest). IPv6 eliminates noisy broadcast messages entirely.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌞 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- Why IPv6 is needed: IPv4 provides only 4.3 billion addresses, which are now completely exhausted by billions of smartphones, computers, and cloud servers.
- 128-Bit Structure: IPv6 uses 128 binary bits written as eight groups of four hexadecimal digits separated by colons (e.g., 2001:0db8:85a3:0000:0000:8a2e:0370:7334).
- Zero Compression Rule (::): Consecutive groups of zeros can be abbreviated with a double colon (::) once in an address (e.g., 2001:db8::1).
- Address Types Without Broadcast: IPv6 uses Unicast (one-to-one), Multicast (one-to-many), and Anycast (one-to-nearest).
- IPv6 eliminates noisy broadcast messages entirely.
- IPv6 provides 340 undecillion addresses (3.4 × 10^38), ensuring every device on Earth can have its own permanent, globally unique IP address without needing NAT.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of introduction to ipv6 basics.

Key Takeaway: Internet Protocol version 6 (IPv6) solves Internet Protocol version 4 (IPv4) address exhaustion by providing 128-bit addresses, offering practically unlimited addresses for modern global devices.

Slide 17 of 18

Subnet Sizing and Address Planning

APPLICATION

📖 WHAT TO READ & DISPLAY ON SCREEN

Determine the required host capacity before selecting a subnet prefix. Sizing must account for gateway routers, reserved addresses, and planned future growth.

- /28 offers only 14 ordinary usable addresses, which is insufficient.
- /27 gives 30 usable addresses: 28 PCs, 1 router, 1 spare.
- Allocate addresses sequentially and document the plan.

💡 BRIEF EXPLANATION AFTER READING (TEACHER'S DISCUSSION NOTES)

🌟 REAL-WORLD ANALOGY / INTUITION

> *A classroom needs addresses for 28 PCs plus a router interface.*

🗣️ HOW TO EXPLAIN IT (TALKING POINTS)

- /28 offers only 14 ordinary usable addresses, which is insufficient.
- /27 gives 30 usable addresses: 28 PCs, 1 router, 1 spare.
- Allocate addresses sequentially and document the plan.

❓ QUICK CHECK FOR UNDERSTANDING (ASK THE CLASS)

Teacher Asks: "Ask the class: Why is this concept essential when setting up or troubleshooting a modern network?"

Expected Answer / Guidance: Encourages learners to explain the functional role and real-world impact of subnet sizing and address planning.

Key Takeaway: Determine the required host capacity before selecting a subnet prefix. Sizing must account for gateway routers, reserved addresses, and planned future growth.