```
Install SonarQube on Ubuntu Community Edition
     Prerequisites
 3
    A fresh Ubuntu 22.04 dedicated server
    A user with sudo privileges
4
     Java 11 or 17 installed
6
     we have used cloud server with the configuration of 2vCPU, 4GB RAM, 80GB SSD.
     It should have at least 2GB of RAM 1 CPU core and 30GB free space.
 7
8
9
     Step 1: Update the System
10
     First, ensure your system is up-to-date:
11
12
     sudo apt update
13
     sudo apt upgrade -y
14
     Step 2: Install Java
15
16
17
     sudo apt install openjdk-17-jdk -y
18
     Verify the installation:
19
20
     java -version
21
22
     Step 3: Install SonarQube
23
     Download the latest SonarQube version:
24
25
     wget https://binaries.sonarsource.com/Distribution/sonarqube/sonarqube-
     10.5.1.90531.zip
26
     Extract the SonarQube package:
27
28
     unzip sonarqube-10.5.1.90531.zip
29
     sudo mv sonarqube-10.5.1.90531 /opt/sonarqube
30
31
     Create a SonarQube user:
32
33
     sudo adduser --system --no-create-home --group --disabled-login sonarqube
34
35
     Change ownership of the SonarQube directory:
36
37
     sudo chown -R sonarqube:sonarqube /opt/sonarqube
38
39
     Step 5: Create a Systemd Service File
40
     Create a new service file for SonarQube:
41
42
     sudo nano /etc/systemd/system/sonarqube.service
43
     Add the following content:
44
45
     [Unit]
46
     Description=SonarQube service
47
     After=syslog.target network.target
48
49
     [Service]
50
     Type=forking
51
52
     ExecStart=/opt/sonarqube/bin/linux-x86-64/sonar.sh start
53
     ExecStop=/opt/sonarqube/bin/linux-x86-64/sonar.sh stop
54
55
     User=sonarqube
56
     Group=sonarqube
57
    Restart=always
58
59
     LimitNOFILE=65536
60
    LimitNPROC=4096
61
62
     [Install]
63
     WantedBy=multi-user.target
64
     Reload the systemd daemon and start SonarQube:
65
66
     sudo systemctl daemon-reload
67
     sudo systemctl start sonarqube
68
     sudo systemctl enable sonarqube
69
     sudo systemctl status sonarqube
70
     Step 9: Access SonarQube
     Open your web browser and go to <a href="https://your_domain_or_ip">https://your_domain_or_ip</a>.
     You should see the SonarQube login page. The default credentials are:
```

73
74 Username: admin
75 Password: admin
76 Upon first login, you will be prompted to change the default password.
77
78
79