# CodeWarrior® C Compilers Reference



Because of last-minute changes to CodeWarrior, some of the information in this manual may be inaccurate. Please read the Release Notes on the CodeWarrior CD for the latest up-to-date information.

Revised: 99/01/24 map

Metrowerks CodeWarrior copyright ©1993–1999 by Metrowerks Inc. and its licensors. All rights reserved.

Documentation stored on the compact disk(s) may be printed by licensee for personal use. Except for the foregoing, no part of this documentation may be reproduced or transmitted in any form by any means, electronic or mechanical, including photocopying, recording, or any information storage and retrieval system, without permission in writing from Metrowerks Inc.

Metrowerks, the Metrowerks logo, CodeWarrior, and Software at Work are registered trademarks of Metrowerks Inc. PowerPlant and PowerPlant Constructor are trademarks of Metrowerks Inc.

All other trademarks and registered trademarks are the property of their respective owners.

ALL SOFTWARE AND DOCUMENTATION ON THE COMPACT DISK(S) ARE SUBJECT TO THE LICENSE AGREEMENT IN THE CD BOOKLET.

#### **How to Contact Metrowerks:**

**U.S.A. and international** Metrowerks Corporation

9801 Metric, Suite 100 Austin, TX 78758

U.S.A.

**Canada** Metrowerks Inc.

1500 du College, Suite 300 Ville St-Laurent, QC

Canada H4L 5G6

**Ordering** Voice: (800) 377–5416

Fax: (512) 873–4901

World Wide Web http://www.metrowerks.com

**Registration information** register@metrowerks.com

**Technical support** cw\_support@metrowerks.com

Sales, marketing, & licensing sales@metrowerks.com

CompuServe Go: Metrowerks

# **Table of Contents**

1	Introduction		11
	What's in this Reference?		11
	Read the Release Notes!		
	What's New		
	CodeWarrior Year 2000 Compliance		
	Conventions Used in This Reference		
2	Setting C/C++ Compiler Options		15
	Setting C Compiler Options Overview		15
	C/C++ Language Panel		
	C/C++ Warnings Panel		
	Treat All Warnings as Errors		20
	Illegal Pragmas		
	Empty Declarations		
	Possible Errors		
	Unused Variables		22
	Unused Arguments		23
	Extra Commas		
	Extended Error Checking		24
	Hidden Virtual Functions		
	Implicit Arithmetic Conversions		26
	Non-Inlined Functions		
	Inconsistent Use of 'class' and 'struct' Keywords		27
3	C Compiler		29
	C Compiler Overview		29
	The CodeWarrior Implementation of C		30
	Identifiers		30
	Include Files		30
	Prefix Files		32
	Sizeof() Operator		32
	Volatile Variables		
	Enumerated Types		33
	Extensions to ANSI/ISO C		

ANSI Strict		. 37
Using the wchar_t Type		. 38
C++ Style Comments		. 38
Unnamed Arguments in Function Definitions		. 38
A # not Followed by Argument in a Macro		38
Using an Identifier After #endif		39
Using Typecasted Pointers as Ivalues		40
Declaring Variables By Address		40
ANSI Keywords Only		41
Expand Trigraphs		42
Character Constants as Integer Values		42
Inlining		43
Multibyte Strings and Comments		44
Pool Strings		45
Reusing Strings		46
Require Function Prototypes		47
Map Newlines to CR		49
Relaxed Pointer Type Rules		50
Use Unsigned Chars		50
Using 64-bit Integers		51
Converting Pointers to Types of the Same Size		. 51
Getting Alignment and Type Information at Compile-Time	. ڊ	. 52
Arrays of Zero Length in Structures		. 52
Intrinsic Functions for Bit Rotation		. 53
The "D" Constant Suffix		. 53
C++ Compiler		55
C++ Compiler Overview		
CodeWarrior Implementation of $C++\dots\dots$		
Implicit Return Statement for main()		
Keyword Ordering		
Additional Keywords		
Conversions in the Conditional Operator		
Default Arguments in Member Functions		
Local Class Declarations with Inline Functions		. 59

Copying and Constructing Class Objects				59
Checking for Resources To Initialize Static Data				60
Calling an Inherited Member Function				61
Unsupported Extensions				64
Controlling the C++ Compiler				64
Using the C++ Compiler Always				64
Controlling ARM Conformance				65
Controlling Exception Handling				66
Controlling RTTI				66
Using the bool Type				67
Controlling C++ Extensions				67
Working With C++ Exceptions				68
Working With RTTI				69
Using the dynamic_cast Operator				69
Using the typeid Operator				71
Working With Templates				72
Declaring and Defining Templates				73
Instantiating a Template				76
5 C++ and Embedded Systems				79
C++ and Embedded Systems Overview				79
Activating EC++				
Differences Between ANSI/ISO C++ and EC++.				
Templates				80
Libraries				
File Operations				
Localization				
Exception Handling				
Other Language Features				
Meeting EC++ Specifications With CodeWarrior				
Language Related Issues				81
Library Related Issues				
Strategies for Smaller Code Size in C++				82
Strategies for Smaner Code Size in C++	 •	•		
Size Optimizations				

Virtual Functions								84
Runtime Type Identification .								85
Exception Handling								
Operator New								
Multiple Inheritance								86
Virtual Inheritance								86
Stream-Based Classes								86
Alternative Class Libraries								87
6 Pragmas and Symbols								89
Pragmas and Symbols Overview								
Pragmas								
Pragma Syntax								
Pragma Scope								
a6frames								
align								
align_array_members								
always_inline								
ANSI_strict								
arg_dep_lookup								
ARM_conform								
auto_inline								
bool								
check_header_flags								100
code_seg								
code68020								101
code68881								102
cplusplus								103
cpp_extensions								103
d0_pointers								
data_seg								106
def_inherited							•	106
defer_codegen							•	107
define_section							•	108
dinat dasturation								110

direct_to_som
disable_registers
dollar_identifiers
dont_inline
dont_reuse_strings
ecplusplus
EIPC_EIPSW
enumsalwaysint
exceptions
export
extended_errorcheck
far_code, near_code, smart_code
far_data
far_strings
far_vtables
faster_pch_gen
float_constants
force_active
fourbyteints
fp_contract
fp_pilot_traps
function
global_optimizer, optimization_level
[EEEdoubles
gnore_oldstyle
Import
init_seg
nline_depth
inline_intrinsics
internal
interrupt
k63d
k63d_calls
ib_export
longlong

longlong_enums									. 139
longlong_prepval									. 139
macsbug, oldstyle_symbols									. 140
mark									. 141
message									. 142
microsoft_exceptions									. 142
microsoft_RTTI									. 142
mmx									. 143
mmx_call									. 143
mpwc									. 144
mpwc_newline									. 145
mpwc_relax									. 146
no_register_coloring									. 147
no_static_dtors									. 148
once									. 149
only_std_keywords									. 149
opt_common_subs									. 150
opt_dead_assignments									. 150
opt_dead_code									. 151
opt_lifetimes									. 151
opt_loop_invariants									. 152
opt_propagation									. 152
opt_strength_reduction									. 153
opt_unroll_loops									. 153
opt_vectorize_loops									. 154
optimization_level									. 154
optimize_for_size									. 154
oldstyle_symbols									. 155
pack									. 155
parameter									. 156
pcrelstrings									. 157
peephole									. 158
pointers_in_A0, pointers_in_	_D	0							. 159
pool_data									. 160
nool strings									161

pop, push	. 161
precompile_target	. 162
profile	. 163
readonly_strings	. 164
register_coloring	. 165
require_prototypes	. 165
RTTI	. 166
scheduling	. 166
section	. 167
segment	. 174
side_effects	. 175
simple_prepdump	. 176
SOMCallOptimization	. 176
SOMCallStyle	. 177
SOMCheckEnvironment	. 177
SOMClassVersion	. 179
SOMMetaClass	. 180
SOMReleaseOrder	. 180
stack_cleanup	. 181
static_inlines	. 182
suppress_init_code	. 182
sym	. 183
syspath_once	. 184
oc_data	. 184
rigraphs	. 185
raceback	. 185
ınsigned_char	. 186
unused	. 187
use_fp_instructions	. 187
use_frame	. 188
use_mask_registers....................	
warn_emptydecl	. 189
warning_errors	
warn_extracomma	
warn hidevirtual	

Index	211
	Checking Options
	Metrowerks Predefined Symbols
	ANSI Predefined Symbols
	Predefined Symbols
	wchar_type
	warning
	warn_unusedvar
	warn_unusedarg
	warn_structclass
	warn_possunwant
	warn_padding
	warn_notinlined
	warn_implicitconv
	warn_illpragma



## Introduction

This manual describes the CodeWarrior C and C++ compilers, and how to use them to generate code for all CodeWarrior targets. There are chapters that cover information about the C/C++ compiler that applies to all targets. Information that is specific to a particular target operating system or processor appears in separate chapters, one per target.

The sections in this introduction are:

- What's in this Reference?
- Read the Release Notes!
- What's New
- CodeWarrior Year 2000 Compliance
- Conventions Used in This Reference

## What's in this Reference?

The manual is organized into these principle sections:

- Interface—how to set compiler options
- Language—generic information on the compilers as they apply to all CW targets
- Pragmas—information on all pragmas for all targets

Each chapter begins with an overview section. Table 1.1 lists each of these and describes what each chapter in this manual covers.

Table 1.1 What's in this reference

This chapter	Describes
Setting C Compiler Options Overview	where to find information on the C/C++ Language and C/C++ Warnings settings panels.
C Compiler Overview	how the CodeWarrior C/C++ compiler implements C
C++ Compiler Overview	how the CodeWarrior $C/C++$ compiler implements $C++$ features that are not shared by $C$ .
C++ and Embedded Systems Overview	how to use CodeWarrior C++ for embedded systems development and how to design programs to anticipate the proposed EC++ (Embedded C++) standard.
Pragmas and Symbols Overview	the pragmas and predefined symbols available with CodeWarrior C/C++ compiler

## **Read the Release Notes!**

Because of last-minute changes to the CodeWarrior C/C++ compiler, some of the information may be inaccurate. Please read the Release Notes on the CodeWarrior CD for the latest up-to-date information.

## What's New

This reference has been updated to cover CodeWarrior C/C++ version 2.3 and later.

New and changed topics in this reference are:

- <u>"Introduction" on page 11</u>—this chapter has been updated to follow the organization followed by other CodeWarrior language references
- <u>"ANSI Strict" on page 37</u>—updated to cover the "D" constant suffix
- <u>"ANSI Keywords Only" on page 41</u>—updated to note that far is no longer a keyword in some versions of CodeWarrior C/C++

- <u>"Character Constants as Integer Values" on page 42</u>—updated to distinguish integer values denoted with character string constants from multi-byte character sets
- "Intrinsic Functions for Bit Rotation" on page 53—describes new "built-in" functions
- <u>"The "D" Constant Suffix" on page 53</u>—describes how to explicitly specify floating point constant values of type double
- <u>"Using the bool Type" on page 67</u>—updated to distinguish between the ANS/ISO C++ Standard's definition of the bool type and its non-standard implementations
- "Declaring and Defining Templates" on page 73—new information on improved conformance with the ANS/ISO C++ Standard for template declarations
- <u>"direct\_destruction" on page 112</u>—this pragma is obsolete and is no longer available
- <u>"float constants" on page 125</u>—a new pragma to treat floating point constants as values of type float by default
- <u>"longlong\_prepval" on page 139</u>—a new pragma to allow the preprocessor to handle expressions of type long\_long
- <u>"message" on page 142</u>—a new pragma for issuing messages to the user
- <u>"no static dtors" on page 148</u>—a new pragma for controlling the generation of C++ static destructors
- <u>"warn\_padding" on page 193</u>—a new pragma for controlling warnings for data structure alignment

## **CodeWarrior Year 2000 Compliance**

The Products provided by Metrowerks under the License agreement process dates only to the extent that the Products use date data provided by the host or target operating system for date representations used in internal processes, such as file modifications. Any Year 2000 Compliance issues resulting from the operation of the Products are therefore necessarily subject to the Year 2000 Compliance of the relevant host or target operating system. Metrowerks directs you to the relevant statements of Microsoft Corporation, Sun Microsystems, Inc., Apple Computer, Inc., and other host or target operating

systems relating to the Year 2000 Compliance of their operating systems. Except as expressly described above, the Products, in themselves, do not process date data and therefore do not implicate Year 2000 Compliance issues.

For additional information, visit: http://www.metrowerks.com/about/y2k.html.

## **Conventions Used in This Reference**

This manual includes syntax examples that describe how to use certain statements, such as the following:

```
#pragma parameter [return-reg] func-name [param-regs]
#pragma optimize_for_size on | off | reset
```

<u>Table 1.2</u> describes how to interpret these statements.

**Table 1.2 Understanding Syntax Examples** 

If the text	
looks like	Then
literal	Include it in your statement exactly as it's printed.
metasymbol	Replace the symbol with an appropriate value. The text after the syntax example describes what the appropriate values are.
alblc	Use one and only one of the symbols in the statement: either a, b, or c.
[a]	Include this symbol only if necessary. The text after the syntax example describes when to include it.



# Setting C/C++ Compiler Options

This chapter describes where to find information on the C/C++ Compiler and C/C++ Warnings settings panels.

## **Setting C Compiler Options Overview**

This section contains the following sections:

- <u>"C/C++ Language Panel" on page 15,</u> illustrates each option available to you, and tells you where that option is explained fully.
- <u>"C/C++ Warnings Panel" on page 18</u>, illustrates each compiler warning available to you, and tells you where that warning is explained fully.

The C/C++ Compiler settings panel, where you set compiler options, is also known as the C/C++ Language settings panel.

## C/C++ Language Panel

You may configure how the C/C++ compiler works by setting a variety of options. You set these options in the C/C++ Compiler settings panel, shown in <u>Figure 2.1</u>. For information on how to display a particular settings panel, see the *IDE User Guide*.

**TIP:** Another way to set these options is to use pragma directives in your source code. See <u>"Pragmas and Symbols" on page</u> 89 for more information.

Each compiler option has a corresponding pragma that you can use in source code to turn that particular option on or off, regardless of the settings in the C/C++ Compiler panel. In addition, there are some pragmas that do not have a corresponding setting in the C/C++ Compiler panel. See <u>"Pragmas and Symbols Overview" on page 89</u> for details on each available pragma.

You may also use a special preprocessor directive in your code to determine the current setting of each option. See <u>"Checking Options" on page 202</u> for information on how to use this directive.

Some of the options shown in <u>Figure 2.1</u> may not appear for some targets. For example, the Direct to SOM item appears for Mac OS.

Figure 2.1 The C/C++ Compiler Settings Panel

C/C++ Language	
☐ Activate C++ Compiler	☑ ANSI Strict
ARM Conformance	ANSI Keywords Only
☐ Enable C++ Exceptions	Expand Trigraphs
☐ Enable RTTI	☐ Multi-Byte Aware
Inline Depth: Smart 💠	Direct to SOM: Off 🐤
☐ Auto-Inline	☐ Map newlines to CR
☐ Deferred Inlining	Relaxed Pointer Type Rules
☐ Pool Strings	☐ Enums Always Int
☐ Don't Reuse Strings	Use Unsigned Chars
☑ Require Function Prototypes	☐ EC++ Compatibility Mode
☐ Enable bool Support	☐ Enable Objective C
☑ Enable wchar_t Support	
Prefix File: my_prefix.h	

Most of the items in this panel are discussed elsewhere in this manual, because they are closely related to how the compiler implements standard C and C++.

#### Other items

This table lists where to find information about the other items in this panel.

This item	Is described here				
Activate C++ Compiler	"Using the C++ Compiler Always" on page 64.				
ARM Conformance	"Controlling ARM Conformance" on page 65				
<b>Enable C++ Exceptions</b>	"Controlling C++ Extensions" on page 67				
Enable RTTI	"Controlling RTTI" on page 66				
Inline Depth Auto-inline	"Inlining" on page 43				
Pool Strings	"Pool Strings" on page 45				
Don't Reuse Strings	"Reusing Strings" on page 46				
<b>Require Function Prototypes</b>	"Require Function Prototypes" on page 47				
<b>Enable bool Support</b>	"Using the bool Type" on page 67				
Enable wchar_t Support	"Using the wchar t Type" on page 38				
ANSI Strict	"ANSI Strict" on page 37				
ANSI Keywords Only	"ANSI Keywords Only" on page 41				
<b>Expand Trigraphs</b>	"Expand Trigraphs" on page 42				
Multi-Byte Aware	"Multibyte Strings and Comments" on page 44				
Direct to SOM	Targeting Mac OS manual				
Map Newlines to CR	"Map Newlines to CR" on page 49				
<b>Relaxed Pointer Type Rules</b>	"Relaxed Pointer Type Rules" on page 50				
<b>Enums Always Int</b>	"Enumerated Types" on page 33				

This item	Is described here
Use Unsigned Chars	"Use Unsigned Chars" on page 50
Prefix File	"Prefix Files" on page 32
EC++ Compatibility Mode	"Activating EC++" on page 79
<b>Enable Objective C</b>	Targeting Rhapsody manual

## C/C++ Warnings Panel

The C/C++ compiler generates errors when it cannot understand your code as a result of improper syntax. In addition to errors, the compiler can generate a series of helpful warnings that alert you to legal but usually unintentional syntax. These mistakes are legal C and C++ code, but the code might not do what you expect.

When the compiler finds one of these possible mistakes, it can generate a warning. Warnings are not fatal. Unless you choose to treat these warnings as errors, your code will still compile (although it may not run correctly).

This section describes the items in the C/C++ Warnings panel. You determine which warnings you receive by setting options in the panel. Figure 2.2 illustrates this panel.

Each warning also has a corresponding pragma that you can use in source code to turn that particular warning on or off for a limited piece of code. See <u>"Pragmas and Symbols Overview" on page 89</u> for details on each available pragma.

You may also use a special preprocessor directive in your code to determine the current setting of each option. See <u>"Checking Options" on page 202</u> for information on how to use this directive.

For information on how to display a particular settings panel, see the *IDE User Guide*.

Figure 2.2 The C/C++ Warnings Settings Panel

C/C++ Varnings
☐ Treat All Warnings As Errors
☐ Illegal Pragmas
☐ Empty Declarations
Possible Errors
☐ Unused Variables
Unused Arguments
Extra Commas
☐ Extended Error Checking
☐ Hidden Yirtual Functions
☐ Implicit Arithmetic Conversions
☐ Non-Inlined Functions
☐ Inconsistent Use of 'class' and 'struct' Keywords

The items in this panel are:

- "Treat All Warnings as Errors" on page 20
- "Illegal Pragmas" on page 20
- "Empty Declarations" on page 20
- "Possible Errors" on page 21
- "Unused Variables" on page 22
- "Unused Arguments" on page 23
- <u>"Extra Commas" on page 24</u>
- "Extended Error Checking" on page 24
- "Hidden Virtual Functions" on page 26
- "Implicit Arithmetic Conversions" on page 26

- "Non-Inlined Functions" on page 27
- <u>"Inconsistent Use of 'class' and 'struct' Keywords" on page 27</u>

## **Treat All Warnings as Errors**

When the **Treat All Warnings as Errors** option is on, the compiler treats all warnings as though they were errors. It will not compile a file until all warnings are resolved.

The **Treat All Warnings as Errors** option corresponds to the pragma warning\_errors, described at <u>"warning errors" on page 189.</u> To check whether this option is on, use <u>option</u> (warning\_errors). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

## **Illegal Pragmas**

If the **Illegal Pragmas** option is on, the compiler displays a warning when it encounters an illegal pragma. For example, these pragma statements generate warnings:

The **Illegal Pragmas** option corresponds to the pragma warn\_illpragma, described at <u>"warn\_illpragma" on page 191</u>. To check whether this option is on, use \_\_option (warn\_illpragma). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

#### **Empty Declarations**

If the **Empty Declarations** option is on, the compiler displays a warning when it encounters a declaration with no variable name. For example:

The **Empty Declarations** option corresponds to the pragma warn\_emptydecl, described at <u>"warn emptydecl" on page 189</u>. To check whether this option is on, use <u>\_\_option</u> (warn\_emptydecl). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

#### **Possible Errors**

If the **Possible Errors** option is on, the compiler checks for some common typographical mistakes that are legal C syntax but that may have unwanted side effects, such as putting in unintended semicolons or confusing = and ==. The compiler generates a warning if it encounters one of these:

• An assignment in a logical expression or the condition in an if, while, or for expression. This check is useful if you frequently use = when you meant to use ==. For example:

• An equal comparison in a statement that contains a single expression. This check is useful if you frequently use == when you meant to use =. For example:

• A semicolon (;) directly after a while, if, or for statement. For example, the statement generates a warning and is probably an unintended infinite loop:

```
while (i++); // WARNING: Unintended infinite loop
```

If you intended to create an infinite loop, put white space or a comment between the while statement and the semicolon. For example, these statements do not generate errors or warnings, and ensure that you will win the hearts of everyone using your software when the code is executed.

```
while (i++); // OK: White space separation while (i++) /*: Comment separation */;
```

The **Possible Errors** option corresponds to the pragma warn\_possunwant, described at <u>"warn\_possunwant" on page 194.</u>
To check whether this option is on, use \_\_option
(warn\_possunwant). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

#### **Unused Variables**

If the **Unused Variables** option is on, the compiler generates a warning when it encounters a variable that you declare but do not use. This check helps you find misspelled variable names and variables you have written out of your program. For example:

If you want to use this warning, but need to declare a variable that you don't use, use the pragma unused, as in this example:

```
void foo(void)
{
  int i, temp, error;
  #pragma unused (i, temp) /* Compiler won't warn that i and temp
```

```
error=do_something();    /* are not used */
}
```

The **Unused Variables** option corresponds to the pragma warn\_unusedvar, described at <u>"warn\_unusedvar" on page 196.</u> To check whether this option is on, use \_\_option (warn\_unusedvar). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

## **Unused Arguments**

If the **Unused Arguments** option is on, the compiler generates a warning when it encounters an argument you declare but do not use. This check helps you find misspelled argument names and arguments you have written out of your program.

```
void foo(int temp,int errer); // ERROR: errer is misspelled
{
  error = do_something(); // WARNING: temp and error are unused.
}
```

If you need to declare an argument that you don't use, there are two ways to avoid this warning. You can use the pragma unused, as in this example:

```
void foo(int temp, int error)
{
    #pragma unused (temp)
    /* Compiler won't warn that temp is not used */
    error=do_something();
}
```

You can also turn off the <u>ANSI Strict</u> option, and not give the unused argument a name. (See <u>"Unnamed Arguments in Function Definitions" on page 38.</u>) For example:

```
void foo(int /* temp */, int error)
{
    /* Compiler won't warn that temp is not used, it's not named
    error=do_something(); */
}
```

The **Unused Arguments** option corresponds to the pragma warn\_unusedarg, described at <u>"warn\_unusedarg" on page 196.</u> To check whether this option is on, use \_\_option (warn\_unusedarg). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

#### **Extra Commas**

If the **Extra Commas** option is on, the compiler generates a warning when it encounters an extra comma. For example, this statement is legal in C, but it causes a warning when this option is on:

```
int a[] = \{ 1, 2, 3, 4, \}; // ^ WARNING: Extra comma after 4
```

The Extra Commas option corresponds to the pragma warn\_extracomma, described at <u>"warn\_extracomma" on page 190</u>. To check whether this option is on, use \_\_option (warn\_extracomma). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

## **Extended Error Checking**

If the **Extended Error Checking** option is on, the C compiler generates a warning (not an error) if it encounters one of these syntax problems:

 A non-void function that does not contain a return statement. For example, this would generate a warning:

```
printf ("hello world\n");
} /* WARNING: no return statement */
```

#### This would be OK:

```
void main() /* function declared to return void */
{
  printf ("hello world\n");
}
```

• Assigning an integer or floating-point value to an enum type. For example:

• An empty return statement (return;) in a function that is not declared void. For example, this code would generate a warning:

```
int MyInit(void)
{
  int err = GetMyResources();
  if (err !=0) return; /* ERROR: Empty return statement */
  /* ... */
```

#### This would be OK:

```
int MyInit(void)
{
  int err = GetMyResources();
  if (err!=0) return -1; /* OK */
  /* ... */
```

The Extended Error Checking option corresponds to the pragma extended\_errorcheck, described at <u>"extended errorcheck" on page 121</u>. To check whether this option is on, use <u>\_\_option</u> (extended\_errorcheck). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

#### **Hidden Virtual Functions**

If the **Hidden virtual functions** option is on, the compiler generates a warning if you declare a non-virtual member function in a subclass that hides an inherited virtual function in a superclass. One function hides another if it has the same name but a different argument types. For example:

The **Hidden virtual functions** option corresponds to the pragma warn\_hidevirtual, described at <u>"warn hidevirtual"</u> on page 190. To check whether this option is on, use <u>option</u> (<u>warn hidevirtual</u>). See <u>"Checking Options"</u> on page 202 for information on how to use this directive.

## **Implicit Arithmetic Conversions**

If the **Implicit Arithmetic Conversions** option is on, the compiler issues a warning if the destination of an operation isn't large enough to hold all possible results. For example, assigning the value of a variable of type long to a variable of type char will result in a warning if this option is on.

#### **Non-Inlined Functions**

If the **Non-Inlined Functions** option is on, the compiler issues a warning when it is unable to inline a function.

This option corresponds to pragma <u>warn notinlined</u>. To check whether this option is on, use <u>option</u> (<u>warn notinlined</u>). See <u>"Checking Options" on page 202</u> for information on how to use this directive.

## Inconsistent Use of 'class' and 'struct' Keywords

If the **Inconsistent Use of 'class' and 'struct' Keywords** option is on, the compiler issues a warning if the class and struct keywords are used in the definition and declaration of the same identifier.

```
class X;
struct X { int a; }; // warning
```

Use this warning when linking (with static or dynamic libraries) with object code produced from another C++ compiler that makes a distinction between class and struct variables in its name "mangling."

This option corresponds to pragma <u>warn structclass</u>. To check whether this option is on, use <u>option (warn structclass)</u>. See <u>"Checking Options" on page 202</u> for information on how to use this directive.



# **C** Compiler

This chapter describes how the CodeWarrior C compiler implements the C language.

## **C** Compiler Overview

This chapter discusses the CodeWarrior C compiler as it applies to all CodeWarrior targets. For the most part, the information in this chapter is equally applicable to any operating system or processor.

Other chapters in this manual discuss other features of the compiler that are specific to particular operating systems and processors. For a complete picture, you need to consider all the information relating your target of interest.

This chapter does not cover C++ features. For more information on the C++ language, see <u>"C++ Compiler Overview" on page 55.</u>

This chapter contains the following sections:

- <u>"The CodeWarrior Implementation of C" on page 30</u> explains how the CodeWarrior compiler implements certain parts of the standard C language.
- <u>"Extensions to ANSI/ISO C" on page 36</u> describe some of CodeWarrior C's extensions to the C standards.

You'll find frequent references to K&R §A, which is Appendix A, "Reference Manual," of *The C Programming Language, Second Edition* (Prentice Hall) by Kernighan and Ritchie. These references show you where to look for more information on the topics discussed in the corresponding section.

## The CodeWarrior Implementation of C

This section describes how CodeWarrior implements many parts of the C programming language. For information on the parts of the C++ language that are specific to C++, see <u>"C++ Compiler Overview"</u> on page 55.

This section discusses the following topics:

- Identifiers
- Include Files
- Prefix Files
- Sizeof() Operator
- Volatile Variables
- Enumerated Types

#### **Identifiers**

(K&R, §A2.3) The C compiler lets let you create identifiers of any size. However, only the first 255 characters are significant for internal and external linkage.

#### **Include Files**

(K&R, §A12.4) The C compiler can nest #include files up to 32 times. An include file is nested if another #include file uses it in an #include statement. For example, if Main.c includes the file MyFunctions.h, which includes the file MyUtilities.h, the file MyUtilities.h is nested once.


You can use full path names in #include directives, as in this example for Mac OS:

```
#include "HD:Tools:my headers:macros.h"
```

The CodeWarrior IDE lets you specify where the compiler looks for #include files with the Access Paths settings panel, shown in Figure 3.1. It contains two lists of folders: the User list and the System list. By default, each list contains one folder. The User list contains  $\{Project f\}$ , which is the folder that the project file is in and all

the folders it contains. The System list contains  $\{Compiler f\}$ , which is the folder that CodeWarrior is in, and all the folders it contains.

Figure 3.1 The Access Paths settings panel



The compiler searches for a #include file in either the System list or both the User and System lists, depending on which characters enclose the file. If you enclose the file in brackets (#include <stdio.h>), the compiler looks for the file in the System list. If you enclose the file in quotes (#include "myfuncs.h"), the compiler looks for the file in the User list first, and then in the System list. In general, use brackets for include files that are for a large variety of projects and use quotes for include files that are for a specific project.

If the **Always Search User Paths** option is selected, the compiler also uses the User access paths for include files enclosed in brackets (#include *<file>*).

For information on how to modify the Access Paths settings panel, see the *CodeWarrior IDE User Guide*.

See also: "Prefix Files" on page 32.

**TIP:** If you're using the compiler under Apple Computer's MPW programming environment, you can specify where to find #include files with the -i compiler option and the {CIncludes} variable, described in *Command-Line Tools Manual* and *MPW Command Reference*.

#### **Prefix Files**

If you have a single file you wish to include in every source file in a project, you can use the **Prefix File** item in the <u>C/C++ Language</u> <u>Panel</u>. Enter the name of the file in the Prefix File edit field in this panel.

The compiler automatically includes this file (and any files that it, in turn, includes) in every source file in the project's current target. This is an excellent way to include a precompiled header file in a project.

This field is also used as an alternative to the -d option commonly issued to compilers that operate at the command line.

See also: "Include Files" on page 30.

## Sizeof() Operator

The sizeof() operator returns a number of type size\_t, which the compiler declares to be of type unsigned long int (in the file stddef.h). If your code assumes that sizeof() returns a number of type int, it may not work correctly.

#### **Volatile Variables**

(K&R, §A4.4) When you declare a variable to be volatile the C compiler takes the following precautions:

- It does not store the variable in a register.
- It computes the variable's address every time a piece of code references the variable.

<u>Listing 3.1</u> shows an example of volatile variables.

#### Listing 3.1 volatile variables

```
void main(void)
{
   int i[100];
   volatile int a, b;

   a = 5;
   b = 20;

   i[a + b] = 15;
   i[a + b] = 30;
}
```

The compiler does not place the value of a, b, or a+b in registers. Also, the compiler recalculates a+b in both assignment statements.

## **Enumerated Types**

(K&R, §A8.4) This section describes how the C compiler selects the underlying integer data type for an enumerated type. The compiler behavior is controlled primarily by the **Enums Always Int** option in the <u>C/C++ Language Panel</u>.

The compiler uses one of two different strategies, depending on the setting of the Enums Always Int option.

If Enums Always Int is *on*, the underlying type is always signed int. All enumerators must be no larger than a signed int. If an

enumerated constant is larger than an int, the compiler generates an error.

However, if the <u>ANSI Strict</u> option is off, enumerators that can be represented as an unsigned int are implicitly converted to signed int. For example:

See <u>"ANSI Strict" on page 37</u> for additional features of that setting.

If Enums Always Int is *off*, the compiler chooses the integral data type that supports the largest enumerated constant. The type could be as small as a char or as large as a long int. It could even be a 64-bit long long value.

To be more precise, if Enums Always Int is off, the compiler picks one of the following:

- If all enumerators are positive, it picks the smallest unsigned integral base type that is large enough to represent all enumerators
- If at least one enumerator is negative, it picks the smallest signed integral base type large enough to represent all enumerators.

For example:

The compiler will use long long data types only if Enums Always Int is off and the <u>longlong enums</u> pragma is on. (There is no settings panel option corresponding to the longlong\_enums pragma.)

#### For example:

When the longlong\_enums pragma is off and ANSI Strict is on, you cannot mix unsigned 32-bit enumerators greater than 0x7FFFFFFF and negative enumerators. If both the longlong\_enums pragma and the ANSI Strict option are off, huge unsigned 32-bit enumerators are implicitly converted to signed 32-bit types.

#### For example:

```
#pragma enumsalwaysint off
#pragma longlong_enums off
#pragma ANSI_strict on
enum { a=-1,b=0xFFFFFFFF };  // error
#pragma ANSI_strict off
enum { c=-1,d=0xFFFFFFFF };  // base type: signed int (b==-1)
```

The **Enums Always Int** option corresponds to the pragma <u>enum-salwaysint</u>. To check whether this option is on, use <u>option</u> (enumsalwaysint). By default, this option is off.

See also <u>"enumsalwaysint"</u> on page 117, <u>"longlong enums"</u> on page 139, and <u>"Checking Options"</u> on page 202.

## Extensions to ANSI/ISO C

This section describes CodeWarrior extensions to the C standard that apply to all targets. In most cases you turn the extension on or off with an option in the C/C++ Language Panel. See "C/C++ Language Panel" on page 15 for information about that panel.

#### The topics in this section are:

- "ANSI Strict" on page 37
- "C++ Style Comments" on page 38
- "Unnamed Arguments in Function Definitions" on page 38
- "A # not Followed by Argument in a Macro" on page 38
- "Using an Identifier After #endif" on page 39
- "Using Typecasted Pointers as Ivalues" on page 40
- "Declaring Variables By Address" on page 40
- "ANSI Keywords Only" on page 41
- "Expand Trigraphs" on page 42
- "Character Constants as Integer Values" on page 42
- "Inlining" on page 43
- "Multibyte Strings and Comments" on page 44
- "Reusing Strings" on page 46
- <u>"Require Function Prototypes" on page 47</u>
- "Map Newlines to CR" on page 49
- "Relaxed Pointer Type Rules" on page 50
- "Use Unsigned Chars" on page 50
- <u>"Using 64-bit Integers" on page 51</u>
- "Converting Pointers to Types of the Same Size" on page 51
- "Getting Alignment and Type Information at Compile-Time" on page 52
- "Arrays of Zero Length in Structures" on page 52
- "Intrinsic Functions for Bit Rotation" on page 53
- "The "D" Constant Suffix" on page 53

For information on target-specific extensions, you should refer to the *Target* manual for the particular target in which you are interested.

#### **ANSI Strict**

The ANSI Strict option in the <u>C/C++ Language Panel</u> affects several extensions to the C language supported by the CodeWarrior compiler. The extensions are:

- C++ Style Comments
- <u>Unnamed Arguments in Function Definitions</u>
- A # not Followed by Argument in a Macro
- <u>Using an Identifier After #endif</u>
- <u>Using Typecasted Pointers as Ivalues</u>
- Converting Pointers to Types of the Same Size
- Arrays of Zero Length in Structures
- The "D" Constant Suffix

In each case the extension is only available if the ANSI Strict setting is *off*. If the ANSI Strict setting is on, then these extensions to the ANSI C standard are disabled.

You cannot turn on the extensions controlled by the ANSI Strict setting individually. They are all on or off depending upon the setting.

This setting may affect how the compiler handles enumerated constants. See <u>"Enumerated Types" on page 33</u> for more information.

This setting may also affects the main() function for C++ programs. See "Implicit Return Statement for main()" on page 57.

The ANSI Strict option corresponds to the pragma <u>ANSI strict</u>. To check whether this option is on, use <u>option</u> (ANSI\_strict).

See also <u>"ANSI strict"</u> on page 96. and <u>"Checking Options"</u> on page 202.

#### Using the wchar\_t Type

Turn on the **Enable wchar\_t Support** option if you want to use the standard C++ wchar\_t type to represent wide characters. Turn this option off to use the regular character type, char.

#### C++ Style Comments

(K&R, §A2.2) The C compiler can accept C++ comments in source code. In a C++ comment, anything that follows // on a line is considered a comment. For example:

```
a = b; // This is a C++ comment
```

To turn this feature on, turn *off* the ANSI Strict setting in the  $\frac{C/C++}{Language\ Panel}$ . If the ANSI Strict setting is on, then this extension to standard C is disabled.

See also: "ANSI Strict" on page 37.

## **Unnamed Arguments in Function Definitions**

(K&R, §A10.1) The C compiler can accept an unnamed argument in a function definition. For example:

```
void f(int ) {} /* OK, if ANSI Strict is off */
void f(int i) {} /* ALWAYS OK */
```

To turn this feature on, turn *off* the ANSI Strict setting in the  $\frac{C/C++}{Language\ Panel}$ . If the ANSI Strict setting is on, then this extension to standard C is disabled.

See also: "ANSI Strict" on page 37.

## A # not Followed by Argument in a Macro

(K&R, §A12.3) The C compiler can accept a # token not followed by an argument in a macro definition. For example:

To turn this feature on, turn *off* the ANSI Strict setting in the C/C++ Language Panel. If the ANSI Strict setting is on, then this extension to standard C is disabled.

See also: "ANSI Strict" on page 37.

#### Using an Identifier After #endif

(K&R, §A12.5) The C compiler can accept an identifier token after #endif and #else. This extension helps you match an #endif statement with its corresponding #if, #ifdef, or #ifndef statement, as shown here:

To turn this feature on, turn *off* the ANSI Strict setting in the C/C++ Language Panel. If the ANSI Strict setting is on, then this extension to standard C is disabled.

See also: "ANSI Strict" on page 37.

**TIP:** If you turn on the **ANSI Strict** option (disabling the extension), you can still use the same idea to help you match your #if-def and #endif directives. Simply put the identifiers into comments, as in the following example.

## **Using Typecasted Pointers as Ivalues**

The C compiler can accept a pointer that you typecast to another pointer type as an lvalue.

For example:

```
char *cp;
((long *) cp)++; /* OK if ANSI Strict is off. */
```

To turn this feature on, turn *off* the ANSI Strict setting in the <u>C/C++</u> <u>Language Panel</u>. If the ANSI Strict setting is on, then this extension to standard C is disabled.

See also: "ANSI Strict" on page 37.

#### **Declaring Variables By Address**

(K&R, §A8.7) The C compiler lets you specify the address that a variable refers to. For example, this definition defines MemErr to contain whatever is at the address 0x0220:

```
short MemErr: 0x220;
```

The variable MemErr contains whatever is at the address 0x220.

**WARNING!** For Mac OS programming, avoid using this extension to refer to low-memory globals. To ensure that your programs

are compatible with future versions of the Mac OS, use the functions defined in the LowMem.h header file.

This extension cannot be turned off. There is no corresponding pragma or setting in the C/C++ Language Panel.

## **ANSI Keywords Only**

(K&R, §A2.4) The C compiler can recognize several additional reserved keywords. The **ANSI Keywords Only** option in the <u>C/C++</u> <u>Language Panel</u> controls whether the compiler recognizes these keywords.

If this option is *on*, the compiler generates an error if it encounters any of the CodeWarrior C additional keywords. If you're writing code that must follow the ANSI/ISO standard strictly, turn on the **ANSI Keywords Only** option in the settings panel.

When this option is *off*, these additional keywords are available to you:

asm

This keyword lets you use the compiler's built-in inline assembler. (K&R, §A10.1) For more information on the inline assemblers, consult:

• far

The CodeWarrior C/C++ compiler for Motorola 68K processors treats far as a keyword. Other versions of CodeWarrior C/C++ do not recognize far as a keyword.

• inline

Lets you declare a C function to be inline. For more information, see "Inlining" on page 43.

pascal

This keyword is used in Mac OS programming.

\_\_stdcall

This keyword is used in Microsoft Win32 programming.

The **ANSI Keywords Only** option corresponds to the pragma only std keywords. To check whether this option is on, use \_\_option (only\_std\_keywords). By default, this option is off.

See also <u>"only std keywords" on page 149</u> and <u>"Checking Options"</u> on page 202.

## **Expand Trigraphs**

(K&R, §A12.1) The C compiler lets you ignore trigraph characters. Many common character constants (especially on Mac OS) look like trigraph sequences, and this extension lets you use them without including escape characters.

If you're writing code that must follow the ANSI/ISO standard strictly, turn *on* the **Expand Trigraphs** option in the <u>C/C++ Language Panel</u>. If this option is on, be careful when you initialize strings or multi-character constants that contain question marks.

The Expand Trigraphs option corresponds to the pragma <u>tri-graphs</u>, To check whether this option is on, use <u>option</u> (tri-graphs). By default, this option is off.

See also <u>"trigraphs" on page 185</u> and <u>"Checking Options" on page 202.</u>

#### **Character Constants as Integer Values**

(K&R, §A2.5.2) The C compiler lets you use character string constants that contain 2 to 4 characters to denote a 32-bit integer values. Here are some examples:

Character constant	Equivalent hexadecimal
'ABCD'	0x41424344
'ABC'	0x00414243
'AB'	0x00004142

This extension cannot be turned off. There is no corresponding pragma or setting in the C/C++ Language Panel.

**NOTE:** This feature is different from using multibyte character sets, where a single character is represented by a data type larger than 1 byte.

See <u>"Multibyte Strings and Comments" on page 44</u> for a discussion of a different extension relating to using character sets with more than 256 characters (such as Kanji).

#### **Inlining**

The compiler determines whether to inline a function based on the settings of the <u>ANSI Keywords Only</u> item and the <u>Inline Depth</u> and <u>Auto-inline</u> items in the <u>C/C++ Language Panel</u>.

**For beginners:** When you call an inline function, the compiler inserts the function's code instead instructions to call that function. Inlining functions makes your programs faster (because you execute the function's code immediately without a function call), but possibly larger (because the function's code may be repeated in several different places).

If you turn *off* the <u>ANSI Keywords Only</u> option, you can declare C functions to be inline. The inlining items in the <u>C/C++ Language</u> <u>Panel</u> let you choose to inline no functions, only functions declared inline, or all small functions as shown in <u>Table 3.2</u>.

Table 3.2 Options for the Inline Depth pop-up menu

This option	Does this
Don't Inline	Inlines no functions, not even C or C++ functions declared inline.
Smart	Inlines small functions to a depth of 2 to 4 inline functions deep.
1 to 8	Always inlines to the depth specified by the numerical selection.
Always Inline	Always inlines functions, no matter the depth.

The **Smart** item and items 1 to 8 in the **Inline Depth** pop-up menu correspond to the pragma inline\_depth ("C/C++ Language Panel" on page 15). To check whether this option is on, use \_\_option(inline\_depth), described at "Checking Options" on page 202.

The **Don't Inline** item in the Inline Depth pop-up menu corresponds to the pragma dont\_inline, described at <u>"dont inline" on page 115</u>. To check whether this option is on, use \_\_option (dont\_inline), described at <u>"dont inline" on page 204</u>. By default, this option is off.

The **Auto-Inline** option lets the compiler choose which functions to inline. Also inlines C++ functions declared inline and member functions defined within a class declaration. This option corresponds to the pragma auto\_inline, described at <u>"auto\_inline" on page 98.</u> To check whether this option is on, use <u>\_\_option</u> (auto\_inline), described at <u>"auto\_inline" on page 203.</u> By default, this option is off.

#### **Multibyte Strings and Comments**

The C compiler supports languages that use more than one byte to represent a character, such as Unicode and Japanese Kanji. This feature is controlled by the **Multi-Byte Aware** item in the <u>C/C++ Language Panel</u>.

To use multibyte strings or comments, turn on the **Multi-Byte Aware** option. If you don't need multibyte strings or comments, turn this option off, because it slows down the compiler.

See <u>"Character Constants as Integer Values" on page 42</u> for a discussion of creating a character constant consisting of more than one character (a completely different subject with a similar sounding name).

## **Pool Strings**

The **Pool Strings** option in the <u>C/C++ Language Panel</u> affects how the compiler stores string constants

**NOTE:** In principle this option works for all targets. However, it is useful only for a Table of Contents based (TOC-based) linking mechanism such as that used for Mac OS on the PowerPC processor, or with Code Fragment Manager support on the 68K processor.

If this option is on, the compiler collects all string constants into a single data object so your program needs one TOC entry for all of them. Turning this option on decreases the number of TOC entries in your program but increases your program's size, because it uses a less efficient method to store the string's address.

If this option is off, the compiler creates a unique data object and TOC entry for each string constant.

**TIP:** You can change the size of the TOC with the **Store Static Data in TOC** option in the PPC Processor settings panel. For more information, see the *Targeting Mac OS* manual.

Turning this option on is especially useful if your program is large and has many string constants.

**NOTE:** If you turn the **Pool Strings** option on, the compiler ignores the setting of the **PC-Relative Strings** option. This is a 68K-only feature.

The **Pool Strings** option corresponds to the pragma <a href="pool\_strings">pool\_strings</a>. To check whether this option is on, use \_\_option (pool\_strings). By default, this option is off.

See also <u>"pool strings"</u> on page 161 and <u>"Checking Options"</u> on page 202.

## Reusing Strings

The **Don't Reuse Strings** option in the <u>C/C++ Language Panel</u> affects how the compiler stores string literals.

If this option is on, the compiler stores each string literal separately.

If this option is off, the compiler stores only one copy of identical string literals. This option helps you save memory if your program contains identical string literals which you do not modify.

If this option is off (meaning that string storage is reused for identical strings) and you change one of the strings, you change them all. For example, take this code snippet:

```
char *str1="Hello";
char *str2="Hello"; // two identical strings
*str2 = 'Y';
```

If the Don't Reuse Strings option is *on*. the strings are stored separately. After changing the first character, str1 is still "Hello" but str2 is "Yello".

If the Don't Reuse Strings option is *off*, the two strings are stored in one memory location (i.e. the same memory location is reused), because they are both identical. After changing the first character, *both* str1 and str2 are "Yello". This is counter-intuitive, and can lead to difficult-to locate bugs.

The Don't Reuse Strings option corresponds to the pragma dont reuse strings. To check whether this option is on, use \_\_option (dont\_reuse\_strings). By default, this option is on. (Strings are *not* reused.)

See also <u>"dont reuse strings" on page 115.</u> and <u>"Checking Options"</u> on page 202.

#### **Require Function Prototypes**

(K&R, §A8.6.3, §A10.1) The C compiler lets you choose how to enforce function prototypes. This behavior is controlled by the **Require Function Prototypes** item in the <u>C/C++ Language Panel</u>.

When the **Require Function Prototypes** option is on, the compiler generates an error if you use a function that is defined after it is referenced and does not have a prototype. If the function is implicitly defined, that is, is defined before it is referenced, and does not have a prototype, then the compiler will issue a warning if **Require Function Prototypes** is on.

This option helps you prevent errors that happen when you call a function before you declare or define it. For example, without a function prototype, you may pass data if the wrong type. As a result, your code may not work as you expect even though it compiles without error.

In <u>Listing 3.2</u>, PrintNum() is called with an integer argument but is later defined to take a floating-point argument.

#### Listing 3.2 Unnoticed type-mismatch

```
#include <stdio.h>

void main(void)
{
    PrintNum(1); // PrintNum() tries to interpret the integer as a float. Prints 0.000000.
}
```

```
void PrintNum(float x)
{
    printf("%f\n", x);
}
```

When you run this code, you could get this result:

```
0.000000
```

Although the compiler does not complain about the type mismatch, the function does not work as you want. Since PrintNum() is not prototyped, the compiler does not know it needs to convert the integer to a floating-point number before calling the function. Instead, the function interprets the bits it received as a floating-point number and prints nonsense.

If you prototype PrintNum() first, as in <u>Listing 3.3</u>, the compiler converts its argument to a floating-point number, and the function prints what you wanted.

#### Listing 3.3 Using a prototype to avoid type-mismatch

In the above example, the compiler automatically typecast the passed value. In other situations where automatic typecasting is not available, the compiler will generate an error if an argument does not match the data type required by a function prototype. Such a

mismatched data type error is easy to locate at compile time. If you do not use prototypes, you get no compiler error. However, at runtime the code may behave strangely, and the cause of the resulting unintentional behavior can be extremely difficult to track down.

The **Require Function Prototypes** option corresponds to the pragma <u>require prototypes</u>. To check whether this option is on, use <u>option</u> (require\_prototypes). By default, this option is on.

See also <u>"require prototypes" on page 165</u>, and <u>"Checking Options" on page 202</u>.

#### Map Newlines to CR

The C compiler lets you choose how to interpret the newline (' $\n'$ ) and return (' $\r'$ ) characters. This behavior is controlled by the **Map Newlines to CR** item in the <u>C/C++ Language Panel</u>.

In most compilers, including CodeWarrior C/C++, '\r' is translated to the value  $0 \times 0 D$ , the standard value for carriage return, and '\n' is translated to the value  $0 \times 0 A$ , the standard value for linefeed.

However, the C compiler in the Macintosh Programmers Workshop, known as MPW C, '\r' is translated to 0x0A and '\n' is translated to 0x0D—the opposite of the typical behavior.

If you turn this option on, the compiler uses the MPW conventions for the '\n' and '\r' characters.

If this option is off, the compiler uses the CodeWarrior C and C++ conventions for these characters.

If you turn this option on, be sure you use ANSI/ISO C and C++ libraries that were compiled with this option on. If you turn this option on and use libraries built with this option off, you won't be able to read and write ' $\n'$  and ' $\r'$  properly. For example, printing ' $\n'$  would bring you to the beginning of the current line instead of inserting a new line.

This option corresponds to the pragma mpwc\_newline. To check
whether this option is on, use \_\_option (mpwc\_newline). By default, this option is off.

See also <u>"mpwc\_newline" on page 145</u>, and <u>"Checking Options" on page 202</u>.

For more information on issues relating to compatibility with MPW in Mac OS programming, see *Targeting Mac OS*.

## **Relaxed Pointer Type Rules**

When you turn on the **Relaxed Pointer Type Rules** option in the <u>C/C++ Language Panel</u>, the compiler treats char\* and unsigned char\* as the same type. While prototypes are checked for compatible pointer types, direct pointer assignments will be allowed.

This option is especially useful if you're using code written before the ANSI/ISO C standard. Old source code frequently uses these types interchangeably.

This option has no effect on C++. When compiling C++ source code, the compiler differentiates char\* and unsigned char\* data types even if the relaxed pointer option is on.

The **Relaxed Pointer Type Rules** option corresponds to the pragma <a href="mpwc\_relax">mpwc\_relax</a>. To check whether this option is on, use \_\_option (mpwc\_relax).

See also <u>"mpwc\_relax" on page 146</u>, and <u>"Checking Options" on page 202</u>.

## **Use Unsigned Chars**

The C compiler can automatically treat a char declarations as unsigned char. This behavior is controlled by the **Use Unsigned Chars** setting in the <u>C/C++ Language Panel</u>.

When the Use Unsigned Chars option is on, the C compiler treats a char declaration as if it were an unsigned char declaration.

**NOTE:** If you turn this option on, your code may not be compatible with libraries that were compiled with this option turned off.

The **Use Unsigned Chars** option corresponds to the pragma <u>unsigned char</u>. To check whether this option is on, use <u>option</u> (unsigned\_char). By default, this option is off.

See also <u>"unsigned char" on page 186</u> and <u>"Checking Options" on page 202.</u>

## **Using 64-bit Integers**

The C compiler lets you define a 64-bit integer with the type specifier long long. This behavior is controlled by the <u>longlong</u> pragma. There is no item in the <u>C/C++ Language Panel</u> to control this option.

If this option is on, you may declare a long long integer. A long long can hold values from -9,223,372,036,854,775,808 to 9,223,372,036,854,775,807. An unsigned long long can hold values from 0 to 18,446,744,073,709,551,615.

If this option is off, using long long causes a syntax error.

In an enumerated type, you can use an enumerator large enough for a long long. For more information, see <u>"Enumerated Types" on page 33.</u> However, long long bitfields are not supported.

You control the long long type with pragma <u>longlong</u>. To check whether this option is on, use <u>\_\_option</u> (longlong). By default, this pragma is on.

See also <u>"longlong" on page 138</u> and <u>"Checking Options" on page 202.</u>

#### Converting Pointers to Types of the Same Size

The C compiler allows the conversion of pointer types to integral data types of the same size in global initializations. Since this type of conversion doesn't conform to the ANSI C standard, it is only avail-

able if the **ANSI Strict** option is off in the **C/C++ Language** settings panel. See <u>"ANSI Strict" on page 37</u> for more information on this option.

#### Listing 3.4 Converting a pointer to a same-sized integral type

```
char c;
long arr = (long)&c; // accepted (not ANSI/ISO C)
```

# **Getting Alignment and Type Information at Compile-Time**

The C compiler has two built-in functions that return information about a data type's byte alignment and its data type.

The function call \_\_builtin\_align(typeID) returns the byte-alignment used for the data type typeID.

The function call \_\_builtin\_type(typeID) returns an integral value that describes what kind of data type typeID is. If typeID is an integral or an enumerated type, \_\_builtin\_type(typeID) returns 0. If typeID is a floating point type, \_\_builtin\_type(typeID) returns 1. If typeID is any other kind of data type, \_\_builtin\_type(typeID) returns 2.

#### Arrays of Zero Length in Structures

If the **ANSI Strict** option is off in the <u>C/C++ Language Panel</u>, the compiler allows arrays of no length as the last item in a structure. <u>Listing 3.5</u> shows an example. Arrays may be defined with a zero as the index value or with no index value between brackets.

#### Listing 3.5 Using zero-length arrays

```
struct listOfLongs {
  long listCount;
  long list[0]; // OK if ANSI Strict is off, [] is OK, too.
}
```

#### **Intrinsic Functions for Bit Rotation**

CodeWarrior C has functions

```
__rol(op, n)
__ror(op, n)
```

that do left or right bit rotation respectively.

The *op* argument represents the item to have its bits rotated. The *n* argument represents the number of times to rotate *op* bits. The *op* argument is not promoted to a larger data type, and may be of type char, short, int, long or long long.

These functions are intrinsic ("built-in"). That is, to use the functions you do not first have to provide function prototypes for them. Also, you do not need to link with any special libraries.

**NOTE:** Currently, these functions are limited to the Motorola 68K and Intel x86 versions of the CodeWarrior C/C++ compiler.

#### The "D" Constant Suffix

When CodeWarrior C finds a "D" immediately after a floating point constant value, it treats that value as data of type double.

When the <u>float constants</u> pragma is on, floating point constants should end with a "D" so that they are not treated as values of type float.

For related information, see "float constants" on page 125.

Extensions to ANSI/ISO C				



# C++ Compiler

This chapter describes how the CodeWarrior C++ compiler implements the C++ language.

# C++ Compiler Overview

This chapter discusses the CodeWarrior C++ compiler as it applies to all CodeWarrior targets. For the most part, the information in this chapter is equally applicable to any operating system or processor.

Other chapters in this manual discuss other features of the compiler that are specific to particular operating systems and processors. For a complete picture, you need to consider all the information relating your target of interest.

In addition, the C compiler is an integral part of the CodeWarrior C++ compiler. As a result, everything about the C compiler applies equally to C++. This discussion of the C++ compiler does not repeat information on the C Compiler. See "C Compiler Overview" on page 29 for information on the C compiler.

This chapter covers all the features of the compiler that exist in support of the C++ language. In addition to describing those features and how to control them, this chapter also has sections on working with advanced features of C++ such as RTTI, exceptions, and templates.

This chapter contains the following sections:

- <u>"CodeWarrior Implementation of C++" on page 56</u> describes how CodeWarrior C++ implements certain sections of the C++ standard.
- "Unsupported Extensions" on page 64 describes some additions to the ANSI/ISO C++ standard that CodeWarrior C++ does not support

- <u>"Controlling the C++ Compiler" on page 64</u> describes how to change the compiler's behavior by setting options in the <u>C/C++ Language Panel</u>.
- <u>"Working With C++ Exceptions" on page 68</u> describes how to use the try and catch statements to perform exception handling.
- <u>"Working With RTTI" on page 69</u> describes how to use runtime type information support in your code.
- <u>"Working With Templates" on page 72</u> describes the best way set up the files that define and declare your templates. It also documents an addition to the C++ standard which lets you explicitly instantiate templates.

For information on using Embedded C++ (EC++) and for strategies on developing smaller C++ programs, see <u>"C++ and Embedded Systems Overview"</u> on page 79.

Many topics contain references to ARM, which is *The Annotated C++ Reference Manual* (Addison-Wesley) by Ellis and Stroustrup. These references show you where to look for more information on the information discussed in that topic.

# CodeWarrior Implementation of C++

This section describes how CodeWarrior C++ implements certain parts of the C++ standard, as described in *The Annotated C++ Reference Manual* (Addison-Wesley) by Ellis and Stroustrup. The topics discussed in this section are:

- Implicit Return Statement for main()
- Keyword Ordering
- Additional Keywords
- Conversions in the Conditional Operator
- <u>Default Arguments in Member Functions</u>
- Local Class Declarations with Inline Functions
- Copying and Constructing Class Objects
- Checking for Resources To Initialize Static Data

• Calling an Inherited Member Function

## Implicit Return Statement for main()

The compiler adds a

```
return 0;
```

statement in C++ a program's main() function if the function returns an int result and doesn't end with a user return statement.

#### Examples:

The compiler will also enforce an external int main() function if ANSI Strict is on in the C/C++ Language Panel.

## **Keyword Ordering**

(ARM §7.1.2, §11.4) If you use either the virtual or the friend keyword in a declaration, it must be the first word in the declaration. For example:

#### Listing 4.1 Using the virtual or friend keywords

```
class foo {
  virtual int f0();  // OK
  int virtual f1();  // ERROR
  friend int f2();  // OK
  int friend f3();  // ERROR
}
```

## **Additional Keywords**

(ARM §2.4, ANSI §2.8) In addition to reserving the symbols in §2.4 of the ARM as keywords, CodeWarrior C++ reserves these symbols from §2.8 of the ANSI C++ Standard as keywords:

bool	const_cast	dynamic_cast
explicit	false	mutable
namespace	reinterpret_cast	static_cast
true	typeid	using

## **Conversions in the Conditional Operator**

(ARM §5.16) The compiler does not apply reference conversions to the second and third expressions of the conditional operator. In other words, unless the second and third expressions are numeric types, they must be the same type.

#### Listing 4.2 A conversion in a conditional operator

```
class base { };
class derived : public base { };

static void foo(derived i)
{
  base     &a = i;
  derived &b = i, c;

c = (sizeof(0) ? a:b); // ERROR: b is not converted to (base &)
c = (sizeof(0) ? a:(base &)b)  // OK, typecast
}
```

## **Default Arguments in Member Functions**

(ARM, §8.2.6) The compiler does not bind default arguments in a member function at the end of the class declaration. Before the default argument appears, you must declare any value that you use in the default argument expression. For example:

#### Listing 4.3 Using default arguments in member functions

```
class foo {
  enum A { AA };
  int f(A a = AA); // OK
  int f(B b = BB); // ERROR: BB is not declared yet
  enum B { BB };
};
```

#### **Local Class Declarations with Inline Functions**

(ARM, §9.8) If you're declaring a class within a function, the class's inline functions cannot access the outer function's local types or variables. In other words, the compiler inserts the class's inline functions on global scope level. For example:

#### Listing 4.4 Using local class declarations with inline functions

```
int x;

void foo()
{
   static int s;

   class local {
     int f1() { return s; } // ERROR: cannot access 's'

     int f2() { return local::f1(); } // ERROR: cannot access local int f3() { return x; } // OK
   };
}
```

## **Copying and Constructing Class Objects**

(ARM, §12.1, §12.8) The compiler does not generate a copy constructor or a default operator= for a simple class. A simple class is a class that:

• Is a base class or is derived only from simple classes

- Has no class members or has only simple class members
- Has no virtual member functions
- Has no virtual base classes
- Has no constructor or destructor

#### Listing 4.5 Constructors

The compiler does not guarantee that generated assignment or copy constructors will assign or initialize objects representing virtual base classes only once.

# **Checking for Resources To Initialize Static Data**

Sometimes you create static C++ objects that require certain resources, such as a floating-point unit (FPU). You can check for these resources by creating a function called \_\_\_PreInit\_\_\_() which the compiler calls before it initializes static data. You cannot check for these resources in your main() routine, because the compiler initializes static data before it calls main().

You must declare the \_\_PreInit\_\_() function like this:

```
extern "C" void __PreInit__(void);
```

**NOTE:** This function is not supported when generating code for PowerPC.

For example, this stub checks for a floating-point unit. In this case you would also have to define the functions <code>HasFPU()</code> and <code>DisplayNoFPU()</code> yourself.

#### Listing 4.6 Checking for an FPU before initializing static data

```
#include <Types.h>
#include <stdlib.h>

extern "C" void __PreInit__(void);

void __PreInit__(void)
{
   if(!HasFPU()) {
      DisplayNoFPU(); // Display "No FPU" Alert abort(); // Abort program exection
   }
}
```

#### **Calling an Inherited Member Function**

(ARM, §10.2) If you want to call an inherited virtual member function, rather than the local override of that function, you can do so in two ways. The first way is the recommended method for referring to member functions defined in a base class, or any other parent class. The second way, while more convenient, is not recommended if you intend to use your source code with other compilers.

#### The standard way to call inherited member functions

The first way is supported by the ANSI/ISO C++ Standard and simply qualifies the member function with its base class.

Assume you have two classes, MyBaseClass and MySubClass, each implementing a function named MyFunc().

From within a function of MySubClass, you can call the base class version of MyFunc() this way:

MyBaseClass::MyFunc();

However, if you change the class hierarchy, this code may break. Assume you introduce an intermediate class, and your hierarchy is now MyBaseClass, MyMiddleClass, and MySubClass. Each has a version of MyFunc(). The code above still calls the *original* version of MyFunc() in the MyBaseClass, bypassing the additional behavior you implemented in MyMiddleClass. In all likelihood, this is not what you intend, and this kind of subtlety in the code can lead to unexpected results and bugs that are very hard to locate.

#### Using inherited keyword to call inherited member functions

**NOTE:** The inherited keyword is not supported by the ANSI/ISO C++ standard and is only implemented for single inheritance with CodeWarrior C++.

You may call the inherited version of MyFunc() this way:

inherited::MyFunc();

With the inherited keyword, the compiler identifies the base class at compile time. This line of code would call the immediate base class in both cases: where the base class is MyBaseClass, and where the immediate base class is MyMiddleClass.

If your class hierarchy changes at a later date and your subclass inherits from a different base class, the immediate base class is still called, despite the change in hierarchy.

The syntax is the following:

inherited::func-name(param-list);

The statement calls the *func-name* in the class's immediate base class. If class has more than one immediate base class (because of multiple inheritance) and the compiler can't decide which *func-name* to call, the compiler generates an error.

This example creates a Q class that draws its objects by adding behavior to the O class.

#### Listing 4.7 Using inherited to call an inherited member function

Make sure to insert this directive before using the inherited keyword:

```
#pragma def_inherited on
```

For related information on this pragma see <u>"def\_inherited" on page 106.</u>

## **Unsupported Extensions**

The C++ compiler does not support this extension to the C++ standard as described in *The Annotated C++ Reference Manual* (Addison-Wesley) by Ellis and Stroustrup:

• Overloading methods operator new[] and operator delete[] to allocate and deallocate the memory for a whole array of objects at once. Instead overload operator new() and operator delete(), which are the functions that operator new[] and operator delete[] call (ARM, §5.3.3, §5.3.4).

# Controlling the C++ Compiler

This section describes how to change the behavior of CodeWarrior C++ by setting some options in the <u>C/C++ Language Panel</u>. For information on this panel and all its options, see <u>"C/C++ Language Panel" on page 15.</u>

This section contains the following:

- <u>Using the C++ Compiler Always</u>
- Controlling ARM Conformance
- Controlling Exception Handling
- Controlling RTTI
- Using the bool Type
- Controlling C++ Extensions

For more information on Direct to SOM, see *Targeting Mac OS*.

## **Using the C++ Compiler Always**

If you turn on the **Activate C++ Compiler** option in the <u>C/C++ Language Panel</u>, the compiler compiles all the C source files in your project as C++ code. If you turn this option off, the CodeWarrior IDE looks at a file name's suffix to determine whether to use the C or C++ compiler. The the suffixes it looks for are described by the entries in the CodeWarrior IDE's **File Mappings** settings panel. See

the *IDE User Guide* for more information on configuring this settings panel.

This option corresponds to the pragma <u>cplusplus</u>. To check whether this option is on, use <u>\_\_option</u> (cplusplus). By default, this option is off.

See also <u>"cplusplus" on page 103</u> and <u>"Checking Options" on page 202</u>.

#### **Controlling ARM Conformance**

When the **ARM Conformance** option in the <u>C/C++ Language Panel</u> is on, CodeWarrior C++ generates an error when it encounters certain ANSI/ISO C++ features that conflict with the C++ specification in *The Annotated C++ Reference Manual*. Use this option only if you must make sure that your code strictly follows the specification in *The Annotated C++ Reference Manual*.

Turning on this option prevents you from doing the following

• Using protected base classes (ARM, §11.2). For example:

```
class X {};
class Y : protected X {}; // OK in CodeWarrior C++. Error in ARM.
```

• Changing the syntax of the conditional operator to let you use assignment expressions without parentheses in the second and third expressions (K&R, §A7.16). For example:

```
i ? x=y : y=z // OK in CodeWarrior C++. Error in ARM.
i ? (x=y):(y=z) // OK in ARM and CodeWarrior C++
```

• Declaring variables in the conditions of if, while and switch statements (K&R, §A9.4, §A9.5). For example:

```
while (int i=x+y) { /* ... */ }
// OK in CodeWarrior C++. Error in ARM.
```

Turning on this option allows you to do the following:

• Using variables declared in the condition of a for statement after the for statement (K&R, §9.5). For example:

```
for(int i=1; i<1000; i++) { /* ... */ }
return i; // OK in ARM, Error in CodeWarrior C++</pre>
```

This option corresponds to the pragma <u>ARM conform</u>. To check whether this option is on, use <u>\_\_option (ARM\_conform)</u>. By default, this option is off.

See also "ARM conform" on page 97 and "Checking Options" on page 202.

## Controlling Exception Handling

Turn on the **Enable C++ Exceptions** option in the <u>C/C++ Language</u> <u>Panel</u> if you use the ANSI/ISO-standard try and catch statements. Otherwise, turn off this option to generate smaller and faster code.

**TIP:** If you use PowerPlant for Mac OS programming, make sure this option is turned on. PowerPlant uses C++ exceptions.

For more information on CodeWarrior implements ANSI/ISO C++ exception handling mechanism, see <u>"Working With C++ Exceptions"</u> on page 68.

This option corresponds to the pragma <u>exceptions</u>. To check whether this option is on, use <u>option</u> (exceptions). By default, this option is off.

See also <u>"exceptions" on page 118</u> and <u>"Checking Options" on page 202.</u>

#### **Controlling RTTI**

CodeWarrior C++ supports run-time type information (RTTI), including the dynamic\_cast and typeid operators. To use these op-

erators, turn on the **Enable RTTI** option in the <u>C/C++ Language</u> Panel.

For more information on how to use these two operators, see "Working With RTTI" on page 69.

## Using the bool Type

Turn on the **Enable bool Support** option if you want to use the standard C++ bool type to represent true and false. Turn this option off if recognizing bool, true, or false as keywords would cause problems in your program.

Enabling the bool data type and its true and false values is not equivalent to defining them using typedef and #define. The C++ bool type is a distinct type defined by the ANSI/ISO C++ Standard. Source code that does not treat it as a distinct type might not compile properly.

For example, some compilers other than treat CodeWarrior C++ treat the bool type as equivalent to the unsigned char data type. Source code that compiles successfully on such a compiler might not compile without errors with CodeWarrior C++ unless the Enable bool Support option is off.

This option corresponds to the pragma <u>bool</u>. To check whether this option is on, use <u>option</u> (<u>bool</u>). By default, this option is off.

See also "bool" on page 99 and "Checking Options" on page 202.

## **Controlling C++ Extensions**

The C++ compiler has additional extensions that you can activate. There is no item in the <u>C/C++ Language Panel</u> to activate these extensions. You must turn on the pragma <u>cpp extensions</u>.

If this pragma is on, the compiler lets you use these extensions to the ANSI/ISO C++ standard:

• Anonymous structs (ARM, §9). For example:

• Unqualified pointer to a member function (ARM, §8.1c). For example:

```
#pragma cpp_extensions on
struct Foo { void f(); }
void Foo::f()
{
   void (Foo::*ptmf1)() = &Foo::f;
        // ALWAYS OK

   void (Foo::*ptmf2)() = f;
        // OK, if cpp_exptensions is on.
}
```

To check whether this option is on, use the \_\_option (cpp\_extensions). By default, this option is off.

See also <u>"cpp\_extensions" on page 103</u> and <u>"Checking Options" on page 202.</u>

# **Working With C++ Exceptions**

If you turn on the **Enable C++ Exceptions** options in the C/C++ Language Panel, you may use the try and catch statements to perform exception handling. For more information on activating sup-

port for C++ exception handling, see <u>"Controlling Exception Handling"</u> on page 66.

If exceptions are enabled, you can throw exceptions across any code that's compiled by the CodeWarrior C/C++ compiler. You cannot throw exceptions across the following:

- Mac OS Toolbox function calls
- Libraries compiled with exception support turned off
- Libraries compiled with versions of the CodeWarrior C/C++ compiler earlier than CodeWarrior 8
- Libraries compiled with CodeWarrior Pascal or other compilers

If you throw an exception across one of these, the code calls terminate() and exits.

If you throw an exception when you're allocating a class object or an array of class objects, the code automatically destructs the partially constructed objects and de-allocates the memory for them.

# Working With RTTI

This section describes how to work with run-time type information features of C++ supported in the CodeWarrior C++ compiler. RTTI lets you cast one type of object to be another type, get information about objects, and compare their types at runtime.

The topics in this section are:

- <u>Using the dynamic cast Operator</u>
- <u>Using the typeid Operator</u>

## Using the dynamic\_cast Operator

The dynamic\_cast operator lets you safely convert a pointer of one type to a pointer of another type. Unlike an ordinary cast, dynamic\_cast returns 0 if the conversion is not possible. An ordi-

nary cast returns an unpredictable value that may crash your program if the conversion is not possible.

This is the syntax for dynamic\_cast operator:

```
dynamic_cast<Type*>(expr)
```

The *Type* must be either void or a class with at least one virtual member function. If the object that *expr* points to (\**expr*) is of type *Type* or is derived from type *Type*, this expression converts *expr* to a pointer of type *Type*\* and returns it. Otherwise, it returns 0, the null pointer.

For example, take these classes:

```
class Person { virtual void func(void) { ; } };
class Athlete : public Person { /* . . . */ };
class Superman : public Athlete { /* . . . */ };
```

#### And these pointers:

```
Person *lois = new Person;

Person *arnold = new Athlete;

Person *clark = new Superman;

Athlete *a;
```

This is how dynamic\_cast would work with each:

```
a = dynamic_cast<Athlete*>(arnold);
  // a is arnold, since arnold is an Athlete.
a = dynamic_cast<Athlete*>(lois);
  // a is 0, since lois is not an Athlete.
a = dynamic_cast<Athlete*>(clark);
  // a is clark, since clark is both a Superman and an Athlete.
```

You can also use the dynamic\_cast operator with reference types. However, since there is no equivalent to the null pointer for references, dynamic\_cast throws an exception of type bad\_cast if it cannot perform the conversion.

**NOTE:** The bad\_cast type is defined in the header file exception. Whenever you use dynamic\_cast with a reference, you must #include exception.

This is an example of using dynamic\_cast with a reference:

```
#include <exception>
// . . .
Person &superref = *clark;

try {
    Person &ref = dynamic_cast<Person&>(superref);
}
catch(bad_cast) {
    cout << "oops!" << endl;
}</pre>
```

## **Using the typeid Operator**

The typeid operator lets you determine the type of an object. Like the sizeof operator, it takes two kinds of arguments:

- the name of a class
- an expression that evaluates to an object

**NOTE:** Whenever you use typeid operator, you must #include the typeinfo header file.

The typeid operator returns a reference to a type\_info object that you can compare with the == and != operators. For example, if you have these classes and objects:

```
class Person { /* . . . */ };
class Athlete : public Person { /* . . . */ };
Person *lois = new Person;
```

```
Athlete *arnold = new Athlete;
Athlete *louganis = new Athlete;
```

#### All these expressions are true:

```
#include <typeinfo>
// . . .
if (typeid(Athlete) == typeid(*arnold))
    // arnold is an Athlete, result is true
if (typeid(*arnold) == typeid(*louganis))
    // arnold and louganis are both Athletes, result is true
if (typeid(*lois) == typeid(*arnold)) // ...
    // lois and arnold are not the same type, result is false
```

You can access the name of a type with the name() member function in the type\_info class. For example, these statements:

#### Print this:

```
Lois is a(n) Person
Arnold is a(n) Athlete
```

# **Working With Templates**

(ARM, §14) This section describes the best way to organize your template declarations and definitions in files. It also documents how to explicitly instantiate templates, using a syntax that is not in the ARM but is part of the ANSI/ISO C++ standard.

This section includes the following topics:

- <u>Declaring and Defining Templates</u>
- Instantiating a Template

# **Declaring and Defining Templates**

In a header file, declare your class functions and function templates, as shown in <u>Listing 4.8</u>.

## Listing 4.8 templ.h: A Template Declaration File

```
template <class T>
class Templ {
   T member;
public:
   Templ(T x) { member=x; }
   T Get();
};

template <class T>
T Max(T,T);
```

In a source file, include the header file and define the function templates and the member functions of the class templates. <u>Listing 4.9</u> shows you an example.

This source file is a template definition file. You'll include this file in any file that uses your templates. You do not need to add the template definition file to your project. Although this is technically a source file, you work with it as if it were a header file.

The template definition file does *not* generate code. The compiler cannot generate code for a template until you specify what values it should substitute for the templates arguments. Specifying these values is called instantiating the template. See <u>"Instantiating a Template"</u> on page 76.

## Listing 4.9 templ.cp: A Template Definition File

```
#include "templ.h"

template <class T>
T Templ<T>::Get()
{
   return member;
}

template <class T>
T Max(T x, T y)
{
   return ((x>y)?x:y);
}
```

**WARNING!** Do *not* include the original template declaration file, which ends in .h. If you include the template .h file in your source file, the compiler will generate an error saying that the function or class is undefined.

#### Providing declarations when declaring the template

CodeWarrior C++ processes any declarations in a template when the template is declared, not when it is instantiated.

Although the C++ compiler currently accepts declarations in templates that are not available when the template is declared, future versions of the compiler will not. shows some examples.

## Listing 4.10 Declarations in template declarations

```
// Names in a class template declaration have to be defined
template<typename T> struct foo {
  bar *member; // illegal (but currently accepted)
};
struct bar { };
```

```
foo<int> fi;
// Workaround: Declare all names before using them:
struct bar;
template<typename T> struct foo {
 bar *member; // OK
};
struct bar { };
foo<int> fi;
// Names in template argument dependent base classes:
template<typename T> struct foo {
   typedef T *tptr;
};
template<typename T> struct bar : foo<T> {
   tptr member; // illegal (but currently accepted)
};
// Workaround: Use qualifed name syntax:
template<typename T> struct foo {
  typedef T *tptr;
};
template<typename T> struct bar : foo<T> {
 typename foo<T>::tptr member; // OK
};
// The correct usage of typename in template argument
// dependent qualified names in some contexts:
template<class T> struct X {
  typedef X *xptr;
  xptr f();
template<class T> X<T>::xptr X<T>::f() // 'typename' missing
{
```

```
return 0;
}

// Workaround: Use 'typename':

template<class T> typename X<T>::xptr X<T>::f() // OK
{
  return 0;
}
```

## **Instantiating a Template**

The compiler cannot generate code for a template until you:

- declare the template class
- provide a template definition
- specify the data type(s) for the template

For information on the first two requirements, see <u>"Declaring and Defining Templates" on page 73.</u>

Specifying the data type(s) and other arguments for a template is called instantiating the template. CodeWarrior C++ gives you two ways to instantiate a template. You can let the compiler instantiate it automatically when you first use it, or you can explicitly create all the instantiations you'll need.

#### **Automatic instantiation**

To instantiate templates automatically, include the template definition file in all the source files that use the template, and just use the template members as you would any other type or function. The compiler automatically generates code for a template instantiation whenever it sees a new one. <u>Listing 4.11</u> shows how to automatically instantiate the templates in <u>Listing 4.8</u> and <u>Listing 4.9</u>, class Templ and class Max.

## Listing 4.11 myprog.cp: A Source File that Uses Templates

If you use automatic instantiation, the compiler may take longer to compile your program because it has to determine on its own which instantiations you'll need. Also, the object code for the template instantiations will be scattered throughout your program.

## **Explicit instantiation**

To instantiate templates explicitly, include the template definition file in a source file, and write a template instantiation statement for every instantiation. The syntax for a class template instantiation is

template class class-name<templ-specs>;

The syntax for a function template instantiation is

template return-type func-name<templ-specs>(arg-specs)

<u>Listing 4.12</u> shows how to explicitly instantiate the templates in <u>Listing 4.8</u> and <u>Listing 4.9</u>.

## Listing 4.12 myinst.cp: Explicitly Instantiating Templates

```
#include "templ.cp"

template class Templ<long>; // class instantiation
template long Max<long>(long,long); // function instantiation
```

When you're explicitly instantiating a function, you do not need to include in *templ-specs* any arguments that the compiler can deduce from *arg-specs*. For example, in <u>Listing 4.12</u> you can instantiate Max<long>() like this:

```
template long Max<>(long, long);
  // The compiler can tell from the arguments
  // that you're instantiating Max<long>()
```

If you use explicit instantiation, the compiler compiles your program more quickly. Because the instantiations can be in one file with no other code, you can even choose to put them in a separate library.

**NOTE:** Explicit instantiation is not in the ARM but is part of the ANSI/ISO C++ standard.



# C++ and Embedded Systems

This chapter describes how to develop effective software for embedded systems using CodeWarrior C++. It also has topics that all C++ programmers may find useful for developing smaller programs.

# C++ and Embedded Systems Overview

This chapter covers the following items of concern to embedded systems programmers.

- Activating EC++
- Differences Between ANSI/ISO C++ and EC++
- Meeting EC++ Specifications With CodeWarrior
- Strategies for Smaller Code Size in C++

**NOTE:** This chapter discusses some strategies for program design for embedded systems and is not meant to be a definitive solution.

Currently, CodeWarrior C++ may be used for EC++-compatible embedded systems development, but does not include some libraries mentioned in the EC++ proposal.

# **Activating EC++**

To compile EC++ source code, make sure the **EC++ Compatibility Mode** option is on in the **C/C++ Language** settings panel.

To test for EC++ compatibility mode at compile time use the \_\_embedded\_cplusplus predefined symbol. For more information, see <u>"Predefined Symbols" on page 198.</u>

# Differences Between ANSI/ISO C++ and EC++

Several features of ANSI/ISO C++ (ANSI C++) are not present in EC++. Among the features not supported in EC++ are:

- Templates
- Libraries
- File Operations
- Localization
- Exception Handling
- Other Language Features

## **Templates**

ANSI C++ supports templates. The EC++ proposal does not include template support for class or functions.

## Libraries

The classes <string>, <complex>, <ios>, <streambuf>, <is-tream> and <ostream> are supported in Embedded C++ specifications. However only in a non-template form. All other ANSI C++ libraries including the STL-type algorithm libraries are not supported

## File Operations

There are no file operations specified in the EC++ proposed standard except for simple console input and output file types.

## Localization

There are no localization libraries in the EC++ proposed standard because of the excessive memory requirements.

## **Exception Handling**

Exception handling is not supported in the EC++ proposed standard.

## Other Language Features

The following language features are not supported. Some other minor features are also unsupported but not listed.

- mutable specified
- RTTI
- namespace
- multiple inheritance
- virtual inheritance

# Meeting EC++ Specifications With CodeWarrior

This section describes how to be compliant with the proposed Embedded C++ (EC++). These topics discuss different facets of designing software to meet the EC++ standard:

- <u>Language Related Issues</u>
- <u>Library Related Issues</u>

## **Language Related Issues**

To make sure your source code is compatible with both the ANSI/ISO C++ and EC++ standards, follow these guidelines:

- do not use RTTI (Run-Time Type Identification).
- do not use exception handling, namespaces, or other unsupported features.
- do not use multiple or virtual inheritance

Some of these C++ features, such as RTTI and exceptions, can be turned off in the compiler settings for your code. These options are

in the C++ Language settings panel, described in <u>"Setting C Compiler Options Overview"</u> on page 15.

# **Library Related Issues**

Do not refer to routines, data structures, and classes in the Metrowerks Standard Libraries for C++.

Metrowerks will explore alternative class libraries that are more suitable for use with EC++-compliant applications and may make them available in a future release.

# Strategies for Smaller Code Size in C++

When using C++ where program size may be critical, there are certain strategies that a programmer can follow to ensure optimal code size.

**NOTE:** In all strategies, reducing the size of object may affect the performance of that code.

Some of these strategies are used by the proposed Embedded C++ (EC++) uses some of these strategies as part of its specification. Other strategies apply to C++ programming in general. All of these strategies may be used by any C++ program, whether the program follows the EC++ standard or not.

In CodeWarrior, you can group these into compiler-related, language-related, and library-related steps.

## Compiler-related strategies

Compiler-related strategies rely on using compiler features to reduce the size of object code.

<u>Size Optimizations</u>—use the compiler size optimization settings

• <u>Inlining</u>—how to control and limit the effectiveness of the inline directive

#### Language-related strategies

Language-related strategies limit or avoid the use of ANSI/ISO C++ features. Although these features may make software design and maintenance easier, they often do so at the cost of affecting code size

- <u>Virtual Functions</u>—not using virtual functions reduces the size of code
- <u>Runtime Type Identification</u>—the compiler won't generate extra data if a program doesn't use Runtime Type Identification (RTTI)
- Exception Handling—while CodeWarrior C++ provides zero-overhead exception handling to provide optimum execution speed, it still generates extra object code for exception support
- Operator New—be careful not to throw an exception within the new operator
- <u>Multiple Inheritance</u>—the compiler won't generate extra data if the use of multiple inheritance isn't used

## Library-related strategies

- <u>Stream-Based Classes</u>—these classes in the Metrowerks Standard Libraries comprise a lot of object code
- <u>Alternative Class Libraries</u>—non-standard class libraries may provide a subset of the standard library's functionality with less overhead

## **Size Optimizations**

Metrowerks compilers include optimization settings for size or speed, and various levels of optimization. Choose size as your desired outcome, and the level of optimization you wish to apply.

You control optimization settings as an option in the settings for your target. The option is in the Processor settings panel.

When debugging, compile your code without any optimizations. Some optimizations disrupt the relationship between source and object code required by the debugger. Optimize your code after you have finished debugging.

See also "Setting C Compiler Options Overview" on page 15.

# **Inlining**

With CodeWarrior you can turn inlining off, allow normal inlining, auto-inline, or set the maximum depth of inlining.

Inlining may reduce or increase code size. There is no definite answer for this question. Inlining small functions can make a program smaller. In particular if you have a class library with a lot of getter/setter member functions, the code size can be quite a bit smaller with inlining on.

However, MSL C++ defines many functions as inline, and this is not good if you want minimal code size. For optimal code size when using MSL C++, turn inlining off when you build the library. If you are not using MSL C++, normal inlining and a common sense use of the keyword "inline" may improve your code size.

In CodeWarrior you control inlining as a language option in the target settings. The option is in the C/C++ Language settings panel.

When debugging your code, turn inlining off to maintain a clear correspondence between source and object code. After debugging, set the inlining level that has the best effect on your object code.

See also <u>"Inlining" on page 43.</u>

## **Virtual Functions**

For optimal code size virtual functions should not be used except when necessary. A virtual function is never dead-stripped, even if it's never called.

## **Runtime Type Identification**

If code size is an issue, do not use RTTI. RTTI generates a data table for every class, so turning this off will make the data section smaller.

The proposal for Embedded C++ does not allow runtime type identification. Turn RTTI off as a C++ language option in the target settings. The option is in the C/C++ Language settings panel.

See also "Controlling RTTI" on page 66.

# **Exception Handling**

Be selective when using C++ exception handling routines, or not use exceptions at all. CodeWarrior has a zero runtime overhead error handling mechanism. However, using exceptions still adds some code size. The exception tables (data) can get pretty big when using exception handling.

The proposal for Embedded C++ does not allow exception handling. Turn exception handling off as a C++ language option in the target settings. The option is in the C/C++ Language settings panel.

**NOTE:** The proposed ANSI/ISO standard libraries and the use of the "new" operator will require exception handling. See "Operator New" on page 85.

## **Operator New**

The C++ new operator might throw an exception or not depending on how the runtime library implements the new operator. To have it throw exceptions set \_\_throws\_bad\_alloc to 1, to have it not set \_\_throws\_bad\_alloc to 0 in the prefix file for your target and rebuild your library.

Please read your release notes or *Targeting* manual for more information.

# **Multiple Inheritance**

The code and data overhead required to implement multiple inheritance is fairly modest.

The proposal for Embedded C++ does not allow multiple inheritance.

## Virtual Inheritance

For optimal code size, do not use virtual inheritance. Virtual base classes are often complex and will add a lot of code to the constructor and destructor functions.

The proposal for Embedded C++ does not allow virtual inheritance.

## **Stream-Based Classes**

The Metrowerks Standard Library (MSL) C++ stream-based classes will initialize several instances of direct and indirect objects. When code size is critical, do not use any stream-based classes. The stream-based classes include standard input (cin), standard output (cout), and standard error (cerr). There are wide-character equivalents for the normal input and output routines as well. Unless there is a great need for these classes, use standard C input and output functions instead.

In addition to the standard C++ stream classes, there are string streams for in-core formatting that will also evoke a heavy overhead and should be avoided. If size is critical, use C's sprintf or sscanf functions instead.

The proposal for Embedded C++ does not allow for templatized classes or functions. MSL is compliant with the ANSI/ISO proposed standards that are based on templates.

## **Alternative Class Libraries**

Metrowerks Standard Library (MSL) C++ is based on the ANSI/ISO proposed C++ standard. This C++ Standard is implemented using templates, which have a large initial overhead for specialization.

To avoid this overhead, you may want to devise your own vector, string, or other utility classes that you use commonly. In addition, there are other class libraries available, such as the NIH's (National Institute of Health) Class Library. These may be more suitable for your work.

If you do use an alternative library, keep in mind possible problems with virtual inheritance, RTTI, or other causes of larger code size that we described above.



# Pragmas and Symbols

This chapter describes the pragmas and predefined symbols available with the Metrowerks C/C++ compiler.

# **Pragmas and Symbols Overview**

You set compiler options for an entire project by changing the settings in the <u>C/C++ Language Panel</u>. You can also control how the compiler compiles your code from within your code, using pragmas.

Most of the pragmas correspond to options in the <u>C/C++ Language Panel</u>, or other settings panels such as the 68K Processor panel, the PowerPC processor panel, and so forth.

Typically, you use the settings panels to set the options for most of your code and use pragmas to change the options for special cases. For example, with the <a href="C/C++ Language Panel">C/C++ Language Panel</a>, you can turn off a time-consuming optimization and, with a pragma, turn it on only for the code it helps most.

**TIP:** If you use Metrowerks command-line tools, such as those for MPW or Be OS, see the *Command-Line Tools* manual for information on how to duplicate the effect of #pragma statements using command-line tool options.

The sections in this chapter are:

- <u>Pragma Syntax</u>—explains pragma syntax
- <u>Pragma Scope</u>—the range of a pragma

- Pragmas—lists each pragma
- <u>Predefined Symbols</u>—lists ANSI and CodeWarrior symbols
- <u>Checking Options</u>—explains how to determine the current setting of most pragmas and options

# **Pragmas**

This section describes how to use pragmas and lists and explains each pragma.

These topics describe how to use pragmas:

- Pragma Syntax
- Pragma Scope

# **Pragma Syntax**

Most pragmas have this syntax:

```
#pragma option-name on | off | reset
```

Generally, use on or off to change the option's setting, and then use reset to restore the option's original setting, as shown below:

```
#pragma profile off
  // If the option Generate Profiler Calls is on,
  // turns it off for these functions.

#include <smallfuncs.h>

#pragma profile reset
  // If the option Generate Profiler Calls was originally on,
  // turns it back on. Otherwise, the option remains off
```

Suppose that you use #pragma profile on instead of #pragma profile reset. If you later turn off **Generate Profiler Calls** from the Preference dialog, that pragma turns it on. Using reset ensures

that you don't inadvertently change the settings in the Project Settings dialog.

# **Pragma Scope**

In general, the scope of a pragma setting is limited to a single file.

As discussed in <u>Pragma Syntax</u>, you should use on, or off after the pragma's name to change a pragma's setting to the condition you want. After you have set the pragma to the desired state, all code after that point is compiled with that setting until either:

- change the setting with on, off, or (preferred) reset
- you reach the end of the file

At the beginning of each file, the compiler reverts to the project or default settings.

Pragma settings are not stored in a precompiled header file. In other words, you can modify compiler settings inside a precompiled header, but the change affects the code within that file only. The settings that were active at the end of the precompiled header file are lost and have to be set up again.

The settings for an item that is declared in a precompiled header file (such as data or a function) are saved and restored when the precompiled header file is included.

For example, this code says that the variable xxx is a far variable.

```
// in file pch.h

#pragma far_data on
extern int xxx;
```

Now, assume a file includes this as a precompiled header.

```
// in file test.c
#pragma far_data off // far data is off
#include "pch.pch" // this file set far_data on
```

// far\_data is still 'off' but xxx is still a far variable

The pragma setting still works within the header file, even though the source file including the header has a different setting.

## a6frames

**Description** 

Controls the generation of stack frames based on the A6 register.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma a6frames on | off | reset

Remarks

This pragma applies to Mac OS on 68K programming only.

If this pragma is on, the compiler generates A6 stack frames which let debuggers trace through the call stack and find each routine. Many debuggers, including the Metrowerks debugger and Jasik's The Debugger, require these frames. If this pragma is off, the compiler does not generate these frames, so the generated code is smaller and faster.

This is the code that the compiler generates for each function, if this pragma is on:

LINK #nn,A6 UNLK A6

This pragma corresponds to **Generate A6 Stack Frames** option in the 68K Linker settings panel. To check whether this option is on, use \_\_option (a6frames), described in <u>"Checking Options" on page 202.</u>

# align

Description

Specifies how to align data.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma options align= alignment

**Remarks** 

This pragma applies to Mac OS programming only.

This pragma specifies how to align structs and classes, where *alignment* can be one of the following values:

If <i>alignment</i> is	The compiler
ii aligiiilielit is	The compiler
mac68k	Aligns every field on a 2-byte boundaries, unless a field is only 1-byte long. This is the standard alignment for 68K Macintosh computers.
mac68k4byte	Aligns every field on 4-byte boundaries.
power	Align every field on its natural boundary. This is the standard alignment for Power Macintosh computers. For example, it aligns a character on a 1-byte boundary and a 16-bit integer on a 2-byte boundary. The compiler applies this alignment recursively to structured data and arrays containing structured data. So, for example, it aligns an array of structured types containing an 4-byte floating point member on an 4-byte boundary.
native	Aligns every field using the standard alignment. It is equivalent to using mac68k for 68K Macintosh computers and power for Power Macintosh computers.

If alignment is	The compiler
packed	Aligns every field on a 1-byte boundary. It is not available in any settings panel. This alignment will cause your code to crash or run slowly on many platforms. <i>Use it with caution</i> .
reset	Resets the option to the value in the previous #pragma options align statement, if there is one, or to the value in the 68K or PPC Processor settings panel.

Note there is a space between options and align.

This pragma corresponds to the **Struct Alignment** option in the 68K Processor settings panel.

# align\_array\_members

### Description

Controls the alignment of arrays within struct and class data.

## Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

#### **Prototype**

#pragma align\_array\_members on | off | reset

#### Remarks

This pragma applies to Mac OS programming only.

This option lets you choose how to align an array in a struct or class. If this option is on, the compiler aligns all array fields larger than a byte according to the setting of the **Struct Alignment** option. If this option is off, the compiler doesn't align array fields.

## Listing 6.1 Choosing how to align arrays

```
char arr[4];  // offset==1 (char aligned)
};
#pragma align_array_members on
#pragma align mac68k
struct X2 {
       char c;
                       // offset==0
       char arr[4];  // offset==2 (2-byte align)
};
#pragma align_array_members on
#pragma align mac68k4byte
struct X3 {
       char c;
                       // offset==0
       char arr[4];
                      // offset==4 (4-byte align)
};
```

To check whether this option is on, use \_\_option (align\_array\_members), described in <u>"Checking Options" on page 202.</u> By default, this option is off.

# always\_inline

Description

Controls the use of inlined functions.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

#### **Prototype**

```
#pragma always_inline on | off | reset
```

#### Remarks

When this option is on, the compiler attempts to inline every function declared with the inline keyword.

This pragma doesn't correspond to any settings panel option. To check whether this option is on, use \_\_option (always\_inline), described in <u>"Checking Options" on page 202</u>.

## ANSI\_strict

**Description** Controls the use of non-standard language features.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

```
#pragma ANSI_strict on | off | reset
```

Remarks

The common ANSI extensions are the following. If you turn on the pragma ANSI\_strict, the compiler generates an error if it encounters any of these extensions.

• C++-style comments. For example:

```
a = b;  // This is a C++-style comment
```

• Unnamed arguments in function definitions. For example:

• A # token not followed by an argument in a macro definition. For example:

```
#define add1(x) #x #1
    /* OK, if ANSI_strict is off,
    but probably not what you wanted:
    add1(abc) creates "abc"#1 */

#define add2(x) #x "2"
    /* ALWAYS OK: add2(abc) creates "abc2" */
```

• An identifier after #endif. For example:

```
#ifdef __MWERKS__
    /* . . . */
#endif /*__MWERKS__*/    /* ALWAYS OK */
```

This pragma corresponds to the **ANSI Strict** option in the <u>C/C++</u> <u>Language Panel</u>. To check whether this option is on, use \_\_option (ANSI\_strict), described in <u>"Checking Options" on page 202</u>.

# arg\_dep\_lookup

**Description** Controls C++ argument-dependent name lookup.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
1				

**Prototype** 

#pragma arg\_dep\_lookup on | off | reset

Remarks

When this option is on, the C++ compiler uses argument-dependent name lookup. By default this option is on.

This pragma doesn't correspond to any settings panel option. To check whether this option is on, use \_\_option (arg\_dep\_lookup), described in <u>"Checking Options" on page 202.</u>

## ARM\_conform

**Description** 

Controls the use of non-ARM language features.

Compatibility

This pragma is compatible with the following platform targets:

68K Powe	erPC NEC V800	Intel x86	MIPS
----------	---------------	-----------	------

**Prototype** 

#pragma ARM\_conform on | off | reset

Remarks

When pragma ARM\_conform is on, the compiler generates an error when it encounters certain ANSI C++ features that conflict with the

C++ specification in *The Annotated C++ Reference Manual*. Use this option only if you must make sure that your code strictly follows the specification in *The Annotated C++ Reference Manual*.

Turning on this pragma prevents you from doing the following

• Using protected base classes. For example:

```
class X {};
class Y : protected X {}; // OK if ARM_conform is off.
```

 Changing the syntax of the conditional operator to let you use assignment expressions without parentheses in the second and third expressions. For example:

```
i ? x=y : y=z // OK if ARM_conform is off.
i ? (x=y):(y=z) // ALWAYS OK
```

• Declaring variables in the conditions of if, while and switch statements. For example:

```
while (int i=x+y) { . . . } // OK if ARM_conform is off.
```

Turning on this option *allows* you to do the following:

• Using variables declared in the condition of an if statement after the if statement. For example:

```
for(int i=1; i<1000; i++) \{ /* . . . */ \} return i; // OK if ARM_conform is on.
```

This pragma corresponds to the **ARM Conformance** option in the C/C++ Language Panel. To check whether this option is on, use \_\_option (ARM\_conform), described in <u>"Checking Options" on page 202.</u>

## auto\_inline

**Description** Controls the selection of which functions to inline.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

#pragma auto\_inline on | off | reset

#### Remarks

If this pragma is on, the compiler, automatically picks functions to inline for you

Note that if either the **Don't Inline** option (<u>"Inlining" on page 43</u>) or the dont\_inline pragma (<u>"dont inline" on page 115</u>) is on, the compiler ignores the setting of the auto\_inline pragma and doesn't inline any functions.

This pragma corresponds to the **Auto-Inline** option of the **Inlining** menu the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (auto\_inline), described in <u>"Checking Options" on page 202.</u>

## bool

#### **Description**

Controls if bool, true, and false are treated as keywords or not.

#### Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86	MIPS
--------------------------------	------

#### **Prototype**

#pragma bool on | off | reset

#### Remarks

When this pragma is on, you can use the standard C++ bool type to represent true and false. Turn this pragma off if recognizing bool, true, or false as keywords would cause problems in your program.

This pragma corresponds to the **Enable bool Support** option in the <u>C/C++ Language Panel</u>, described in <u>"Using the bool Type" on page 67</u>. To check whether this option is on, use <u>option(bool)</u>, described in <u>"Checking Options" on page 202</u>. By default, this option is off.

# check\_header\_flags

Description

Sets if checking should be done to ensure that a precompiled header's data matches a project's target settings.

Compatibility

This pragma is compatible with the following platform targets:

|--|

**Prototype** 

#pragma check\_header\_flags on | off | reset

Remarks

This pragma affects precompiled headers only.

When this pragma is on, the compiler makes sure that the precompiled header's preferences for double size (8-byte or 12-byte), int size (2-byte or 4-byte) and floating point math correspond to the build target's settings. If they do not match, the compiler generates an error.

If your precompiled header file has settings that are independent from those in the project, turn this pragma off. If your precompiled header depends on these settings, turn this pragma on.

This pragma does not correspond to any option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use <u>\_\_option</u> (check\_header\_flags), described in <u>"Checking Options" on page 202</u>. By default, this pragma is off.

## code\_seg

Description

Specifies the segment into which code is placed.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
0 0 2 2	-000	1120 1000		11110

Prototype #pragma code\_seg(name)

**Remarks** This pragma designates the segment into which compiled code is

placed. The *name* is a string specifying the name of the code seg-

ment. For example, the pragma

#pragma code\_seg(".code")

places all subsequent code into a segment named.code.

## code68020

**Description** Controls object code generation for Motorola 680x0 (and higher)

processors.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 M	IPS
----------------------------------	-----

**Prototype** 

#pragma code68020 on | off | reset

Remarks

This pragma applies to 68K programming only.

When this option is on, the compiler generates code that's optimized for the MC68020. The code runs on a Power Macintosh or a Macintosh with a MC68020 or MC68040. The code does crash on a Macintosh with a MC68000. When this option is off, the compiler generates code that will run on any Macintosh.

**WARNING!** Do not change this option's setting within a function definition.

Before your program runs code optimized for the MC68020, use the gestalt() function to make sure the chip is available. For more information on gestalt(), see Chapter "Gestalt Manager" in *Inside Macintosh: Operating System Utilities*.

In the Mac OS compiler, this option is off by default.

This pragma corresponds to the **68020 Codegen** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (code68020), described in <u>"Checking Options" on page 202</u>.

## code68881

#### **Description**

Controls object code generation for Motorola 68881 (and higher) math coprocessors.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

#pragma code68881 on | off | reset

#### Remarks

This pragma applies to 68K programming only.

When this option is on, the compiler generates code that's optimized for the MC68881 floating-point unit (FPU). This code runs on a Macintosh with an MC68881 FPU, MC68882 FPU, or a MC68040 processor. (The MC68040 has a MC68881 FPU built in.) The code does not run on a Power Macintosh, a Macintosh with an MC68LC040, or a Macintosh with any other processor and no FPU. When this option is off, the compiler generates code that will run on any Macintosh.

**WARNING!** If you use the code68881 pragma to turn this option on, place it at the beginning of your file, before you include any files and declare any variables and functions.

Before your program runs code optimized for the MC68881, use the gestalt() function to make sure an FPU is available. For more information on gestalt(), see Chapter "Gestalt Manager" in *Inside Macintosh: Operating System Utilities*.

This pragma corresponds to the **68881 Codegen** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (code68881), described in <u>"Checking Options" on page 202.</u>

## cplusplus

**Description** 

Specifies if subsequent source code should be translated as C or C++ source code.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma cplusplus on | off | reset

Remarks

When this pragma is on, the compiler compiles the code that follows as C++ code. When this option is off, the compiler uses the suffix of the filename to determine how to compile it. If a file's name ends in .cp, .cpp, or .c++, the compiler automatically compiles it as C++ code. If a file's name ends in .c, the compiler automatically compiles it as C code. You need to use this pragma only if a file contains a mixture of C and C++ code.

This pragma corresponds to the **Activate C++ Compiler** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (cplusplus), described in <u>"Checking Options" on page 202.</u>

# cpp\_extensions

Description

Controls language extensions to ANSI/ISO C++.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
1 00K	POWELLC	NEC VOOD	INCEL YOU	MIFS

**Remarks** If this option is on, it enables these extensions to the ANSI C++ standard:

• Anonymous structs. For example:

```
#pragma cpp_extensions on
void foo()
{
  union {
    long hilo;
    struct { short hi, lo; }; // annonymous struct
  };
  hi=0x1234;
  lo=0x5678; // hilo==0x12345678
}
```

• Unqualified pointer to a member function. For example:

```
#pragma cpp_extensions on
struct Foo { void f(); }
void Foo::f()
{
  void (Foo::*ptmf1)() = &Foo::f; // ALWAYS OK

  void (Foo::*ptmf2)() = f; // OK, if cpp_exptensions is on.
}
```

This pragma does not correspond to any option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use the <u>option</u> (<u>cpp\_extensions</u>), described in <u>"Checking Options"</u> on page <u>202</u>. By default, this option is off.

## d0\_pointers

Description

Specifies which register should be used to hold function result pointers.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

#### **Prototype**

#pragma d0\_pointers

#### Remarks

This pragma applies to 68K programming only.

This pragma lets you choose between two calling conventions: the convention for MPW and Macintosh Toolbox routines and the convention for Metrowerks C and C++ routines. In the MPW and Macintosh Toolbox calling convention, functions return pointers in the register DO. In the Metrowerks C and C++ convention, functions return pointers in the register AO.

When you declare functions from the Macintosh Toolbox or a library compiled with MPW, turn on the d0\_pointers pragma. After you declare those functions, turn off the pragma to start declaring or defining Metrowerks C and C++ functions.

In <u>Listing 6.2</u>, the Toolbox functions in Sound.h return pointers in D0 and the user-defined functions in Myheader.h use A0.

## Listing 6.2 Using #pragma pointers\_in\_A0 and #pragma pointers\_in\_D0

```
#pragma d0_pointers on  // set for Toolbox calls
#include <Sound.h>
#pragma d0_pointers reset // set for my routines
#include "Myheader.h"
```

The pragmas pointers\_in\_A0 and pointers\_in\_D0 have much the same meaning as d0\_pointers and are available for background compatibility. The pragma pointers\_in\_A0 corresponds to #pragma d0\_pointers off and the pragma pointers\_in\_D0 corresponds to #pragma d0\_pointers on. The pragma d0\_pointers is recommended for new code since it supports the reset argument. For more information, see "pointers in A0, pointers in D0" on page 159.

This pragma does not correspond to any option in the 68K Processor settings panel. To check whether this option is on, use the \_\_option (d0\_pointers), described in <u>"Checking Options" on page 202.</u>

## data\_seg

**Description** Ignored, but included for compatibility with Microsoft compilers.

**Compatibility** This pragma is compatible with the following platform targets:

68K Power	PC NEC V800	Intel x86	MIPS
-----------	-------------	-----------	------

Prototype #pragma data\_seg(name)

**Remarks** Ignored. Included for compatibility with Microsoft. It designates the segment into which initialized is placed. The *name* is a string specifying the name of the data segment. For example, the pragma

data\_seg(".data")

places all subsequent data into a segment named .data.

## def\_inherited

**Description** Controls the use of the inherited keyword.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Remarks** This option allows the use of the inherited keyword in C++ programming. The default is off.

**NOTE:** The inherited keyword is not supported by the ANSI/ISO C++ standard and is only implemented for single inheritance with CodeWarrior C++.

To check whether this option is on, use the \_\_option (def\_inherited), described in <u>"Checking Options" on page 202.</u>

## defer\_codegen

**Description** 

Controls the inlining of functions that haven't been compiled yet.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

#pragma defer\_codegen on | off | reset

#### Remarks

This option allows inlining of inline and auto-inline functions that are called before their definition:

```
#pragma defer_codegen on
#pragma auto_inline on

extern void f();
extern void g();

main()
{
  f(); // will be inlined
  g(); // will be inlined
}

inline void f() {}

void g() {}
```

**NOTE:** The compiler will need more memory when this option is selected.

To check whether this option is on, use the \_\_option (defer\_codegen), described in <u>"Checking Options" on page 202.</u>

## define section

#### **Description**

Arranges object code into sections.

## Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

#pragma define\_section sname istr [ustr] [addrmode]
[accmode]

#### Remarks

This sophisticated and powerful pragma lets you arrange compiled object code into predefined sections and sections you define.

#### The parameters are:

• *sname*—identifier by which this user-defined section is referenced in the source.

#### For example:

```
#pragma section sname begin
or
__declspec(sname)
```

- istr—section name string for initialized data assigned to sname, such as.data (applies to uninitialized data if ustr is omitted)
- *ustr*—elf section name for *uninitialized* data assigned to sname
- addrmode—indicates how the section is addressed. It can be one of the following
  - standard—32-bit absolute address
  - near\_absolute—16-bit absolute address
  - far\_absolute—32-bit absolute address
  - near\_code—16-bit offset from TP

- far\_code—32-bit offset from TP
- near data—16-bit offset from GP
- far\_data—32-bit offset from GP
- *accmode*—indicates the attributes of the section. It can be one of the following:
  - R—readable
  - RW—readable and writable
  - RX—readable and executable
  - RWX—readable, writable, and executable

The default value for ustring is the same as istring. The default value for addrmode is "standard". The default value for accmode is "RWX".

The compiler predefines the following common MIPS sections in absolute addressing mode (<u>Table 6.1</u>).

### Table 6.1 MIPS predefined sections

```
#pragma define_section text ".text" far_absolute RX
#pragma define_section data ".data" ".bss" far_absolute RW
#pragma define_section sdata ".sdata" ".sbss" near_data RW
#pragma define_section const ".rodata" far_absolute R
```

In addition, the following are reserved for the C++ implementation (<u>Table 6.2</u>).

### Table 6.2 MIPS predefined sections for C++

```
#pragma define_section exception ".exception" far_absolute R
#pragma define_section exceptlist ".exceptix" far_absolute R
#pragma define_section vtables ".vtables" far_absolute R
```

The compiler predefines the following common MIPS sections in PID addressing mode (<u>Table 6.3</u>).

Table 6.3 MIPS predefined sections in PID addressing mode

```
#pragma define_section text ".text" far_absolute RX
#pragma define_section data ".data" ".bss" far_data RW
#pragma define_section sdata ".sdata" ".sbss" near_data RW
#pragma define_section const ".rodata" far_absolute R
#pragma define_section exception ".exception" far_ data R
#pragma define_section exceptlist ".exceptix" far_ data R
#pragma define_section vtables ".vtables" far_ data R
```

The compiler predefines the following common MIPS sections in PIC addressing mode (<u>Table 6.4</u>).

Table 6.4 MIPS predefined sections in PIC addressing mode

```
#pragma define_section text ".text" far_code RX

#pragma define_section data ".data" ".bss" far_absolute RW

#pragma define_section sdata ".sdata" ".sbss" near_data RW

#pragma define_section const ".rodata" far_code R

#pragma define_section exception ".exception" far_absolute R

#pragma define_section exceptlist ".exceptix" far_absolute R

#pragma define_section vtables ".vtables" far_absolute R
```

The compiler predefines the following common V810/V830 sections (<u>Table 6.5</u>).

Table 6.5 Predefined sections for NEC V810 and V830 processors

```
#pragma define_section text ".text" far_code RX
#pragma define_section data ".data" ".bss" far_data RW
#pragma define_section sdata ".sdata" ".sbss" near_data RW
#pragma define_section itext ".itext" far_absolute RX
#pragma define_section const ".const" far_absolute R
#pragma define_section sconst ".sconst" near_absolute R
#pragma define_section sedata ".sedata" ".sebss" near_absolute RW
#pragma define_section sidata ".sidata" near_absolute RW
#pragma define_section cdata1 ".cdata1" far_absolute RW
#pragma define_section cdata2 ".cdata2" far_absolute RW
#pragma define_section udata1 ".udata1" far_absolute RW
#pragma define_section udata1 ".udata1" far_absolute RW
#pragma define_section udata2 ".udata2" far_absolute RW
#pragma define_section udata2 ".udata2" far_absolute RW
#pragma define_section udata2 ".udata2" far_absolute RW
#pragma define_section udata3 ".udata3" far_absolute RW
#pragma define_section udata3 ".udata3" far_absolute RW
```

In addition, the following are reserved for the C++ implementation (<u>Table 6.6</u>):

Table 6.6 Predefined sections for NEC V810 and V830 processors (C++)

```
#pragma define_section exception ".exception" far_data R
#pragma define_section exceptlist ".exceptlist" far_data R
#pragma define_section vtables ".vtables" far_data R
#pragma define_section string ".string" far_data RW
#pragma define_section cstring ".cstring" far_data R
```

#pragma define\_section can also be used to redefine the attributes of these existing sections:

1. You can force all data to be addressed using 16-bit absolute addresses using

#pragma define\_section data ".data" near\_absolute

2. You can force exception tables to be addressed using 32-bit TP-relative using

#pragma define\_section exceptlist ".exceptlist" far\_code
#pragma define\_section exception ".exception" far\_code

If you're going to do this, it is best to put these #pragmas in a prefix file or some other header that will be #included by all source files in your program.

**NOTE:** Any section that is user-defined in the compiler must be mapped to an appropriate segment in the ELF linker's **Section Mappings** settings panel:

**NEV V800** Sections defined near\_absolute must be assigned to a segment whose address is in the ranges 00000000:00007FFF and FFFFF8000:FFFFFFFF. Sections defined near\_code or far\_code must be assigned to the same segment as .text. Sections defined near\_data or far\_data'must be assigned to the same segment as .data

### direct destruction

This pragma is no long available.

### direct\_to\_som

**Description** Controls the generation of SOM object code.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma direct\_to\_som on | off | reset

Remarks

This pragma is available for Mac OS using C++ only.

This pragma lets you create SOM code directly in the CodeWarrior IDE. SOM is an integral part of OpenDoc. For more information, see *Targeting Mac OS*.

Note that when you turn on this pragma, Metrowerks C/C++ automatically turns on the **Enums Always Int** option in the C/C++ Language Panel, described in "Enumerated Types" on page 33.

This pragma corresponds to the **Direct to SOM** menu in the C/C++ Language Panel. Selecting **On** from that menu is like setting this pragma to on and setting the SOMCheckEnviornment pragma to off. Selecting **On with Environment Checks** from that menu is like setting both this pragma and SOMCheckEnviornment to on. Selecting **off** from that menu is like setting both this pragma and SOMCheckEnviornment to off. For more information on SOMCheckEnviornment see "SOMCheckEnvironment" on page 177.

To check whether this option is on, use the \_\_option (<u>direct to SOM</u>). See <u>"Checking Options" on page 202.</u> By default, this pragma is off.

### disable\_registers

**Description** 

Controls compatibility for the ANSI/ISO function setjmp().

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

Prototype #pragma disable\_registers on | off | reset

Remarks

If this option is on, the compiler turns off certain optimizations for any function that calls setjmp(). It disables global optimization and does not store local variables and arguments in registers. These changes ensure that all local variables will have up-to-date values.

**NOTE:** This option disables register optimizations in functions that use PowerPlant's TRY and CATCH macros but *not* in functions that use the ANSI-standard try and catch statements. The TRY and CATCH macros use  $\mathtt{setjmp}()$ , but the try and catch statements are implemented at a lower level and do not use  $\mathtt{setjmp}()$ .

For Mac OS, this pragma mimics a feature that's available in THINK C and Symantec C++. Use this pragma only if you're porting code that relies on this feature, since it drastically increases your code's size and decreases its speed. In new code, declare a variable to be volatile if you expect its value to persist across set jmp() calls.

This pragma does not correspond to any option in the PowerPC or NEC V800 settings panels. To check whether this option is on, use the \_\_option (disable\_registers), described in <u>"Checking Options" on page 202.</u> By default, this option is off.

## dollar\_identifiers

Description

Controls use of dollar signs (\$) in identifiers.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

**Prototype** 

#pragma dollar\_identifiers on | off | reset

Remarks

When this pragma is on, the compiler accepts dollar signs (\$) in identifiers. When this option is off, the compiler issues an error if it encounters anything but underscores, alphabetic, and numeric characters in an identifier.

The default for this pragma is off.

This pragma does not correspond to any settings panel option. To check whether this option is on, use the \_\_option (dollar\_identifiers), described in "Checking Options" on page 202.

### dont\_inline

**Description** 

Controls the generation of inline functions.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma dont\_inline on | off | reset

Remarks

If the pragma dont\_inline is on, the compiler doesn't inline any function calls, even functions declared with the inline keyword or member functions defined within a class declaration. Also, it doesn't automatically inline functions, regardless of the setting of the auto\_inline pragma, described in <u>"auto\_inline" on page 98</u>. If this option is off, the compiler expands all inline function calls.

This pragma corresponds to the **Don't Inline** option of the **Inlining** menu the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (dont\_inline), described in <u>"Checking Options" on page 202.</u>

### dont\_reuse\_strings

**Description** 

Specifies if each string literal should be stored separately in the string pool.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** #pragma dont\_reuse\_strings on | off | reset

Remarks

If the pragma dont\_reuse\_strings is on, the compiler stores each string literal separately. If this pragma is off, the compiler stores only one copy of identical string literals. This pragma helps you save memory if your program contains lots of identical string literals which you do not modify.

For example, take this code segment:

```
char *str1="Hello";
char *str2="Hello"
*str2 = 'Y';
```

If this option is on, str1 is "Hello" and str2 is "Yello". If this option is off, both str1 and str2 are "Yello".

This pragma corresponds to the **Don't Reuse Strings** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (dont\_reuse\_strings), described in <u>"Checking Options" on page 202.</u>

## ecplusplus

Description

Controls the use of embedded C++ features.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma ecplusplus on | off | reset

Remarks

If this option is on the C++ compiler disables the non-EC++ features of ANSI C++ such as templates, multiple inheritance, and so on. See <u>"C++ and Embedded Systems" on page 79</u> for more information on Embedded C++ support in CodeWarrrior C/C++.

This pragma doesn't correspond to any settings panel option. To check whether this option is on, use \_\_option (ecplusplus), de-

scribed in <u>"Checking Options" on page 202.</u> By default this pragma is off.

### **EIPC EIPSW**

Description

Controls the saving of processor information for interrupt functions.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

**Prototype** 

#pragma EIPC\_EIPSW on|off|reset

Remarks

If this option is in effect when compiling an interrupt function, the compiler will also save or restore the EIPC and EIPSW. It is then safe to enable additional interrupts by calling \_\_EIEP().

This pragma doesn't correspond to any settings panel option. To check whether this option is on, use \_\_option (dont\_reuse\_strings), described in "Checking Options" on page 202.

## enumsalwaysint

**Description** 

Specifies the size of enumerated types.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma enumsalwaysint on | off | reset

Remarks

When pragma enumsalwaysint is on, the C or C++ compiler makes an enumerated types the same size as an int. If an enumerated constant is larger than int, the compiler generates an error. When the pragma is off, the compiler makes an enumerated type the size of any integral type. It chooses the integral type with the size that most closely matches the size of the largest enumerated

constant. The type could be as small as a char or as large as a long int.

### For example:

```
enum SmallNumber { One = 1, Two = 2 };
    /* If enumsalwaysint is on, this type will
    be the same size as a char.
    If the pragma is off, this type will be
    the same size as an int. */

enum BigNumber
    { ThreeThousandMillion = 3000000000 };
    /* If enumsalwaysint is on, this type will
    be the same size as a long int.
    If this pragma is off, the compiler may
    generate an error. */
```

For more information on how the compiler handles enumerated types, see <u>"Enumerated Types"</u> on page 33.

This pragma corresponds to the **Enums Always Int** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (enumsalwaysint), described in <u>"Checking Options"</u> on page 202.

## exceptions

**Description** 

Controls the availability of C++ exception handling.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma exceptions on | off | reset

Remarks

If you turn on this pragma, you can use the try and catch statements to perform exception handling. If your program doesn't use

exception handling, turn this option off to make your program smaller.

You can throw exceptions across any code that's compiled by the CodeWarrior 8 (or later) Metrowerks C/C++ compiler with the **Enable C++ Exceptions** option turned on. You cannot throw exceptions across the following:

- Macintosh Toolbox function calls
- Libraries compiled with the **Enable C++ Exceptions** option turned off
- Libraries compiled with versions of the Metrowerks C/C++ compiler earlier than CodeWarrior 8
- Libraries compiled with Metrowerks Pascal or other compilers.

If you throw an exception across one of these, the code calls terminate() and exits.

This pragma corresponds to the **Enable C++ Exceptions** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (exceptions), described in <u>"Checking Options" on page 202.</u>

## export

#### **Description**

Controls items to export from a module.

#### Compatibility

This pragma is compatible with the following platform targets:

68K PowerI	NEC V800	Intel x86	MIPS
------------	----------	-----------	------

#### **Prototype**

#pragma export on | off | reset | list names

#### Remarks

This pragma applies to Mac OS programming only.

The pragma export gives you another way to export symbols besides using a .exp file. To export symbols with this pragma, choose **Use #pragma** from the **Export Symbols** menu in the PPC PEF or CFM68K settings panel. Then turn on this pragma to export vari-

ables and functions declared or defined in this file. If you choose any other option from the **Export Symbols** menu, the compiler ignores this pragma.

If you want to export all the functions and variables declared or defined within a certain range, use #pragma export on at the beginning of the range and use #pragma export off at the end of the range. If you want to export all the functions and variables in a list, use #pragma export list. If you want to export a single variable or function, use \_\_declspec(export) at the beginning of the declaration

For example, this code fragment use #pragma export on and off to export the variable w and the functions al() and bl():

```
#pragma export on
int al(int x, double y);
double bl(int z);
int w;
#pragma export off
```

This code fragment use #pragma export list to export the symbols:

```
int al(int x, double y);
double bl(int z);
int w;
#pragma export list al, bl, w
```

This code fragment uses \_\_declspec(internal) to export the symbols:

```
__declspec(export) int al(int x, double y);
__declspec(export) double bl(int z);
__declspec(export) int w;
```

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option(export), described in "Checking Options" on page 202.

# extended\_errorcheck

**Description** 

Controls the issuing of warnings for possible unintended logical errors.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

```
#pragma extended_errorcheck on | off | reset
```

Remarks

If the pragma extended\_errorcheck is on, the C compiler generates a warning (not an error) if it encounters one of the following:

• A non-void function that does not contain a return statement. For example, this would generate a warning:

#### This would be OK:

```
void main()
{
   printf ("hello world\n");
}
```

• Assigning an integer or floating-point value to an enum type. For example:

**NOTE:** Both of these are always errors in C++.

The C/C++ compiler generates a warning if it encounters this:

• An empty return statement (return;) in a function that is not declared void. For example, this code would generate a warning:

```
int MyInit(void)
{
  int err = GetMyResources();
  if (err!=0) return; // WARNING: Empty return statement
  // . . .
}
```

#### This would be OK:

```
int MyInit(void)
{
  int err = GetMyResources();
  if (err!=0) return -1; // OK

  // . . .
}
```

This pragma corresponds to the **Extended Error Checking** option in the <u>C/C++ Warnings Panel</u>. To check whether this option is on, use \_\_option (extended\_errorcheck), described in <u>"Checking Options"</u> on page 202.

### far\_code, near\_code, smart\_code

**Description** Specify the kind of addressing to use for executable code.

### **Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

#### **Prototype**

#pragma far\_code,
#pragma near\_code,
#pragma smart\_code

#### Remarks

This pragma applies to Mac OS on 68K programming only.

These pragmas determine what kind of addressing the compiler uses to refer to functions:

- #pragma far\_code always generates 32-bit addressing, even if 16-bit addressing can be used
- #pragma near\_code always generates 16-bit addressing, even if data or instructions are out of range.
- #pragma smart\_code generates 16-bit addressing whenever possible and uses 32-bit addressing only when necessary.

For more information on these code models, see the *CodeWarrior User's Guide*.

These pragmas correspond to the **Code Model** option in the 68K Processor settings panel. The default is #pragma smart\_code.

### far\_data

#### **Description**

Controls the use of 32-bit addressing to refer to global data.

#### Compatibility

This pragma is compatible with the following platform targets:

	68K	PowerPC	NEC V800	Intel x86	MIPS
1					

#### **Prototype**

#pragma far\_data on | off | reset

#### Remarks

If this pragma is on, you can have any amount of global data since the compiler uses 32-bit addressing to refer to globals instead of 16bit addressing. Your program will also be slightly bigger and slower. this pragma is off, your global data is stored as near data and add to the 64K limit on near data. This pragma corresponds to the **Far Data** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (far\_data), described in <u>"Checking Options" on page 202</u>.

## far\_strings

Description

Controls the use of 32-bit addressing to refer to string literals.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

**Prototype** 

#pragma far\_strings on | off | reset

Remarks

If this pragma is on, you can have any number of string literals since the compiler uses 32-bit addressing to refer to string literals, instead of 16-bit addressing. Your program will also be slightly bigger and slower. If this pragma is off, your string literals are stored as near data and add to the 64K limit on near data.

This pragma corresponds to the **Far String Constants** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (far\_strings), described in <u>"Checking Options"</u> on page 202.

### far\_vtables

**Description** 

Controls the use of 32-bit addressing for C++ virtual function tables.

Compatibility

This pragma is compatible with the following platform targets:

|--|

**Prototype** 

#pragma far\_vtables on | off | reset

Remarks

This pragma applies to Mac OS on 68K programming only.

A class with virtual function members has to create a virtual function dispatch table in a data segment. If this pragma is on, that table can be any size since a the compiler uses 32-bit addressing to refer to the table, instead of 16-bit addressing. Your program will also be slightly bigger and slower. If this pragma is off, the table is stored as near data and adds to the 64K limit on near data.

This pragma corresponds to the **Far Method Tables** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (far\_vtables), described in <u>"Checking Options"</u> on page 202.

### faster\_pch\_gen

**Description** 

Controls the performance of precompiled header generation.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma faster\_pch\_gen on | off | reset

Remarks

Turning this pragma on can make writing a precompiled header much faster (depending on the header structure). Precompiled header files that are generated with this option are slightly bigger. The default is off.

This pragma does not correspond to any option in any settings panel. To check whether this option is on, use the \_\_option (faster\_pch\_gen), described in "Checking Options" on page 202.

## float\_constants

**Description** 

Controls how floating pointing constants are treated.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

Prototype #pragma float\_constants on | off | reset

Remarks

If this option is on, the compiler assumes that all unqualified floating point constant values are of type float, not double.

This pragma is useful when working with source code compiled for the AMD K6 processors.

This pragma does not correspond to any option in any settings panel. To check whether this option is on, use the \_\_option (float\_constants), described in <u>"Checking Options" on page 202.</u>

For related information, see "The "D" Constant Suffix" on page 53.

### force\_active

**Description** Controls how "dead" functions are linked.

Compatibility

This pragma is compatible with the following platform targets:

|--|

**Prototype** 

#pragma force\_active on | off | reset

Remarks

This pragma applies to Mac OS on 68K programming only.

If this option is on, the linker will not strip the following functions out of the finished application, even if the functions are never called in the program.

In Macintosh code, this option is off by default.

This pragma does not correspond to any option in any settings panel. To check whether this option is on, use the \_\_option (force\_active), described in <u>"Checking Options" on page 202.</u>

## fourbyteints

**Description** Controls

Controls the size of the int data type.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
1				

#### **Prototype**

#pragma fourbyteints on | off | reset

#### Remarks

When this option is on, the size of an int is 4 bytes. When this option is off, the size of an int is 2 byes.

This pragma corresponds to the **4-Byte Ints** option in the **68K Processor** settings panel. To check whether this option is on, use \_\_option (fourbyteints), described in <u>"Checking Options" on page 202.</u>

**NOTE:** Whenever possible, set this option from the settings panel and not from a pragma. If you must set it from a pragma, place the pragma at the beginning of your program, before you include any files or declare any functions or variables.

## fp\_contract

#### **Description**

Controls the use of special floating point instructions to improve performance.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

### **Prototype**

#pragma fp\_contract on | off | reset

#### Remarks

This pragma applies to PowerPC programming only.

If this pragma is on, the compiler uses such PowerPC instructions as FMADD, FMSUB, and FNMAD to speed up floating-point computations. However, certain computations give unexpected results when this pragma is on. For example:

```
register double A, B, C, D, Y, Z;
register double T1, T2;

A = C = 2.0e23;
B = D = 3.0e23;

Y = (A * B) - (C * D);
printf("Y = %f\n", Y);
/* prints 2126770058756096187563369299968.000000 */

T1 = (A * B);
T2 = (C * D);
Z = T1 - T2;
printf("Z = %f\n", Z); /* prints 0.000000 */
```

When this option is off, Y and Z have the same value.

This pragma corresponds to the **Use FMADD & FMSUB** option in the PPC Processor settings panel. To check whether this option is on, use \_\_option (fp\_contract), described in <u>"Checking Options"</u> on page 202.

## fp\_pilot\_traps

**Description** 

Controls floating point code generation for Palm OS.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

```
#pragma fp_pilot_traps on | off | reset
```

Remarks

This pragma controls floating point code generation. If on, the compiler makes references to Palm OS library routines to perform floating point operations.

### **function**

**Description** 

Ignored but included for compatibility with Microsoft compilers.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma function( funcname1, funcname2, ...)

Remarks

Ignored. Included for compatibility with Microsoft.

## global\_optimizer, optimization\_level

**Description** 

Controls optimization.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

**Prototype** 

#pragma global\_optimizer on | off | reset
#pragma optimization\_level 1 | 2 | 3 | 4 | 5

Remarks

These pragmas control the global optimizer performs. To turn the global optimizer on and off, use the pragma global\_optimizer. To choose which optimizations the global optimizer performs, use the pragma optimization\_level with an argument from 1 to 5. The higher the argument, the more optimizations that the global optimizer performs. If the global optimizer is turned off, the compiler ignores the pragma optimization\_level.

For more information on the optimization the compiler performs for each optimization level, refer to the *Targeting* manual for the platform you're developing for.

These pragmas correspond to the options in the **Global Optimizations** settings panel. To check whether the global optimizer is on,

use \_\_option (global\_optimizer), described in <u>"Checking Options" on page 202.</u>

### **IEEEdoubles**

**Description** 

Specifies the size of the double type.

Compatibility

This pragma is compatible with the following platform targets:

**Prototype** 

#pragma IEEEdoubles on | off | reset

Remarks

This option, along with the **68881 Codegen** option, specifies the length of a double. The table below shows how these options work:

<b>If</b> IEEEDoubles <b>is</b>	<b>and</b> code68881 <b>is</b>	Then a double is this size
on	on or off	64 bits
off	off	80 bits
off	on	96 bits

This pragma corresponds to the **8-Byte Doubles** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (IEEEdoubles), described in <u>"Checking Options" on page 202.</u>

**NOTE:** Whenever possible, set this option from the settings panel and not from a pragma. If you must set it from a pragma, place the pragma at the beginning of your program, before you include any files or declare any functions or variables.

### ignore\_oldstyle

**Description** 

Controls the recognition of function declaration that follow the convention before ANS/ISO C.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIP	S
------------------------------------	---

**Prototype** 

#pragma ignore\_oldstyle on | off | reset

Remarks

If pragma ignore\_oldstyle is on, the compiler ignores old-style function declarations and lets you prototype a function any way you want. In old-style declarations, you don't specify the types of the arguments in the argument list but on separate lines. It's the style of declaration used in the first edition of *The C Programming Language* (Prentice Hall) by Kernighan and Ritchie.

For example, this code defines a prototype for a function with an old-style declaration:

```
int f(char x, short y, float z);

#pragma ignore_oldstyle on

f(x, y, z)
char x;
short y;
float z;
{
   return (int)x+y+z;
}

#pragma ignore_oldstyle reset
```

This pragma does not correspond to an option in any settings panel. By default this option is off. To check whether this option is on, use \_\_option (ignore\_oldstyle), described in <u>"Checking Options" on page 202.</u>

### import

**Description** Controls or specifies the availability of imported symbols.

Compatibility Th

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

### **Prototype**

#pragma import on | off | reset | list names

#### Remarks

This pragma applies to Mac OS CFM programming only.

This pragma lets you import variables and functions that are in other fragments. Use this to import symbols that have been exported with the export pragma, an .exp file, or the **Export Symbols** menu in the CFM68K and PPC PEF settings panel.

If you want to import all the functions and variables declared or define within a certain range, use #pragma import on at the beginning of the range and use #pragma import off at the end of the range. If you want to import all the functions and variables in a list, use #pragma import list. If you want to import a single variable or function, use \_\_declspec(external) at the beginning of the declaration

For example, this code fragment use #pragma import on and off to import the variable w and the functions al() and bl():

```
#pragma import on
int al(int x, double y);
double bl(int z);
int w;
#pragma import off
```

This code fragment use #pragma import list to import the symbols:

```
int al(int x, double y);
double bl(int z);
```

```
int w;
#pragma import list a1, b1, w
```

And this code fragment uses \_\_declspec(import) to import the symbols:

```
__declspec(import) int al(int x, double y);
__declspec(import) double bl(int z);
__declspec(import) int w;
```

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (import), described in "Checking Options" on page 202.

### init\_seg

#### Description

Controls the order in which initialization code is executed.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

### **Prototype**

```
pragma init_seg( compiler | lib | user | "name ")
```

#### Remarks

This pragma controls the order in which initialization code is executed. The initialization code for a C++ compiled module calls constructors for any statically declared objects. For C, no initialization code is generated.

The order of initialization is

- 1.compiler
- 2.lib
- 3.user

If you specify the name of a segment, a pointer to the initialization code is placed in the designated segment. In this case, the initialization code is not called automatically: it's up to you to call it explicitly.

### inline\_depth

**Description** Controls how deeply inline function calls are expanded.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** #pragma inline\_depth(n)

#pragma inline\_depth(smart)

**Remarks** Sets the number of passes used to expand inline function calls. The number n is an integer from 0 to 1024 or the smart specifier.

The smart specifier is the default mode, with 4 passes where the passes 2-4 are limited to small inline functions. All inlineable functions are expanded if inline\_depth is set to 1-1024.

The pragmas dont\_inline and always\_inline override this pragma.

### inline\_intrinsics

**Description** Controls the inlining of intrinsic functions.

**Compatibility** This pragma is compatible with the following platform targets:

			+	
68K	PowerPC	NEC V800	Intel x86	MIPS

Prototype #pragma inline\_instrinsics on | off | reset

**Remarks** When this option is on, the compiler directly generates intrinsic functions without generating a function call.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (inline\_intrinsics), described in "Checking Options" on page 202.

### internal

**Description** 

Controls the availability of symbols outside a module.

Compatibility

This pragma is compatible with the following platform targets:

### **Prototype**

```
#pragma internal on | off | reset | list names
```

#### Remarks

This pragma applies to Mac OS CFM programming only.

This pragma lets you specify that certain variables and functions are internal and not imported. The compiler generates smaller and faster code when it calls an internal function, even if you declared it as extern.

If you want to declare all the functions and variables declared or define within a certain range as internal, use #pragma internal on at the beginning of the range and use #pragma internal off at the end of the range. If you want to declare all the functions and variables in a list as internal, use #pragma internal list. If you want to declare a single variable or function as internal, use \_\_declspec(internal) at the beginning of the declaration.

For example, this code fragment use #pragma internal on and off to declare the variable w and the functions al() and bl() as internal:

```
#pragma internal on
int al(int x, double y);
double bl(int z);
int w;
#pragma internal off
```

This code fragment uses #pragma internal list to declare the symbols as internal:

```
int al(int x, double y);
double bl(int z);
```

```
int w;
#pragma internal list a1, b1, w
```

And this code fragment uses \_\_declspec(internal) to declare the symbols as internal:

```
__declspec(internal) int al(int x, double y);
__declspec(internal) double bl(int z);
__declspec(internal) int w;
```

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (internal), described in <u>"Checking Options" on page 202.</u>

### interrupt

**Description** 

Controls the compilation of object code for interrupt routines.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma interrupt on|off|reset

Remarks

When this option is on, the compiler generates a special prologue and epilogue for these functions: all modified registers (both non-volatile and scratch registers) are saved or restored, and the function returns via RETI instead of JMP [LP].

For convenience, the compiler will also mark any interrupt function so that the linker does not dead-strip it.

### k63d

**Description** 

Controls special code generation for AMD K6 3D extensions.

Compatibility

This pragma is compatible with the following platform targets:

68K Power:	C NEC V800	Intel x86	MIPS
------------	------------	-----------	------

#### **Prototype**

#pragma k63d on | off | reset

#### Remarks

This pragma tells the x86 compiler to generate code for AMD K6 3D extensions. This option causes the compiler to generate code that will only run on processors that are equipped with the circuitry needed to execute the specialized 3D instructions.

This pragma corresponds to the **K6 3D Favored** option in the **Extended Instruction Set** menu of the **x86 CodeGen** settings panel.

**NOTE:** This #pragma generates code that is not compatible with the Intel Pentium class of microprocessors.

To learn more about this pragma, read the Targeting Win32 manual.

## k63d\_calls

#### Description

Controls use of AMD K6 3D calling conventions.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

#pragma k63d\_calls on | off | reset

### Remarks

This pragma tells the x86 compiler to generate code for AMD K6 3D and Intel MMX extensions. This option causes the compiler to generate code that will only run on processors that are equipped with the circuitry needed to execute these specialized instruction sets. This pragma generates code that requires fewer register operations at mode switching time.

This pragma corresponds to the MMX + K6 3D option in the Extended Instruction Set menu of the x86 CodeGen settings panel.

To learn more about this pragma, read the *Targeting Win32* manual.

### lib\_export

**Description** 

Controls the recognition of the export, import, and internal pragmas.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma lib\_export on | off | reset

Remarks

This pragma applies to Mac OS CFM programming only.

If this pragma is off, the compiler ignores the pragmas export, import, and internal. It is available for compatibility with previous versions of the compiler. It corresponds to the

\_\_declspec(lib\_export) type qualifier, described in <u>"ANSI Keywords Only" on page 41.</u> To check whether this option is on, use \_\_option (lib\_export), described in <u>"Checking Options" on page 202.</u>

This pragma does not correspond to an option in any settings panel.

### longlong

**Description** 

Controls the availability of the long long type.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma longlong on | off | reset

Remarks

When the longlong pragma is on, the C or C++ compiler lets you define a 64-bit integer with the type specifier long long. This is twice as large as a long int, which is a 32-bit integer. A long long can hold values from -9,223,372,036,854,775,808 to

9,223,372,036,854,775,807. An unsigned long long can hold values from 0 to 18,446,744,073,709,551,615.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (longlong), described in <u>"Checking Options" on page 202.</u>

### longlong\_enums

Description

Controls whether or not enumerated types are the size of the long long type.

#### Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

#### **Prototype**

#pragma longlong\_enums on | off | reset

#### Remarks

This pragma lets you use enumerators that large enough to be long long integers. It's ignored if the enumsalwaysint pragma is on (described in <u>"enumsalwaysint"</u> on page 117).

For more information on how the compiler handles enumerated types, see <u>"Enumerated Types" on page 33.</u>

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (longlong\_enums), described in <u>"Checking Options" on page 202.</u> By default, this option is on.

### longlong\_prepval

#### **Description**

Controls whether or not the preprocessor treats expressions of type long as long long instead.

### Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

Prototype #pragma longlong\_prepval on | off | reset

**Remarks** When this option is on, the C/C++ preprocessor treats expressions

of type long as type long long instead.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (longlong\_prepval), described in <u>"Checking Options" on page 202.</u> By default, this option is on.

## macsbug, oldstyle\_symbols

**Description** Control the generation of debugger data for MacsBug.

**Compatibility** This pragma is compatible with the following platform targets:

**Prototype** 

#pragma macsbug on | off | reset
#pragma oldstyle\_symbols on | off | reset

Remarks

This pragma applies to Mac OS on 68K programming only.

These pragmas let you choose how the compiler generates Macsbug symbols. Many debuggers, including Metrowerks debugger, use Macsbug symbols to display the names of functions and variables. The pragma macsbug lets you turn on and off Macsbug generation. The pragma oldstyle\_symbols lets you choose which type of symbols to generate. The table below shows how these pragmas work:

To do this	Use these pragmas
Do not generate Macsbug	#pragma macsbug on
symbols	

To do this	Use these pragmas		
Generate old style Macsbug symbols	<pre>#pragma macsbug on #pragma oldstyle_symbols on</pre>		
Generate new style Macsbug symbols	<pre>#pragma macsbug on #pragma oldstyle_symbols off</pre>		

These pragmas corresponds to **MacsBug Symbols** option in the 68K Linker settings panel. To check whether the macsbug pragma option is on, use \_\_option (macsbug), described in "Checking Options" on page 202. To check whether the old style pragma is on, use \_\_option (oldstyle\_symbols) described in "Checking Options" on page 202.

### mark

#### **Description**

Adds an item to the Function pop-up menu in the IDE's editor window.

#### Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

### **Prototype**

#pragma mark itemName

#### Remarks

This pragma adds *itemName* to the source file's Function pop-up menu. If you open the file in the CodeWarrior Editor and select the item from the Function pop-up menu, the editor brings you to the pragma. Note that if the pragma is inside a function definition, the item will not appear in the Function pop-up menu.

If itemName begins with "--" a menu separator appears in the IDE's function pop-up menu:

#pragma mark --

This pragma does not correspond to an option in any settings panel.

### message

**Description** Issues a text message to the user.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

Prototype #pragma message("text")

**Remarks** This pragma tells the compiler to issue a message, text, to the user.

When running under the CodeWarrior IDE, the message appears in

the Errors & Warnings window.

microsoft\_exceptions

**Description** Controls the use of Microsoft C++ exception handling.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

Prototype #pragma microsoft\_exceptions on | off | reset

**Remarks** This pragma tells the x86 compiler to generate exception handling code that is compatible with Microsoft C++ exception handling code.

To check whether this option is on, use \_\_option

(microsoft\_exceptions), described in "Checking Options" on

page 202.

microsoft\_RTTI

**Description** Controls the use of Microsoft C++ runtime type information.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma microsoft\_RTTI on | off | reset

**Remarks** 

This pragma tells the x86 compiler to generate runtime type information that is compatible with Microsoft C++.

To check whether this option is on, use \_\_option (microsoft\_RTTI), described in <u>"Checking Options" on page 202.</u>

#### mmx

**Description** 

Controls special code generation Intel MMX extensions.

Compatibility

This pragma is compatible with the following platform targets:

68K F	PowerPC NE	C V800 Inte	1 x86	MIPS
-------	------------	-------------	-------	------

**Prototype** 

#pragma mmx on | off | reset

Remarks

This pragma tells the x86 compiler to generate code for Intel MMX extensions. This option causes the compiler to generate code that will only run on processors that are equipped with the circuitry needed to execute the more than 50 specialized MMX instructions.

This pragma corresponds to the **MMX** option in the **Extended Instruction Set** menu of the **x86 CodeGen** settings panel. To check whether this option is on, use \_\_option (mmx), described in <u>"Checking Options" on page 202.</u>

To learn more about this pragma, read the *Targeting Win32* manual.

## mmx\_call

Description

Controls the use of MMX calling conventions.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma mmx\_call on | off | reset

Remarks

When this pragma is on, the compiler favors the use of MMX calling conventions.

To check whether this option is on, use \_\_option (mmx\_call), described in <u>"Checking Options" on page 202.</u>

To learn more about this pragma, read the *Targeting Win32* manual.

### mpwc

**Description** 

Controls the use Apple's MPW C calling conventions.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
1				

**Prototype** 

#pragma mpwc on | off | reset

Remarks

This pragma applies to Mac OS on 68K processors only.

When the pragma mpwc is on, the compiler does the following to be compatible with MPW C's calling conventions:

• Passes any integral argument that is smaller than 2 bytes as a sign-extended long integer. For example, the compiler converts this declaration:

int MPWfunc ( char a, short b, int c, long d, char \*e );

• To this:

long MPWfunc( long a, long b, long c, long d, char \*e );

• Passes any floating-point arguments as a long double. For example, the compiler converts this declaration:

void MPWfunc( float a, double b, long double c );

• To this:

void MPWfunc( long double a, long double b, long double c );

- Returns any pointer value in D0 (even if the pragma pointers\_in\_D0 is off).
- Returns any 1-byte, 2-byte, or 4-byte structure in D0.
- If the **68881 Codegen** option is on, returns any floating-point value in FP0.

This pragma corresponds to the **MPW C Calling Convention** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (mpwc), described in <u>"Checking Options" on page 202.</u>

# mpwc\_newline

### **Description**

Controls the use new line character convention used by Apple's MPW C.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

### **Prototype**

#pragma mpwc\_newline on | off | reset

### Remarks

If you turn on the pragma mpwc\_newline, the compiler uses the MPW conventions for the '\n' and '\r' characters. If this pragma is off, the compiler uses the Metrowerks C and C++ conventions for these characters.

In MPW, '\n' is a Carriage Return (0x0D) and '\r' is a Line Feed (0x0A). In Metrowerks C and C++, they're reversed: '\n' is a Line Feed and '\r' is a Carriage Return.

If you want to turn this pragma on, be sure you use the ANSI C and C++ libraries that were compiled with this option on. The 68K versions of these libraries are marked with an NL; for example, MSL C.68K (NL\_2i).Lib. The PowerPC versions of these libraries are marked with NL; for example, MSL C.PPC (NL).Lib.

If you turn this pragma on and use the standard ANSI C and C++ libraries, you won't be able to read and write  $\n'$  and  $\n'$  properly. For example, printing  $\n'$  brings you to the beginning of the current line instead of inserting a new line.

This pragma corresponds to the **Map Newlines to CR** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (mpwc\_newline), described in <u>"Checking Options" on page 202.</u>

# mpwc\_relax

### **Description**

Controls the compatibility of the char\* and unsigned char\* types.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

### **Prototype**

#pragma mpwc\_relax on | off | reset

#### Remarks

When you turn on this pragma, the compiler treats char\* and unsigned char\* as the same type. This option is especially useful if you're using code written before the ANSI C standard. This old source code frequently used these types interchangeably.

This option has no effect on C++ source code.

This pragma may be used to relax function pointer checking:

```
#pragma mpwc_relax on
extern void f(char *);
```

This pragma corresponds to the **Relaxed Pointer Type Rules** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, \_\_option (mpwc\_relax), described in <u>"Checking Options" on page 202.</u>

# no\_register\_coloring

### **Description**

Controls the use of a register to hold the values of more than one variable.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

#### **Prototype**

```
#pragma no_register_coloring on | off | reset
```

#### Remarks

When the no\_register\_coloring pragma is off, the compiler performs register coloring. In this optimization, the compiler lets two or more variables share a register: it assigns different variables or parameters to the same register if you do not use the variables at the same time. In this example, the compilers could place i and j in the same register:

```
short i;
int j;

for (i=0; i<100; i++) { MyFunc(i); }
for (j=0; j<1000; j++) { OurFunc(j); }</pre>
```

However, if a line like the one below appears anywhere in the function, the compiler would realize that you're using i and j at the same time and place them in different registers:

```
int k = i + j;
```

If register coloring is on while you debug your project, it may appear as though there's something wrong with the variables sharing a register. In the example above, i and j would always have the same value. When i changes, j changes in the same way. When j changes, i changes in the same way. To avoid this confusion while debugging, turn off register coloring or declare the variables you want to watch as volatile.

The pragma corresponds to the **Global Register Allocation** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (no\_register\_coloring), described in "Checking Options" on page 202. By default, this option is off.

**NOTE:** To turn off register coloring in code for a PowerPC Macintosh, use the statement #pragma global\_optimizer off. For more information, see "global optimizer, optimization level" on page 129.

See also <u>"register coloring"</u> on page 165.

# no\_static\_dtors

Description

Controls the generation of static destructors in C++

Compatibility

This pragma is compatible with the following platform targets:

68K Powe	rPC NEC V800	Intel x86	MIPS
----------	--------------	-----------	------

**Prototype** 

#pragma no\_static\_dtors on | off | reset

Remarks

When this option is on, the compiler does not generate object code for any static or global object destructors, reducing the size of the object code.

This pragma is useful for C++ programs that never exit.

The pragma doesn't correspong to an option in any settings panel. By default, this option is off. To check whether this option is on, use \_\_option (no\_static\_dtors), described in <u>"Checking Options"</u> on page 202.

### once

**Description** 

Specifies if a header file may be included more than once in the same source file.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS	
-------------------------------------	--

**Prototype** 

#pragma once [ on | off ]

Remarks

Use this pragma to ensure that the compiler includes header files only once in a source file. This pragma is especially useful in precompiled header files.

There are two versions of this pragma: #pragma once and #pragma once on. Use #pragma once in a header file to ensure that the header file is included only once in a source file. Use #pragma once on in a header file or source file to insure that any file is included only once in a source file.

This pragma does not correspond to an option in any settings panel. By default this option is off.

## only\_std\_keywords

**Description** 

Controls the use of ANSI/ISO keywords.

Compatibility

This pragma is compatible with the following platform targets:

68K I	PowerPC	NEC V800	Intel x86	MIPS
-------	---------	----------	-----------	------

**Prototype** 

#pragma only\_std\_keywords on | off | reset

Remarks

The C/C++ compiler recognizes additional reserved keywords. If you're writing code that must follow the ANSI standard strictly,

turn on the pragma only\_std\_keywords. For more information, see "ANSI Keywords Only" on page 41.

This pragma corresponds to the **ANSI Keywords Only** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (only\_std\_keywords), described in <u>"Checking Options"</u> on page 202.

# opt\_common\_subs

**Description** Controls the use of common subexpression optimization.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma opt\_common\_subs on | off | reset

Remarks

When this option is on, the compiler replaces similar redundant expressions with a single expression. For example, if two statements in a function both use the expression

the compiler generates object code that computes the expression only once and applies the resulting value to both statements.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_common\_subs), described in <u>"Checking Options" on page 202.</u>

# opt\_dead\_assignments

**Description** Controls the use of dead store optimization.

**Compatibility** This pragma is compatible with the following platform targets:

	68K	PowerPC	NEC V800	Intel x86	MIPS
- 1					

**Remarks** When this option is on, the compiler removes assignments to variables if the variables are not used before being reassigned.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_dead\_assignments), described in <u>"Checking Options" on page 202.</u>

## opt\_dead\_code

**Description** Controls the use of dead code optimization.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 M	IPS
----------------------------------	-----

**Remarks** When this option is on, the compiler removes statements that, logically, will never be executed or is never referred to by other statements.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_dead\_code), described in <u>"Checking Options" on page 202.</u>

# opt\_lifetimes

**Description** Controls the use of lifetime analysis optimization.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
0010	IOWELLC	THE VOOD	THEET AGO	HIID

Prototype #pragma opt\_lifetimes on | off | reset

Remarks

When this option is on, the compiler uses the same processor register for different variables in the same routine if the variables aren't used in the same statement.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_lifetimes), described in "Checking Options" on page 202.

# opt\_loop\_invariants

**Description** Controls the use of loop invariant optimization.

**Compatibility** This

This pragma is compatible with the following platform targets:

68K Pow	verPC NEC V	800 Intel x8	6 MIPS
---------	-------------	--------------	--------

**Prototype** 

#pragma opt\_loop\_invariants on | off | reset

Remarks

When this option is on, the compiler moves computations that don't change on the inside of a loop to the outside of a loop to improve the loop's speed.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_loop\_invariants), described in <u>"Checking Options" on page 202.</u>

# opt\_propagation

Description

Controls the use of copy and constant propagation optimization.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

Prototype #pragma opt\_propagation on | off | reset

**Remarks** When this option is on, the compiler replaces multiple occurrences of one variable with a single occurrence.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_proagation), described in "Checking Options" on page 202.

# opt\_strength\_reduction

**Description** Controls the use of strength reduction optimization.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma opt\_strength\_reduction on | off | reset

Remarks

When this option is on the compiler replaces multiplication instructions that are inside loops with addition instructions to speed up the loops.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_strength\_reduction), described in <u>"Checking Options" on page 202.</u>

# opt\_unroll\_loops

**Description** Controls the use of loop unrolling optimization.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

Prototype #pragma opt\_unroll\_loops on | off | reset

Remarks

When this option is on the compiler places multiple copies of a loop's statements inside a loop to improve its speed.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_unroll\_loops), described in <u>"Checking Options" on page 202.</u>

# opt\_vectorize\_loops

**Description** Controls the use of loop vectorizing optimization.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma opt\_vectorize\_loops on | off | reset

Remarks

When this option is on the compiler improves loop performance.

The pragma doesn't correspong to an option in any settings panel. To check whether this option is on, use \_\_option (opt\_vectorize\_loops), described in <u>"Checking Options" on page 202.</u>

# optimization\_level

See the pragma global\_optimizer, described in "global optimizer, optimization level" on page 129.

# optimize\_for\_size

**Description** Controls optimization to reduce the size of object code.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

### **Prototype**

#pragma optimize\_for\_size on | off | reset

### Remarks

This option lets you choose what the compiler does when it must decide between creating small code or fast code. If this option is on, the compiler creates smaller object code at the expense of speed. If this option is off, the compiler creates faster object code at the expense of size.

Most significantly if this option is on, the compiler ignores the inline directive, and generates function calls to call any function declared inline.

The pragma corresponds to the **Optimize for Size** option **Global Optimizations** settings panel. To check whether this option is on, use \_\_option (optimize\_for\_size), described in <u>"Checking Options" on page 202.</u>

# oldstyle\_symbols

See <u>"macsbug, oldstyle symbols" on page 140</u> for information about this pragma.

# pack

### **Description**

Controls the alignment of data structures.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
00K	POWELPC	NEC A900	Incer xee	MILD

Prototype	#pragma	pack(	[ n	$\mid$ push, $n$	ı   pop]	)
-----------	---------	-------	-----	------------------	----------	---

### Remarks

Sets the packing alignment for data structures. It affects all data structures declared after this pragma until you change it again with another pack pragma.

This pragma	Does this
<pre>#pragma pack(n)</pre>	Sets the alignment modulus to $n$ , where $n$ may be 1, 2, 4, 8 or 16. For MIPS compilers, if n is 0, structure alignment is reset to the default setting.
<pre>#pragma pack(push, n)</pre>	Pushes the current alignment modulus on a stack, then sets it to <i>n</i> , where <i>n</i> may be 1, 2, 4, 8 or 16. Use push and pop when you need a specific modulus for some declaration or set of declarations, but do not want to disturb the default setting. This form is not supported by the MIPS compilers.
#pragma pack(pop)	Pops a previously pushed alignment modulus from the stack. This form is not supported by the MIPS compilers.
<pre>#pragma pack()</pre>	For x86 compilers, resets alignment modulus to the value specified in the x86 CodeGen settings panel. For MIPS compilers, resets structure alignment to the default setting.

This pragma corresponds to the **Byte Alignment** option in the **x86 CodeGen** settings panel.

## parameter

**Description** Specifies the use of registers to pass parameters.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

### **Prototype**

#pragma parameter return-reg func-name(param-regs)

### Remarks

This pragma applies to 68K programming only.

The compiler passes the parameters for the function *func-name* in the registers specified in *param-regs* instead of the stack, and returns any return value in the register *return-reg*. Both *return-reg* and *param-regs* are optional.

Here are some samples:

```
#pragma parameter __D0 Gestalt(__D0, __A1)
#pragma parameter __A0 GetZone
#pragma parameter HLock(__A0)
```

When you define the function, you need to specify the registers right in the parameter list, as described in the appropriate Targeting manual.

This pragma does not correspond to an option in any settings panel.

# pcrelstrings

### **Description**

Controls the storage and reference of string literals from the program counter.

## Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

### **Prototype**

#pragma pcrelstrings on | off | reset

#### Remarks

If this option is on, the compiler stores the string constants used in a local scope in the code segment and addresses these strings with PC-relative instructions. If this option is off, the compiler stores all

string constants in the global data segment. Regardless of how this option is set, the compiler stores string constants used in the global scope in the global data segment. For example:

Strings in C++ initialization code are always allocated in the global data segment.

**NOTE:** If you turn the pool\_strings pragma on, the compiler ignores the setting of the pcrelstrings pragma.

This pragma corresponds to the **PC-Relative Strings** option in the 68K Processor settings panel. To check whether this option is on, use \_\_option (pcrelstrings), described in <u>"Checking Options" on page 202.</u> By default, this option is off.

# peephole

### **Description**

Controls the use peephole optimization.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

### **Prototype**

#pragma peephole on | off | reset

#### Remarks

If this pragma is on, the compiler performs peephole optimizations, which are small local optimizations that eliminate some compare instructions and improve branch sequences.

This pragma corresponds to the **Peephole Optimizer** option in the PPC Processor settings panel. To check whether this option is on, use \_\_option (peephole), described in <u>"Checking Options" on page 202</u>.

# pointers\_in\_A0, pointers\_in\_D0

**Description** 

Controls which calling convention to use.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerI	C NEC V800	Intel x86	MIPS
------------	------------	-----------	------

**Prototype** 

#pragma pointers\_in\_A0

#pragma pointers\_in\_D0

Remarks

These pragmas are available for Mac OS on 68K processors only.

These pragmas let you choose between two calling conventions: the convention for MPW and Macintosh Toolbox routines and the convention for Metrowerks C and C++ routines. In the MPW and Macintosh Toolbox calling convention, functions return pointers in the register DO. In the Metrowerks C and C++ convention, functions return pointers in the register AO.

When you declare functions from the Macintosh Toolbox or a library compiled with MPW, use the pragma pointers\_in\_D0. After you declare those functions, use the pragma pointers\_in\_A0 to start declaring or defining Metrowerks C and C++ functions.

In <u>Listing 6.3</u>, the Toolbox functions in Sound.h return pointers in D0 and the user-defined functions in Myheader.h use A0.

## Listing 6.3 Using #pragma pointers\_in\_A0 and #pragma pointers\_in\_D0

#pragma pointers\_in\_D0 // set for Toolbox calls
#include <Sound.h>

#pragma pointers\_in\_A0 // set for my own routines
#include "Myheader.h"

The pragmas pointers\_in\_A0 and pointers\_in\_D0 have much the same meaning as d0\_pointers and are available for backwards compatibility. The pragma pointers\_in\_A0 corresponds to #pragma d0\_pointers off and the pragma pointers\_in\_D0 corresponds to #pragma d0\_pointers on. The pragma d0\_pointers is recommended for new code since it supports the reset argument. For more information, see "d0\_pointers" on page 104.

This pragma does not correspond to any option in the settings panel. To check whether this option is on, use the \_\_option (d0\_pointers), described in "Checking Options" on page 202.

# pool\_data

**Description** 

Controls how data is stored.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS

**Prototype** 

#pragma pool\_data on | off | reset

**Remarks** 

This pragma is available for embedded PowerPC programming only.

If this pragma is on, the compiler optimizes pooled data. The pragma must be used before the function you want it apply to.

This pragma corresponds to the **Pool Data** option in the PPC Processor settings panel. To check whether this option is on, use \_\_option (pool\_data), described in <u>"Checking Options" on page 202.</u>

## pool\_strings

**Description** 

Controls how string literals are stored.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma pool\_strings on | off | reset

Remarks

If the pragma pool\_strings in the <u>C/C++ Language Panel</u> is on, the compiler collects all string constants into a single data object so your program needs one TOC entry for all of them. If this pragma is off, the compiler creates a unique data object and TOC entry for each string constant. Turning this pragma on decreases the number of TOC entries in your program but increases your program's size, since it uses a less efficient method to store the string's address.

This pragma is especially useful if your program is large and has many string constants or uses the Metrowerks Profiler.

**NOTE:** If you turn the pool\_strings pragma on, the compiler ignores the setting of the pcrelstrings pragma.

This pragma corresponds to the **Pool Strings** option in the <u>C/C++</u> <u>Language Panel</u>. To check whether this option is on, use \_\_option (pool\_strings), described in <u>"Checking Options" on page 202</u>.

# pop, push

**Description** 

Save and restore pragma settings.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS	68K
-------------------------------------	-----

Prototype #pragma push

#pragma pop

**Remarks** The pragma push saves all the current pragma settings. The pragma

pop restores all the pragma settings to what they were at the last

push pragma. For example, see Listing 6.4.

## Listing 6.4 push and pop example

```
#pragma far_data on
#pragma pointers_in_A0
#pragma push   // push all compiler options
#pragma far_data off
#pragma pointers_in_D0
    // pop restores "far_data" and "pointers_in_A0"
#pragma pop
```

These pragmas are available so you can use MacApp with Metrowerks C and C++. If you're writing new code and need to set a pragma option to its original value, use the reset argument, described in <u>"Pragma Syntax"</u> on page 90.

# precompile\_target

**Description** Specifies the file name for a precompiled header file.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma precompile\_target filename

**Remarks** 

**NOTE:** This pragma is not supported on Be OS.

This pragma specifies the filename for a precompiled header file. If you don't specify the filename, the compiler gives the precompiled header file the same name as its source file.

Filename can be a simple filename or an absolute pathname. If *filename* is a simple filename, the compiler saves the file in the same folder as the source file. If *filename* is a path name, the compiler saves the file in the specified folder.

<u>Listing 6.5</u> shows sample source code from the MacHeaders precompiled header source file. By using the predefined symbols \_\_cplusplus and powerc and the pragma precompile\_target, the compiler can use the same source code to create different precompiled header files for C and C++, 680x0 and PowerPC.

## Listing 6.5 Using #pragma precompile\_target filename

```
#ifdef __cplusplus
#ifdef powerc
#pragma precompile_target "MacHeadersPPC++"
#else
#pragma precompile_target "MacHeaders68K++"
#endif
#else
#ifdef powerc
#pragma precompile_target "MacHeadersPPC"
#else
#pragma precompile_target "MacHeaders68K"
#endif
#endif
```

# profile

**Description** 

Controls the generation of extra object code for use with the CodeWarrior profiler.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

**Prototype** 

#pragma profile on | off | reset

Remarks

This pragma applies to Mac OS programming only.

If this pragma is on, the compiler generates code for each function that lets the Metrowerks Profiler collect information on it. For more information, see the *Metrowerks Profiler Manual*.

This pragma corresponds to the **Generate Profiler Calls** option in the 68K Processor settings panel and the Emit Profiler Calls in the PPC Processor settings panel. To check whether this option is on, use \_\_option (profile) described in <u>"Checking Options" on page 202.</u>

# readonly\_strings

### **Description**

Controls how to store string literals.

### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

### **Prototype**

#pragma readonly\_strings on | off | reset

#### Remarks

This option determines where to stores string constants. If this option is off, the compiler stores string constants in the data section. If this option is on, the compiler stores string constants in the code section.

**NOTE:** Variables that are not initialized to the address of another object at run time are always placed in the code section (class RO). This includes C/C++ variables declared with the const storage-class modifier.

This pragma corresponds to the **Make Strings ReadOnly** option in the **PPC Processor**, **MIPS**, and **V800 Processor** panels. To check whether this option is on, using #if \_\_option (readonly\_strings), see "Checking Options" on page 202.

# register\_coloring

**Description** Controls whether the use of register coloring.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma register\_coloring on | off | reset

Remarks

When this pragma is on, the compiler uses a single register to hold the value of more than one variable if those variables are never used in the same statement to improve a program's performance.

**TIP:** Turn this option off when debugging a program.

This pragma corresponds to the **Register Coloring** option in the **x86 Codegen** panel. To check whether this option is on, use \_\_option (register\_coloring), described in "Checking Options" on page 202.

See also <u>"no register coloring"</u> on page 147.

# require\_prototypes

**Description** 

Controls whether or not the compiler should expect function prototypes.

Compatibility

This pragma is compatible with the following platform targets:

68K P	owerPC	NEC V800	Intel x86	MIPS
-------	--------	----------	-----------	------

**Prototype** 

#pragma require\_prototypes on | off | reset

Remarks

When the pragma require\_prototypes is on, the compiler generates an error if you use a function that does not have a prototype.

This pragma helps you prevent errors that happen when you use a function before you define it.

This pragma corresponds to the **Require Function Prototypes** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (require\_prototypes), described in <u>"Checking Options" on page 202.</u>

## **RTTI**

**Description** 

Controls the availability of runtime type information.

Compatibility

This pragma is compatible with the following platform targets:

**Prototype** 

#pragma RTTI on | off | reset

Remarks

When this pragma is on, you can use runtime type information (or RTTI) features, such as dyanamic\_cast and typeid. The other RTTI expressions are available even if the **Enable RTTI** option is off. Note that \*type\_info::before(const type\_info&) is not yet implemented.

This pragma corresponds to the **Enable RTTI** option in the <u>C/C++</u> <u>Language Panel</u>. To check whether this option is on, use \_\_option (RTTI), described in <u>"Checking Options" on page 202.</u>

# scheduling

**Description** 

Specifies the use of instruction scheduling optimization.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

### **Prototype**

```
#pragma scheduling 601 | 603 | 604 | on | off | reset
```

### **Remarks**

This pragma lets you choose how the compiler rearranges instructions to increase speed. Some instructions, such as a memory load, take more than one processor cycle. By moving an unrelated instruction between the load and the instruction that uses the loaded item, the compiler saves a cycle when executing the program.

For PowerPC, you can use 601, 603, or 604. If you use on, the compiler performs 601 scheduling.

However, if you're debugging your code, turn this pragma off. Since it rearranges the instructions produced from your code, the debugger will not be able to match the statements in your source code to the produced instructions.

## section

### **Description**

Controls the organization of object code.

### Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

### **Prototype**

```
#pragma section [ objecttype | permission ] [iname]
[uname] [data mode=datamode] [code mode=codemode]
```

#### Remarks

This pragma applies to PowerPC embedded programming only.

This sophisticated and powerful pragma lets you arrange compiled object code into predefined sections and sections you define. This topic is organized into these parts:

- Parameters
- Section access permissions
- Predefined sections and default sections
- Forms for #pragma section

- Forcing individual objects into specific sections
- <u>Using #pragma section with #pragma push and #pragma pop</u>

### **Parameters**

The optional *objecttype* parameter specifies where types of object data are stored. It may be one or more of the following values:

- code\_type—executable object code
- data\_type—non-constant data of a size greater than the size specified in the small data threshold option in the PowerPC EABI Project settings panel
- sdata\_type—non-constant data of a size less than or equal to the size specified in the small data threshold option in the PowerPC EABI Project settings panel
- const\_type—constant data of a size greater than the size specified in the small const data threshold option in the PowerPC EABI Project settings panel
- sconst\_type—constant data of a size less than or equal to the size specified in the small const data threshold option in the PowerPC EABI Project settings panel
- all types—all data

Specify one or more of these object types without quotes and separated by spaces.

CodeWarrior C/C++ generates some of its own data, such as exception and static initializer objects, which are not affected by #pragma section.

**NOTE:** CodeWarrior C/C++ uses the initial setting of the **Make Strings ReadOnly** option in the **PowerPC EABI Processor** settings
panel to classify character strings. If Make Strings ReadOnly is on,
character strings are stored in the same section as data of type
const\_type. If Make Strings ReadOnly is off, strings are stored in
the same section as data for data\_type.

The optional *permission* parameter specifies access permission. It may be one or more of these values:

- R—read only permission
- W—write permission
- X—execute permission

For information on access permission, see <u>"Section access permissions" on page 171.</u> Specify one or more of these permissions in any order, without quotes, and no spaces.

The optional *iname* parameter is a quoted name that specifies the name of the section where the compiler stores initialized objects. Variables that are initialized at the time they are defined, functions, and character strings are examples of initialized objects. The iname parameter may be of the form ".abs.xxxxxxx" where xxxxxxxx is an 8-digit hexadecimal number specifying the address of the section.

The optional *uname* parameter is a quoted name that specifies the name of the section where the compiler stores uninitialized objects. This parameter is required for sections that have data objects. The uname parameter may be a unique name or it may be the name of any previous *iname* or *uname* section. If the *uname* section is also an *iname* section then uninitialized data will be stored in the same section as initialized objects.

The special *uname* COMM specifies that uninitialized data will be stored in the common section. The linker will put all common section data into the ".bss" section. When the **Use Common Section** option is on in the **PowerPC EABI Processor** panel, COMM is the default *uname* for the ".data" section. When the **Use Common Section** option is off, COMM is the default *uname* for the ".bss" section.

The *uname* parameter may be changed. For example, you may want most uninitialized data to go into the ".bss" section while specific variables be stored in the COMM section. <u>Listing 6.6</u> shows an example of specifying that specific uninitialized variables be stored in the COMM section.

## Listing 6.6 Storing uninitialized data in the COMM section

```
// the Use Common Section option is off
#pragma push // save the current state
#pragma section ".data" "COMM"
int foo;
int bar;
#pragma pop // restore the previous state
```

You may not use any of the object types, data modes, or code modes as the names of sections. Also, you may not use pre-defined section names in the PowerPC EABI for your own section names.

The optional data\_mode=datamode parameter tells the compiler what kind of addressing mode to use for referring to data objects for a section.

The permissible addressing modes for *datamode* are:

- near\_abs—objects must be within the first 16 bits of RAM
- far\_abs—objects must be within the first 32 bits of RAM
- sda\_rel—objects must be within a 32K range of the linkerdefined small data base address

```
The sda_rel addressing mode may only be used with the ".sdata", ".sbss", ".sdata2", ".sbss2", ".EMB.PPC.sdata0", and ".EMB.PPC.sbss0" sections.
```

The default addressing mode for large data sections is far\_abs. The default addressing mode for the predefined small data sections is sda\_rel.

Specify one these addressing modes without quotes.

The optional code\_mode=codemode parameter tells the compiler what kind of addressing mode to use for referring to executable routines for a section.

The permissible addressing modes for *codemode* are:

 pc\_rel—routines must be within 24 bits of where it is called from • near\_abs—routines must be within the first 24 bits of RAM

The default addressing mode for executable code sections is pc\_rel.

Specify one these addressing modes without quotes.

**NOTE:** All sections have a data addressing mode (data\_mode=datamode) and a code addressing mode (code\_mode=codemode). Although the CodeWarrior C/C++ compiler for PowerPC embedded allows you to store executable code in data sections and data in executable code sections, this practice isn't encouraged.

### Section access permissions

When you define a section using #pragma section, its default access permission is read only. If you change the current section for a particular object type, the compiler adjusts the access permission to allow the storage of objects of that type while continuing to allow objects of previously-allowed object types. Associating code\_type to a section adds execute permission to that section. Associating data\_type, sdata\_type, or sconst\_type to a section adds write permission to that section.

Occasionally you might create a section without making it the current section for an object type. You might do so to force an object into a section with the \_\_declspec keyword. In this case, the compiler will automatically update the access permission for that section to allow the object to be stored in the section, then issue a warning. To avoid such a warning, make sure to give the section the proper access permissions before storing object code or data into it. As with associating an object type to a section, passing a specific permission adds to the permissions that a section already has.

**NOTE:** Associating an object type with a section sets the appropriate acces permissions for you.

#### Predefined sections and default sections

The predefined sections set with an object type become the default section for that type. After assigning a non-standard section to an object type, you may rever to the default section with one of the forms in "Forms for #pragma section" on page 172.

The compiler predefines the sections in <u>Listing 6.7</u>.

### Listing 6.7 Predefined sections

```
#pragma section code_type ".text" data_mode=far_abs \
  code_mode=pc_rel
#pragma section data_type ".data" ".bss" data_mode=far_abs \
   code_mode=pc_rel
#pragma section const_type ".rodata" ".rodata" data_mode=far_abs \
   code_mode=pc_rel
#pragma section sdata_type ".sdata" ".sbss" data_mode=sda_rel \
   code_mode=pc_rel
#pragma section sconst_type ".sdata2" ".sbss2" data_mode=sda_rel \
   code_mode=pc_rel
#pragma section ".EMB.PPC.sdata0" ".EMB.PPC.sbss0" \
   data_mode=sda_rel code_mode=pc_rel
```

**NOTE:** The ".EMB.PPC.sdata0" and ".EMB.PPC.sbss0" sections are predefined as an alternative to the sdata\_type object type.

## Forms for #pragma section

This pragma has these principal forms:

```
#pragma section ".name1"
```

This form simply creates a section called ".name1" if it doesn't already exist. With this form, the compiler doesn't store objects in the section without an appropriate, subsequent #pragma section statement or an item defined with the \_\_declspec keyword. If only one section name is specified, it is considered the name of the

initialized object section, *iname*. If the section is already declared, you may also optionally specify the uninitialized object section, *uname*. If you know that the section is should have read and write permission, use #pragma section RW ".name1" instead, especially if you use the \_\_declspec keyword.

#pragma section objecttype ".name2"

With the addition of one or more object types, the compiler stores objects of the types specified in the section ".name2". If ".name2" doesn't exist, the compiler creates it with the appropriate access permissions. If only one section name is specified, it is considered the name of the initialized object section, iname. If the section is already declared, you may also optionally specify the uninitialized object section, unameThis feature is useful for temporarily circumventing the small data threshold.

#pragma section objecttype

When there is no *iname* parameter, the compiler resets the section for the object types specified to the default section. For information on predefined sections, see <u>"Predefined sections and default sections"</u> on page 172. Resetting an object type's section doesn't reset its addressing modes. You must do so explicitly.

When declaring or setting sections, you may also add a uninitialized section to a section that didn't have one originally by specifiying a uname parameter. However, you may not change the uninitialized section associated with an initialized section once an uninitialized section has already been associated to it. Remember that an initialized section's corresponding uninitialized section may be the same.

### Forcing individual objects into specific sections

You may store a specific object of an object type into a section other than the current section for that type without changing the current section. Use the \_\_declspec keyword with the name of the target section and put it next to the extern declaration or static definition of the item you want to store in the section. <u>Listing 6.8</u> shows examples.

## Listing 6.8 Using \_\_declspec to force objects into specific sections

```
__declspec(".data") extern int myVar;
#pragma section "constants"
__declspec("constants") const int myvar = 0x12345678;
```

## Using #pragma section with #pragma push and #pragma pop

This pragma may be used with #pragma push and #pragma pop to ease complex or frequent changes to sections settings. See <u>Listing</u> 6.6 for an example. Note that #pragma pop doesn't restore any changes to the access permissions of sections that exists before or after the corresponding #pragma push.

## segment

### Description

Specifies the code segment where subsequent object code should be stored.

### Compatibility

This pragma is compatible with the following platform targets:

68K PowerP	NEC V800	Intel x86	MIPS
------------	----------	-----------	------

#### **Prototype**

#pragma segment name

#### Remarks

This pragma applies to Mac OS programming only.

This pragma places all the functions that follow into the code segment named *name*. For more on function-level segmentation, consult the *Targeting* manual for the platform you're developing for.

Generally, the PowerPC compilers ignore this directive since PowerPC applications do not have code segments. However, if you choose **by #pragma segment** from the **Code Sorting** pop-up menu in the **PPC PEF** settings panel, the PowerPC compilers group functions in the same segment together. For more information, consult the *Targeting* manual for the platform you're developing for.

This pragma does not correspond to an option in any settings panel.

## side\_effects

**Description** Controls the use of pointer aliases.

### Compatibility

This pragma is compatible with the following platform targets:

	68K	PowerPC	NEC V800	Intel x86	MIPS
П					

### **Prototype**

```
#pragma side_effects on | off | reset
```

#### Remarks

If your program does not use pointer aliases, turn off this pragma to make your program smaller and faster. If your program does use pointer aliases, turn on this pragma to avoid incorrect code. A pointer alias looks like this:

```
int a, *p;
p = &a; // *p is an alias for a.
```

To understand why pointer aliases are so important, remember that the compiler needs to load a variable into a register before performing arithmetic on it. So, in the example below, the compiler loads a into a register before the first addition. If \*p is an alias for a, the compiler needs to load a into a register again before the second addition, since changing \*p also changed a. If \*p is not an alias for a, the compiler doesn't need to load a into a register again, since changing \*p does not change a.

```
x = a + 1;
*p = 0; // If *p is an alias for a,
y = a + 2; // this changes a.
```

**NOTE:** The PowerPC compilers ignore this pragma and always assume that a program may contain pointer aliases.

This pragma does not correspond to an option in any settings panel. To check whether this pragma is on, use \_\_option

(side\_effects), described in <u>"Checking Options" on page 202.</u> By default, this pragma is on.

# simple\_prepdump

**Description** Controls the suppression of comments in preprocessor dumps.

**Compatibility** This pragma is compatible with the following platform targets:

68K Powe	erPC NEC V800	Intel x86	MIPS
----------	---------------	-----------	------

Prototype #pragma simple\_prepdump on | off | reset

**Remarks** By default, the preprocessor adds comments about the current include file being processed in its output. These comments can be disabled by turning this pragma on.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (simple\_prepdump). See on <u>"Checking Options" on page 202.</u> By default, this pragma is off.

# **SOMCallOptimization**

**Description** Controls the error checking used for making calls to SOM objects.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

Prototype #pragma SOMCallOptimization on | off | reset

**Remarks** This pragma is only available for Mac OS using C++ code.

The PowerPC compiler uses an optimized error check that is smaller but slightly slower.

This pragma is ignored if the direct\_to\_SOM pragma, described in "direct\_to\_som" on page 112, is off.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (<u>SOMCall-Optimization</u>). See on <u>"Checking Options" on page 202.</u> By default, this pragma is off.

# **SOMCallStyle**

**Description** Specifies the convention used to call SOM objects.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma SOMCallStyle OIDL | IDL

Remarks

This pragma is only available for Mac OS using C++ code.

The SOMCallStyle pragma chooses between two SOM call styles:

- OIDL, an older style that does not support DSOM
- IDL, a newer style that does support SOM.

If a class uses the IDL style, its methods must have an Environment pointer as the first parameter. Note that the SOMClass and SOMObject classes use OIDL, so if you override a method from one of them, you should not include the Environment pointer.

This pragma is ignored if the direct\_to\_SOM pragma, described in *Targeting Mac OS*, is off.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (<u>SOMCheckEn-vironment</u>). See <u>"Checking Options" on page 202</u>. By default, this pragma is set to IDL.

## **SOMCheckEnvironment**

**Description** Controls whether or not to perform SOM environment checking.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

### **Prototype**

#pragma SOMCheckEnvironment on | off | reset

### Remarks

This pragma is only available for Mac OS using C++ code.

When the pragma SOMCheckEnvironment is on, the compiler performs automatic SOM environment checking. It transforms every IDL method call and new allocation into an expression which also calls an error-checking function. You must define separate error-checking functions for method calls and allocations. For more information on how to write these functions, see *Targeting Mac OS*.

For example, the compiler transforms this IDL method call:

```
SOMobj->func(&env, arg1, arg2);
```

into something that is equivalent to this:

```
( temp=SOMobj->func(&env, arg1, arg2),
   __som_check_ev(&env), temp );
```

First, the compiler calls the method and stores the result in a temporary variable. Then it checks the environment pointer. Finally, it returns the method's result.

And, the compiler transforms this new allocation:

new SOMclass;

into something that is equivalent to this:

```
( temp=new SOMclass, __som_check_new(temp),
  temp);
```

First, the compiler creates the object and stores it in a temporary variable. Then it checks the object and returns it.

The PowerPC compiler uses an optimized error check that is smaller but slightly slower than the one given above. To use the error check show above in PowerPC code, use the pragma SOMCall-Optimization, described in "SOMCallOptimization" on page 176.

This pragma is ignored if the direct\_to\_SOM pragma, described in *Targeting Mac OS* is off.

This pragma corresponds to the **Direct to SOM** menu in the <u>C/C++</u> <u>Language Panel</u>. Selecting **On with Environment Checks** from that menu is like setting this pragma to on. Selecting anything else from that menu is like setting this pragma to off. To check whether this option is on, use <u>option</u> (RTTI), described in <u>"Checking Options" on page 202.</u> By default, this pragma is on.

## **SOMClassVersion**

**Description** 

Specifies a SOM class's version.

## Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

### **Prototype**

#pragma SOMClassVersion(class, majorVer, minorVer)

### Remarks

This pragma is only available for Mac OS using C++ code.

SOM uses the class's version number to make sure the class is compatible with other software you're using. If you don't declare the version numbers, SOM assumes zeroes. The version numbers must be positive or zero.

When you define the class, the program passes its version number to the SOM kernel in the class's metadata. When you instantiate an object of the class, the program passes the version to the runtime kernel, which checks to make sure the class is compatible with the running software.

This pragma is ignored if the direct\_to\_SOM pragma, described in *Targeting Mac OS*, is off.

This pragma does not correspond to an option in any settings panel.

## **SOMMetaClass**

**Description** 

Specifies a SOM class's metaclass.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma SOMMetaClass (class, metaclass)

Remarks

This pragma is only available for Mac OS using C++ code.

A metaclass is a special kind of SOM class that defines the implementation of other SOM classes. All SOM classes have a metaclass, including metaclasses themselves. By default, the metaclass for a SOM class is SOMClass. If you want to use another metaclass, use the SOMMetaClass pragma:

The metaclass must be a descendant of SOMClass. Also, a class cannot be its own metaclass. That is, *class* and *metaclass* must name different classes.

This pragma is ignored if the direct\_to\_SOM pragma, described in *Targeting Mac OS*, is off.

This pragma does not correspond to an option in any settings panel.

## **SOMReleaseOrder**

Description

Specifies the order in which a SOM class's member functions are released.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

**Prototype** 

#pragma SOMRelaseOrder(func1, func2,... funcN)

Remarks

This pragma is only available for Mac OS using C++ code.

A SOM class must specify the release order of its member functions. As a convenience for when you're first developing the class, Metrowerks C++ lets you leave out the SOMReleaseOrder pragma and assumes the release order is the same as the order in which the functions appear in the class declaration. However, when you release a version of the class, use the pragma, since you'll need to modify its list in later versions of the class.

You must specify every SOM method that the class introduces. Do not specify inline member functions that are virtual, since they're not considered to be SOM methods. Don't specify overridden functions.

If you remove a function from a later version of the class, leave its name in the release order list. If you add a function, place it at the end of the list. If you move a function up in the class hierarchy, leave it in the original list and add it to the list for the new class.

This pragma is ignored if the direct\_to\_SOM pragma, described in *Targeting Mac OS*, is off.

This pragma does not correspond to an option in any settings panel.

# stack\_cleanup

**Description** 

Controls when the compiler generates code to clean up the stack.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
1				

**Prototype** 

#pragma stack\_cleanup on | off | reset

Remarks

Turning this option on will disable the deferred stack cleanup after function calls, forcing the compiler to remove arguments from the stack after every function call. Although this option slows down ex-

ecution, it reduces stack usage, making it less likely the stack will intrude on other parts of the program.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (stack\_cleanup), described in <u>"Checking Options" on page 202</u>. By default, this pragma is off.

# static inlines

#### **Description**

Controls how many instances of inline functions that the compiler generates.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

#pragma static\_inlines on | off | reset

#### Remarks

The pragma static\_inlines determines what the compiler does if it cannot inline a call to a function declared inline and must create a compiled version of the function. If the pragma is off, the compiler creates one compiled version for the whole project. If the pragma is on, the compiler creates a different compiled version for each file that needs a compiled version.

This pragma is available only so that the compiler can pass certain validation suites. Generally, you'll want to leave this pragma off to make your code smaller without any loss of speed.

This pragma does not correspond to an option in any settings panel. To check whether this option is on, use \_\_option (static\_inlines), described in <u>"Checking Options" on page 202.</u> By default, this pragma is off.

# suppress\_init\_code

#### Description

Controls the suppression of static initialization object code.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

#pragma suppress\_init\_code on | off | reset

#### Remarks

When this pragma is on, the compiler doesn't generate any code for static data initialization such as C++ constructors. By default this pragma is off.

**WARNING!** Using this pragma without being aware of its consequences can produce erratic or unpredictable behavior in your program.

#### sym

#### **Description**

Controls the generation of debugger symbol information.

#### Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

#### **Prototype**

#pragma sym on | off | reset

#### Remarks

The compiler pays attention to this pragma only if you turn on the debug marker for a file in the IDE's project window. If this pragma is off, the compiler does not put debugging information into this source file's debugger symbol file (SYM or DWARF) for the functions that follow. If this pragma is on, the compiler does generate debugging information.

Note that the compiler always generates a debugger symbol file for a source file that has a debug diamond next to it in the project window. This pragma changes only which functions have information in that symbol file. To check whether this option is on, use \_\_option (sym), described in <u>"Checking Options" on page 202.</u> By default, this pragma is on.

# syspath\_once

**Description** Controls how include files are treated.

**Compatibility** This pragma is compatible with the following platform targets:

68K Power	rPC NEC V800	Intel x86	MIPS
-----------	--------------	-----------	------

**Prototype** 

#pragma syspath\_once on | off | reset

Remarks

Files referred to in #include <> and #include " " directives are treated as distinct files if this option is selected, even if they refer to the same file.

# toc\_data

**Description** Contro

Controls how static variables are stored.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma toc\_data on | off | reset

Remarks

This pragma applies to Mac OS CFM programming only.

If the toc\_data pragma is on, the compiler makes your code smaller and faster by storing static variables that are 4 bytes or smaller directly in the TOC, instead of allocating space for them elsewhere and storing pointers to them in the TOC. Turn this pragma off only if your code expects the TOC to contain pointers to data.

This pragma corresponds to the **Store Static Data in TOC** option in the PPC Processor settings panel. To check whether this option is

on, use \_\_option (toc\_data), described in <u>"Checking Options"</u> on page 202.

# trigraphs

**Description** 

Controls the use ANSI/ISO trigraph sequences.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

```
#pragma trigraphs on | off | reset
```

Remarks

If you're writing code that must follow the ANSI standard strictly, turn on the pragma trigraphs in the C/C++ Language Panel. Many common Macintosh character constants look like trigraph sequences, and this pragma lets you use them without including escape characters. Be careful when you initialize strings or multi-character constants that contain question marks. For example:

```
char c = '????'; // ERROR: Trigraph sequence expands to '??^ char d = '\?\?\?'; // OK
```

This pragma corresponds to the **Expand Trigraphs** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (trigraphs), described in <u>"Checking Options" on page 202.</u>

# traceback

**Description** 

Controls the generation of AIX-format traceback tables for debugging.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
700K	POWELPC	MEC A900	Intel X00	MILE

**Prototype** 

#pragma traceback on | off | reset

Remarks

This pragma helps other people debug your application or shared library if you do not distribute the source code. If this option is on, the compiler generates an AIX-format traceback table for each function, which are placed in the executable code. Both the Metrowerks and Apple debuggers can use traceback tables.

This pragma corresponds to the **Emit Traceback Tables** option in the PPC Linker settings panel. To check whether this option is on, use the \_\_option (traceback), described in <u>"Checking Options"</u> on page 202. By default, this option is off.

# unsigned\_char

**Description** 

Controls whether or not declarations of type char are treated as unsigned char.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma unsigned\_char on | off | reset

Remarks

When the unsigned\_char pragma is on, the C/C++ compiler treats a char declaration as if it were an unsigned char declaration.

**NOTE:** If you turn this pragma on, your code may not be compatible with libraries that were compiled with it turned off. In particular, your code may not work with the ANSI libraries included with CodeWarrior.

This pragma corresponds to the **Use unsigned chars** option in the <u>C/C++ Language Panel</u>. To check whether this option is on, use \_\_option (unsigned\_char), described in <u>"Checking Options"</u> on page 202. By default, this option is off.

#### unused

**Description** 

Controls the suppression of warnings for variables and parameters that aren't referenced in a function.

Compatibility

This pragma is compatible with the following platform targets:

68K Po	werPC NEC V8	300 Intel x8	MIPS
--------	--------------	--------------	------

**Prototype** 

```
#pragma unused ( var_name [, var_name ]... )
```

Remarks

This pragma suppresses the compile time warnings for the unused variables and parameters specified in its argument list. You can use this pragma only within a function body, and the listed variables must be within the function's scope. You cannot use this pragma with functions defined within a class definition or with template functions. For example:

This pragma does not correspond to an option in any settings panel.

# use\_fp\_instructions

**Description** 

Controls the generation of NEC V800 floating point instructions.

Compatibility

This pragma is compatible with the following platform targets:

Remarks This option corresponds to the option Use V810 Floating-Point In-

structions, which is part of the NEC V800 Processor panel. To check

whether this option is on, use \_\_option

(use\_fp\_instructions), described in "Checking Options" on

page 202.

use\_frame

**Description** Controls the use of the BP register for stack frames.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS

Prototype #pragma use\_frame on|off|reset

**Remarks** When this option is on the compiler uses the BP register to point to the start of the stack frame.

To check whether this option is on, use \_\_option (use\_frame), described in "Checking Options" on page 202.

use\_mask\_registers

**Description** Controls the use of the NEC V800 r20 and r21 registers.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS

**Prototype** #pragma use\_mask\_registers on|off|reset

Remarks This option corresponds to the option Use r20 and r21 as Mask Registers, which is part of the NEC V800 Processor panel. To check

isters, which is part of the **NEC V800 Processor** panel. To check

whether this option is on, use \_\_option

(use\_mask\_registers), described in <u>"Checking Options" on page 202.</u>

# warn\_emptydecl

**Description** 

Controls the recognition of declarations without variables.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma warn\_emptydecl on | off | reset

Remarks

If the pragma warn\_emptydecl is on, the compiler displays a warning when it encounters a declaration with no variables. For example:

This pragma corresponds to the **Empty Declarations** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_emptydecl), described in <u>"Checking Options"</u> on page 202.

# warning\_errors

**Description** 

Controls whether warnings are treated as errors or not.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

**Prototype** 

#pragma warning\_errors on | off | reset

Remarks

When the pragma warning\_errors is on, the compiler treats all warnings as though they were errors. It will not compile a file until all warnings are resolved.

This pragma corresponds to the **Treat All Warnings as Errors** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warning\_errors), described in <u>"Checking Options" on page 202.</u>

#### warn\_extracomma

**Description** Controls the recognition of superfluous commas.

**Compatibility** This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

**Prototype** 

#pragma warn\_extracomma on | off | reset

Remarks

If the pragma warn\_extracomma is on, the compiler generates a warning when it encounters an extra comma. For example, this statement is legal in C, but it causes a warning when this pragma is on:

int a[] =  $\{ 1, 2, 3, 4, \}$ ; // ^ WARNING: Extra comma after 4

This pragma corresponds to the **Treat All Warnings as Errors** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_extracomma), described in <u>"Checking Options" on page 202</u>.

# warn hidevirtual

Description

Controls the recognition of a non-virtual member function that hides a virtual function in a superclass.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS	
-------------------------------------	--

**Prototype** #pragma warn\_hidevirtual on|off|reset

Remarks

If the pragma warn\_hidevirtual is on, the compiler generates a warning if you declare a non-virtual member function that hides a virtual function in a superclass. One function hides another if it has the same name but a different argument types. For example:

```
class A {
  public:
    virtual void f(int);
    virtual void g(int);
};
class B: public A {
 public:
    void f(char);
                          // WARNING: Hides A::f(int)
    virtual void g(int); // OK: Overrides A::g(int)
};
```

This pragma corresponds to the **Hidden virtual functions** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn hidevirtual). See "Checking Options" on page 202. By default, this option is off.

# warn\_illpragma

**Description** Controls the recognition of illegal pragma directives.

Compatibility This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

**Prototype** #pragma warn\_illpragma on | off | reset

Remarks

If the pragma warn\_illpragma is on, the compiler displays a warning when it encounters an illegal pragma. For example, these pragma statements generate warnings:

```
#pragma near_data off // WARNING: near_data is not a pragma.
#pragma far_data select // WARNING: select is not defined
#pragma far_data on // OK
```

This pragma corresponds to the **Illegal Pragmas** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_illpragma), described in <u>"Checking Options" on page 202.</u>

# warn\_implicitconv

**Description** 

Controls the issuing of warnings for implicit arithmetic conversions.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

```
#pragma warn_implicitconv on | off | reset
```

#### Remarks

The compiler will print a warning for implicit arithmetic conversions when the source value may not be representable by the destination type. See <u>Listing 6.9</u> for an example.

#### Listing 6.9 Example of implicit arithmetic conversion

This pragma corresponds to the **Implicit Artithmetic Conversion** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_implicitconv), described in <u>"Checking Options" on page 202.</u>

# warn\_notinlined

**Description** 

Controls the issuing of warnings for functions the compiler isn't able to inline.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma warn\_notinlined on | off | reset

Remarks

The compiler will issue a warning if it is not able to inline a function. This pragma corresponds to the **Non-Inlined Functions** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_notinlined), described in <u>"Checking Options"</u> on page 202.

# warn\_padding

**Description** 

Controls the notification of the padding of data structures.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC	NEC V800	Intel x86	MIPS
-------------	----------	-----------	------

**Prototype** 

#pragma warn\_padding on | off | reset

Remarks

If the pragma warn\_padding is on, the compiler warns about any bytes it adds to data structures to improve their alignment in memory. Refer to the appropriate *Targeting* manual for more information on how CodeWarrior C++ pads data structures for a particular processor or operating system.

To check whether this option is on, use \_\_option (warn\_padding). By default, this option is off. See <u>"Checking Options"</u> on page 202. By default, this option is off.

#### warn\_possunwant

**Description** 

Controls the recognition of possible unintentional logical errors.

Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

```
#pragma warn_possunwant on | off | reset
```

#### Remarks

If the pragma warn\_possunwant is on, the compiler checks for some common typographical mistakes that are legal C and C++ but that may have unwanted side effects, such as putting in unintended semicolons or confusing = and ==. The compiler generates a warning if it encounters one of these:

• An assignment in a logical expression or the condition in an if, while, or for expression. This check is useful if you frequently use = when you meant to use ==. For example:

• An equal comparison in a statement that contains a single expression. This check is useful if you frequently use == when you meant to use =. For example:

```
a == 0;  // WARNING: This is a comparison.
a = 0;  // OK: This is an assignment
```

• A semicolon (;) directly after a while, if, or for statement. For example, the statement generates an error and is probably an unintended infinite loop:

```
while (i++); // WARNING: Unintended infinite loop
```

If you intended to create an infinite loop, put white space or a comment between the while statement and the semicolon, and earn the admiration of all the folks who use your code. For example, these statements do not generate errors:

This pragma corresponds to the **Possible Errors** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_possunwant), described in <u>"Checking Options"</u> on page 202.

#### warn structclass

#### Description

Controls the issuing of warnings for possibly unintended mixing of class and struct keywords.

#### Compatibility

This pragma is compatible with the following platform targets:

68K	PowerPC	NEC V800	Intel x86	MIPS
-----	---------	----------	-----------	------

#### **Prototype**

```
#pragma warn_structclass on | off | reset
```

#### Remarks

If the warn\_structclass pragma is on, the compiler issues a warning if the class and struct keywords are used in the definition and declaration of the same identifier.

```
class X;
struct X { int a; }; // warning
```

This pragma corresponds to the **Inconsistent use of 'class' and 'struct' Keywords** option in the **C/C++ Warnings** settings panel. To check whether this option is on, use \_\_option

(warn\_structclass), described in <u>"Checking Options" on page</u> 202.

# warn\_unusedarg

**Description** Controls the recognition of unreferenced arguments.

**Compatibility** This pragma is compatible with the following platform targets:

68K Powe	erPC NEC V800	Intel x86	MIPS
----------	---------------	-----------	------

**Prototype** 

#pragma warn\_unusedarg on | off | reset

Remarks

If the pragma warn\_unusedarg is on, the compiler generates a warning when it encounters an argument you declare but do not use. This check helps you find misspelled argument names and arguments you have written out of your program.

```
void foo(int temp, int errer)
{
   error = do_something(); // ERROR: Error is undefined
} // WARNING: temp and error are unused.
```

This pragma corresponds to the **Unused Arguments** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_unusedarg), described in <u>"Checking Options" on page 202.</u>

# warn\_unusedvar

**Description** Controls the recognition of unreferenced variables.

**Compatibility** This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

Prototype #pragma warn\_unusedvar on | off | reset

Remarks

If the pragma warn\_unusedvar is on, the compiler generates a warning when it encounters a variable you declare but do not use. This check helps you find misspelled variable names and variables you have written out of your program. For example:

```
void foo(void)
{
  int temp, errer;
  error = do_something(); // ERROR: error is undefined
} // WARNING: temp and error are unused.
```

This pragma corresponds to the **Unused Variables** option in the C/C++ Warnings settings panel. To check whether this option is on, use \_\_option (warn\_unusedvar), described in "Checking Options" on page 202.

# warning

**Description** 

Available for compatibility only.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma warning(warning\_specifier : warning\_number\_list)

Remarks

This pragma applies to x86 programming only.

Ignored. Included for compatibility with Microsoft. The *warning\_number\_list* is a list of warning numbers separated by spaces, and *warning\_specifier* is one of the following:

- once
- default
- 1
- 2
- 3

- 4
- disable
- error

# wchar\_type

Description

Controls the size and format of the wchar\_t type.

Compatibility

This pragma is compatible with the following platform targets:

68K PowerPC NEC V800 Intel x86 MIPS
-------------------------------------

**Prototype** 

#pragma wchar\_type on | off | reset

Remarks

If the pragma wchar\_type is on, wchar\_t is treated as a built-in type, implemented as an unsigned 16-bit integral type. If the pragma is off, wchar\_t and characters in string literals are treated as unsigned short.

This pragma corresponds to the **Enable wchar\_t Support** option in the C/C++ Language settings panel. To check this option, use \_\_option (wchar\_type), described in <u>"Checking Options" on page 202.</u>

# **Predefined Symbols**

Metrowerks C and C++ define several preprocessor symbols that give you information about the compile-time environment. Note that these symbols are evaluated at compile time and not at run time. The topics in this section are:

- ANSI Predefined Symbols
- Metrowerks Predefined Symbols

# **ANSI Predefined Symbols**

The table below lists the symbols that the ANSI C standard requires.

Table 6.7	ANSI	predefined	symbols
-----------	------	------------	---------

This macro	is
DATE	The date at which the file is compiled; for example, "Jul 14, 1995".
FILE	The name of the file being compiled; for example "prog.c".
LINE	The line number of the line being compiled. This is the number before including any header files.
TIME	The time at which the file is compiled in 24-hour format; for example, "13:01:45".
STDC	Defined as 1 if compiling C source code. This macro lets you know that Metrowerks C implements the ANSI C standard. This macro is undefined when compiling C++ source code.

<u>Listing 6.10</u> shows a small program that uses the ANSI predefined symbols.

#### Listing 6.10 Using ANSI's Predefined Symbols

```
#include <stdio.h>

void main(void)
{
   printf("Hello World!\n");

   printf("%s, %s\n", __DATE__, __TIME__);
   printf("%s, line: %d\n", __FILE__, __LINE__);
}
```

The program prints something like the following:

Hello World!

Oct 31 1995, 18:23:50 main.ANSI.c, line: 10

# **Metrowerks Predefined Symbols**

The table below lists additional symbols that Metrowerks C and C++ provides.

Table 6.8 Predefined symbols for Metrowerks

This macro	is
A5	defined as 1 if data is A5-relative, 0 if data is A4 relative. This symbol is defined for 68K compilers. It is undefined for other target platforms.
cplusplus	defined if you're compiling this file as a C++ file, undefined if you're compiling this file as a C file.
embedded_cplus plus	defined as 1 if Embedded C++ is activated. This symbol is undefined if Embedded C++ is not activated. See
fourbyteints	defined as 1, if you turn on the <b>4-byte Ints</b> option in the 68K Processor settings panel. 0, if you turn off that option. This symbol is defined for 68K compilers. It is undefined for other platforms.
IEEEdoubles	defined as 1 if you turn on the <b>8-Byte Doubles</b> option in the 68K Processor settings panel. 0, if you turn off that option. This symbol is defined for 68K compilers. It is undefined for all other target platforms.

This macro	is
INTEL	defined as 1 if you're compiling this code with the x86 compiler and undefined for all other target platforms.
MC68K	defined as 1 if you're compiling this code with the 68K compiler and undefined for all other target platforms.
MC68020	defined as 1 if you turn on the <b>68020 Codegen</b> option in the Processor settings panel, 0 if you turn that option off. This symbol is defined for 68K compilers. It is undefined for all other target platforms.
MC68881	defined as 1 if you turn on the <b>68881 Codegen</b> option in the 68K Processor settings panel, 0 if you turn that option off. This symbol is defined for 68K compilers and undefined for all other target platforms.
MIPS	defined as 1 for MIPS compilers and undefined for other target platforms.
MIPS_ISA2	defined as 1 if the compiler's target plat- form is MIPS and you select the <b>ISA II</b> checkbox in the <b>MIPS Processor</b> settings panel. Undefined if you deselect the checkbox. It is always undefined for other target platforms.
MIPS_ISA3	defined as 1 if the compiler's target plat- form is MIPS and you select the <b>ISA III</b> checkbox in the <b>MIPS Processor</b> settings panel. Undefined if you deselect the checkbox. It is always undefined for other target platforms.

This macro	is
	13
MIPS_ISA4	defined as 1 if the compiler's target plat- form is MIPS and you select the <b>ISA IV</b> checkbox in the <b>MIPS Processor</b> settings panel. Undefined if you deselect the checkbox. It is always undefined for other target platforms
MWBROWSER	defined as 1 if the CodeWarrior browser is parsing your code. 0, otherwise.
MWERKS	defined as the version number of the Metrowerks C/C++ compiler, if you're using CodeWarrior CW7 or later. For example, in Metrowerks C/C++ version 2.2MWERKS would be 0x2200. This macro is defined as 1 if the compiler was issued before CodeWarrior CW7.
profile	1, if you turn on the <b>Generate Profiler Calls</b> option in the Processor settings panel. 0, if you turn that option off.
powerc, powerc,POWERPC	1, if you're compiling this code with the PowerPC compiler. 0, otherwise.
macintosh	1 if you're compiling this code with the 68K or PowerPC Macintosh compiler. 0 otherwise.

# **Checking Options**

The preprocessor function \_\_option() lets you test the setting of many pragmas and options that control the C/C++ compiler and code generation. You typically modify these settings using various panels in the Project Settings dialog box.

The syntax for this preprocessor function is:

option(option-name)
---------------------

If the specified option is on, \_\_option () returns 1; otherwise, it returns 0.

This function is useful when you want one source file to contain code that uses different option settings. The example below shows how to compile one series of lines if you're compiling for machines with the MC68881 floating-point unit and another series if you're compiling for machines without out:

```
#if __option (code68881) // Code for 68K chip with FPU
#else
   // Code for any 68K processor
#endif
```

The table below lists all the option names you can use in the preprocessor function \_\_option().

This argument	Corresponds to the
a6frames	Generate A6 Stack Frames option in the 68K Linker settings panel and pragma a6frames.
align_array_members	Pragma align_array_members.
always_inline	Pragma always_inline.
ANSI_strict	ANSI Strict option in the <u>C/C++ Language Panel</u> and pragma ANSI_strict.
arg_dep_lookup	Pragma arg_dep_lookup.
ARM_conform	<b>ARM Conformance</b> option in the <u>C/C++ Language</u> <u>Panel</u> and pragma ARM_conform.
auto_inline	Auto-Inline option of the Inlining menu in the C/ C++ Language Panel and pragma auto_inline.
bool	Enable C++ bool/true/false option in the C/C++ Language Panel and pragma bool.
check_header_flags	Pragma check_header_flags.
code68020	<b>68020 Codegen</b> option in the 68K Processor settings panel and pragma code68020.

This successor	On many day to the
This argument	Corresponds to the
code68881	<b>68881 Codegen</b> option in the 68K Processor settings panel and pragma code68881.
cplusplus	Whether the compiler is compiling this file as a C++ file. Related to the <b>Activate C++ Compiler</b> option in the <u>C/C++ Language Panel</u> , the pragma cplusplus, and the macro cplusplus
cpp_extensions	Pragma cpp_extensions
d0_pointers	Pragmas pointers_in_D0 and pointers_in_A0.
def_inherited	Pragma def_inherited.
defer_codegen	Pragma defer_codegen.
direct_destruction	Enable Exception Handling option in the <u>C/C++</u> <u>Language Panel</u> and pragma direct_destruction.
direct_to_SOM	<b>Direct to SOM</b> menu in the <u>C/C++ Language Panel</u> and pragma direct_to_SOM
disable_registers	Pragma disable_registers.
dollar_identifiers	Pragma dollar_identifiers.
dont_inline	<b>Don't Inline</b> option in the <u>C/C++ Language Panel</u> and pragma dont_inline.
dont_reuse_strings	<b>Don't Reuse Strings</b> option in the <u>C/C++ Language</u> <u>Panel</u> and pragma dont_reuse_strings.
ecplusplus	Pragma ecplusplus
EIPC_EIPSW	Pragma EIPC_EIPSW
enumsalwaysint	Enums Always Int option in the C/C++ Language Panel and pragma enumsalwaysint
exceptions	Enable C++ Exceptions option in the C/C++ Language Panel and pragma exceptions
export	Pragma export.

This argument	Corresponds to the
extended_errorcheck	Extended Error Checking option in the C/C++ Warnings settings panel and pragma extended_errorcheck.
far_data	Far Data option in the 68K Processor settings panel and pragma far_data.
far_strings	Far String Constants option in the 68K Processor settings panel and pragma far_strings.
far_vtables	Far Method Tables in the 68K Processor settings panel and pragma far_vtables.
faster_pch_gen	Pragma faster_pch_gen.
float_constants	Pragma float_constants
force_active	Pragma force_active.
fourbyteints	<b>4-Byte Ints</b> option in the 68K Processor settings panel and pragma fourbyteints.
fp_contract	Use FMADD & FMSUB option in the PPC Processor settings panel and pragma fp_contract.
global_optimizer	Global Optimization option in the PPC Processor settings panel and pragma global_optimizer.
IEEEdoubles	<b>8-Byte Doubles</b> option in the 68K Processor settings panel and pragma IEEEdoubles.
ignore_oldstyle	Pragma ignore_oldstyle.
import	Pragma import.
inline_intrinsics	Pragma inline_intrinsics.
internal	Pragma internal.
interrupt	Pragma interrupt.
k63d	<b>K6 3D Favored</b> option in the <b>Extended Instruction Set</b> menu of the <b>x86 CodeGen</b> settings panel and pragma k63d.

This argument	Corresponds to the
k63d_calls	MMX + K6 3D option in the Extended Instruction Set menu of the x86 CodeGen settings panel and pragma k63d_calls.
lib_export	Pragma lib_export.
little_endian	No option. It is 1 if you're compiling for a little endian target (such as x86) and 0 if you're compiling for a big endian target (such as Mac OS).
longlong	Pragma longlong.
longlong_enums	Pragma longlong_enums.
longlong_prepval	Pragma longlong_enums.
no_static_dtors	Pragma no_static_dtors.
macsbug	<b>MacsBug Symbols</b> option in the 68K Linker settings panel and pragma macsbug.
microsoft_exceptions	Pragma microsoft_exceptions.
microsoft_RTTI	Pragma microsoft_RTTI.
mmx	MMX option in the Extended Instruction Set menu of the x86 CodeGen settings panel and pragma mmx.
mmx_call	Pragma mmx_call.
mpwc	MPW C Calling Conventions option in the 68K Processor settings panel and pragma mpwc.
mpwc_newline	Map Newlines to CR option in the <u>C/C++ Language</u> <u>Panel</u> and pragma mpwc_newline.
mpwc_relax	Relaxed Pointer Type Rules option in the <u>C/C++</u> <u>Language Panel</u> and pragma mpwc_relax.
no_register_coloring	Global Register Allocation option in the 68K Processor settings panel and pragma no_register_coloring.
oldstyle_symbols	MacsBug Symbols option in the 68K Linker settings panel and pragma oldstyle_symbols

This argument	Corresponds to the
only_std_keywords	ANSI Keywords Only option in the C/C++ Language Panel and pragma only_std_keywords.
opt_common_subs	Pragma opt_common_subs.
opt_dead_assignments	Pragma opt_dead_assignments.
opt_dead_code	Pragma opt_dead_code.
opt_lifetimes	Pragma opt_lifetimes.
opt_loop_invariants	Pragma opt_loop_invariants.
opt_propagation	Pragma opt_propagation.
opt_strength_reduction	Pragma opt_strength_reduction.
opt_unroll_loops	Pragma opt_unroll_loops.
opt_vectorize_loops	Pragma opt_vectorize_loops.
pool_data	<b>Pool Data</b> option in the PPC Processor (for embedded PowerPC programming only) and pragma pool_data
pool_strings	<b>Pool Strings</b> option in the <u>C/C++ Language Panel</u> and pragma pool_strings
precompile	Whether the file is being pre-compiled.
preprocess	Whether the file is being pre-processed
profile	Generate Profiler Calls option in the 68K Processor settings panel, Emit Profiler Calls option in the PPC Processor settings panel, and pragma profile.
readonly_strings	Make String Literals Readonly option in the PPC Processor settings panel and pragma readonly_strings.
register_coloring	Pragma register_coloring.
require_prototypes	<b>Require Function Prototypes</b> option in the <u>C/C++</u> <u>Language Panel</u> and pragma require_prototypes.

This argument	Corresponds to the
RTTI	<b>Enable RTTI</b> option in the $C/C++$ Language Panel and pragma RTTI.
side_effects	Pragma side_effects.
simple_prepdump	Pragma simple_prepdump
SOMCallOptimization	Pragma SOMCallOptimization
SOMCheckEnvironment	Direct to SOM menu in the C/C++ Language Panel and pragma SOMCheckEnvironment
static_inlines	Pragma static_inlines
stack_cleanup	Pragma stack_cleanup.
suppress_init_code	Pragma suppress_init_code.
sym	Marker in the project window debug column and pragma sym
syspath_once	Pragma syspath_once.
toc_data	Store Static Data in TOC option in the PPC Processor settings panel and pragma toc_data
traceback	Pragma traceback.
trigraphs	Expand Trigraphs option in the <u>C/C++ Language</u> <u>Panel</u> and pragma trigraphs.
unsigned_char	Use Unsigned Chars option in the <u>C/C++ Language</u> <u>Panel</u> and pragma unsigned_char.
use_fp_instructions	<b>Use V810 Floating-Point Instructions</b> , which is part of the <b>NEC V800 Processor</b> and pragma use_fp_instructions.
use_frame	Pragma use_frame.
use_mask_registers	Use r20 and r21 as Mask Registers, which is part of the NEC V800 Processor and pragma use_mask_registers.

This argument	Corresponds to the
warn_emptydecl	<b>Empty Declarations</b> option in the C/C++ Warnings settings panel and pragma warn_emptydecl.
warn_extracomma	<b>Extra Commas</b> option in the C/C++ Warnings settings panel and pragma warn_extracomma.
warn_hidevirtual	<b>Hidden virtual functions</b> option in the C/++ Warnings settings panel and pragma warn_hidevirtual.
warn_illpragma	<b>Illegal Pragmas</b> option in the C/C++ Warnings settings panel and pragma warn_illpragma.
warn_implicitconv	<pre>Implicit Arithmetic Conversions option in the C/ C++ Warnings settings panel and pragma warn_implicitconv.</pre>
warn_notinlined	<b>Non-Inlined Functions</b> option in the C/C++ Warnings settings panel and pragma warn_notinlined.
warn_padding	pragma warn_padding
warn_possunwant	<b>Possible Errors</b> option in the C/C++ Warnings settings panel and pragma warn_possunwant.
warn_structclass	<b>Inconsistent Use of 'class' and 'struct' Keywords</b> option in the C/C++ Warnings settings panel and pragma warn_structclass.
warn_unusedarg	<b>Unused Arguments</b> option in the C/C++ Warnings settings panel and pragma warn_unusedarg.
warn_unusedvar	<b>Unused Variables</b> option in the C/C++ Warnings settings panel and pragma warn_unusedvar.
warning_errors	<b>Treat Warnings As Errors</b> option in the C/C++ Warnings settings panel and pragma warning_errors.
wchar_type	<b>Enable wchar_t Support</b> option in the C/C++ Language settings panel and pragma wchar_type.

ymbols		

# Index

Symbols	Numerics
#, and macros 38	3D 137
#else 39	MC68020 201
#endif 39	MC68881 201
#include files. See header files	
#pragma statements 90	Α
illegal 20	A5 200
=	
accidental 21	a6frames pragma 92 Access Paths preference panel 31
operator 59	Activate C++ Compiler option 64
?: conditional operator 65	address
A5 200	specifying for variable 40
builtin_align() 52	align pragma 93
builtin_type() 52	align_array_members pragma 94
cplusplus 200	Always Search User Paths option, Access Paths
DATE 199	panel 32
embedded_cplusplus 80, 200	always_inline pragma 95
FILE 199	AMD K6 126
fourbyteints 200	AMD K6 3D 137
ieeedoubles 200	anonymous structs 67
INTEL 201	ANSI Keywords Only option 41
LINE 199	ANSI_strict pragma 96
MC68020 201	arg_dep_lookup pragma 97
MC68881 201	arguments
MC68K 201	unnamed 38
MIPS 201	unused 23
MIPS_ISA2 201	ARM Conformance option 65
MIPS_ISA3 201	ARM_conform 66
MIPS_ISA4 202	ARM_conform pragma 97
mwbrowser 202	asm keyword 41
mwerks 202	assignment, accidental 21
option(), preprocessor function 202	auto_inline pragma 44,99
powerc 202	
POWERPC 202	В
PreInit() 60	
profile 202	base classes protected 65
_rol() 53	referring to functions in 61
ror() 53	Be OS 89, 162
STDC 199	bit rotation 53
stdcall 41	bool keyword 58,66
TIME 199	bool pragma 99
	by #pragma segment option 174

C	dont_inline pragma 44,115
catch statement 56, 66, 68, 118	dont_reuse_strings pragma 47,116
char 50	dyanamic_cast keyword 166
characters, multi-byte 42	dynamic_cast 69
check_header_flags pragma 100	dynamic_cast keyword 58
CIncludes 32	_
class	E
mixing with struct 27	ecplusplus pragma 116
code_seg pragma 101	EIPC_EIPSW pragma 117
code68020 pragma 101	#else 39
code68881 pragma 102	empty declarations 20
command line 32	Empty Declarations option 20
commas, extra 24	Enable Exception Handling option 66
comments, C++-styles 38	#endif 39
conditional operator 65	Enum Always Int option 33
const_cast keyword 58	enumerated types 24, 25, 33
conversion	enumsalwaysint pragma 117
implicit 26	=
warning 26	accidental 21
copy constructor 59	operator 59
cplusplus 200	errors
cplusplus pragma 65, 103	and warnings 20
cpp_extensions pragma 67,104	avoiding 24
	avoiding logical 21
D	Errors & Warnings window 142
D constant suffix 53	exception handling 66
-d option 32	exceptions pragma 118
d0_pointers pragma 105	.exp file 132
DATE 199	Expand Trigraphs option 42
declaration	explicit keyword 58
empty 20	export pragma 119
of templates 73	Export Symbols option 132
of variable in statements 65	Extended Error Checking option 24
def_inherited pragma 63, 106	extended_errorchecking pragma 26, 121
defer_codegen pragma 107	Extra Commas option 24
destructors 148	F
direct_destruction pragma 112	
direct_to_som pragma 113	false keyword 58
disable_registers pragma 114	far keyword 41
DLL 27	far_code pragma 123
dollar_identifiers pragma 114	far_data pragma 123
Don't Inline option 44	far_strings pragma 124
Don't Reuse Strings option 46	far_vtables pragma 124

FILE 199 File Mappings settings panel 64 flot_constants pragma 126 for statement 21,66 force_active pragma 126fourbyteints 200 fourbyteints pragma 127 fp_contract pragma 127 friend keyword 57 functions    virtual, hidden 26	<pre>inline_depth pragma 134 inline_intrinsics pragma 134 Inlining menu 43 instantiating     templates 76 integer formats 51INTEL 201 Intel MMX 137, 143 internal pragma 135</pre>
G	Japanese character set 44
global destructors 148	K
Global Register Allocation option 206	K6 3D 137
global_optimizer pragma 129	Kanji 44
	keywords, additional 41
Н	
header files 30	L
Hidden virtual functions option 26	lib_export pragma 138
1	libraries 27
1	LINE 199
IDE 64, 142	linking
identifiers 30	identifier length 30
length 30	logical errors 21, 24
ieeedoubles 200	long long 140
IEEEdoubles pragma 130 if statement 21,65	long long 51 longlong 138
ignore_oldstyle pragma 131	longlong_enums pragma 139
Illegal Pragmas option 20	longlong_prepval pragma 140
Implicit Arithmetic Conversions option 26	1011910119_p1 0p voil p1ugniu 110
import pragma 132	M
include files, see header files	macros
Inconsistent Use of 'class' and 'struct' Keywords	and # 38
option 27	macsbug pragma 140
infinite loop 21	main() 57
infinite loop, creating 22	mangled names 27, 30
inherited keyword 62, 106	Map Newlines to CR option 49
inherited keyword 62	MC68020 201
init_seg pragma 133	MC68881 201
inline 107	мс68к 201
warning 27 inline keyword 41	member function pointer 68 message pragma 142

# Index

microsoft_exceptions pragma 142	Р
microsoft_RTTI pragma 143	pack pragma 156
MIPS 201	parameter pragma 157
MIPS_ISA2 201	pascal keyword 41
MIPS_ISA4 202	pcrelstrings pragma 157
MIPS_ISA3 201	peephole pragma 158
MMX 137, 143	pointer to member function 68
mmx pragma 143, 144	pointer types 50
mpwc pragma 144	pointers_in_A0 pragma 159
mpwc_newline pragma 50,145	pointers_in_D0 pragma 159
mpwc_relax pragma 50,146	Pool Strings option 45
multi-byte characters 42	pool_data pragma 160
MultiMedia eXtensions 137, 143	pool_strings pragma 46,161
mutable keyword 58	pop pragma 162
MWBROWSER 202	Possible Errors option 21
MWERKS 202	powerc 202
	POWERPC 202
N	— — pragma
namespace keyword 58	illegal 20
near_code pragma 123	list of all 90
no_static_dtors pragma 148	scope 91
Non-Inlined Functions option 27	syntax 90
•	#pragma statements 90
0	illegal 20
oldstyle_symbols pragma 140	precompile_target pragma 162
once pragma 149	Prefix File 32
only_std_keywords pragma 42,149	PreInit() 60
operator= 59	preprocessor
opt_common_subs pragma 150	and # 38
opt_dead_assignments pragma 151	long long expressions 140
opt_dead_code pragma 151	profile 202
opt_lifetimes pragma 152	profile pragma 163
opt_loop_invariants pragma 152	protected base classes 65
opt_proagation pragma 153	prototypes
opt_strength_reduction pragma 153	requiring 47
opt_unroll_loops pragma 154	push pragma 162
opt_vectorize_loops pragma 154	Q
optimization_level pragma 129	·
optimize_for_size pragma 155	qualifed name syntax 75
option(), preprocessor function 202	В
options align= pragma 93	R
Options Checking 202	readonly_strings pragma 164
ı	reinterpret_char keyword 58

Relaxed Pointer Type Rules option 50 Require Function Prototypes option 47	syspath pragma 184
require_prototypes pragma 49,165	T
return statement	template class statement 77
empty 25	templates 72
missing 24	declaration 73
RTTI 66, 166	instantiating 76
RTTI option 67	TIME 199
RTTI pragma 166	toc_data pragma 184
Run-time type information 66, 166	traceback pragma 186
6	Treat All Warnings as Errors option 20
S	trigraph characters 42
scheduling pragma 167	trigraphs pragma 42,185
Section Mappings panel, NEC V800 112	true keyword 58
section pragma 167	try statement 56, 66, 68, 118
segment pragma 174	type_info 72
side_effects pragma 175	type-checking 50
simple class 59	typeid keyword 58
simple_prepdump pragma 176	typeid keyword 166
size_t 32	typename 75
sizeof() operator 32	
smart_code pragma 123	U
SOM Call Optimization pragma 176	Unicode 44
SOMCallStyle pragma 177	unnamed arguments 38
SOMCheckEnvironment pragma 178	unsigned char $50$
SOMClassVersion pragma 179	unsigned_char pragma 186
SOMMetaClass pragma 180	Unused Arguments option 23
SOMRelaseOrder pragma 181	unused pragma 22, 23, 187
stack_cleanup pragma 181	Unused Variables option 22
static destructors 148	Use Unsigned Chars option 50
static_cast keyword 58	use_fp_instructions pragma 188
static_inlines pragma 182	use_frame pragma 188
STDC 199	use_mask_registers pragma 188
string literals	using keyword 58
pooling 45	
reusing 46	V
struct mixing with class 27	variables
structs	declaring by address 40
anonymous 67	unused 22
anonymous 67 suffix, constant 53	unused 22 volatile 33
suffix, constant 53	unused 22 volatile 33 virtual
suffix, constant 53 suppress_init_code pragma 183	unused 22 volatile 33 virtual functions, hidden 26
suffix, constant 53	unused 22 volatile 33 virtual

#### Index

volatile variables 33

#### W

warn\_emptydecl pragma 21,189
warn\_extracomma pragma 24,190
warn\_hidevirtual pragma 191
warn\_illpragma pragma 20,191
warn\_padding pragma 193
warn\_possunwant pragma 22,194
warn\_structclass pragma 195
warn\_unusedarg pragma 24,196
warn\_unusedvar pragma 23,197
warning
 mixing class and struct 27
warning pragma 197

warning\_errors pragma 20, 189
warnings
as errors 20
definition of 18
empty declarations 20
extra commas 24
hidden virtual functions 26
illegal pragmas 20
implicit conversion 26
non-inlined functions 27
possible errors 21, 24
unused arguments 23
unused variables 22
wchar\_type pragma 198
while statement 21, 65

# CodeWarrior C Compilers Reference

#### **Credits**

writing lead: Marc Paquette

other writers: Mark Anderson, Gene Backlin, BitHead,

Jeff Mattson, Jim Trudeau

engineering: Mark Anderson, Bob Campbell, Ben

Combee, Pascal Cleve, Rajeev Gulati, Andreas Hommel, Udi Kalekin, Michael Kahl, Bob Kushlis, John McEnerney, Fred Peterson, Laurent Visconti, Rhonda Wit-

tels

frontline warriors: Richard Atwell, John C. Daub, Ron

Liechty, John Roseborough, Joel Sumner,

Jim Trudeau, L. Frank Turovich, CodeWarrior users everywhere



#### **Guide to CodeWarrior Documentation**

CodeWarrior documentation is modular, like the underlying tools. There are manuals for the core tools, languages, libraries, and targets. The exact documentation provided with any CodeWarrior product is tailored to the tools included with the product. Your product will not have every manual listed here. However, you will probably have additional manuals (not listed here) for utilities or other software specific to your product.

Core Documentation	
IDE User Guide	How to use the CodeWarrior IDE
Debugger User Guide	How to use the CodeWarrior debugger
CodeWarrior Core Tutorials	Step-by-step introduction to IDE components
Language/Compiler Documentation	
C Compilers Reference	Information on the C/C++ front-end compiler
Pascal Compilers Reference	Information on the Pascal front-end compiler
Error Reference	Comprehensive list of compiler/linker error messages, with many fixes
Pascal Language Reference	The Metrowerks implementation of ANS Pascal
Assembler Guide	Stand-alone assembler syntax
Command-Line Tools Reference	Command-line options for Mac OS and Be compilers
Plugin API Manual	The CodeWarrior plugin compiler/linker API
Library Documentation	
MSL C Reference	Function reference for the Metrowerks ANSI standard C library
MSL C++ Reference	Function reference for the Metrowerks ANSI standard C++ library
Pascal Library Reference	Function reference for the Metrowerks ANS Pascal library
MFC Reference	Reference for the Microsoft Foundation Classes for Win32
Win32 SDK Reference	Microsoft's Reference for the Win32 API
The PowerPlant Book	Introductory guide to the Metrowerks application framework for Mac OS
PowerPlant Advanced Topics	Advanced topics in PowerPlant programming for Mac OS
Targeting Manuals	
Targeting BeOS	How to use CodeWarrior to program for BeOS
Targeting Java VM	How to use CodeWarrior to program for the Java Virtual Machine
Targeting Mac OS	How to use CodeWarrior to program for Mac OS
Targeting MIPS	How to use CodeWarrior to program for MIPS embedded processors
Targeting NEC V810/830	How to use CodeWarrior to program for NEC V810/830 processors
Targeting Net Yaroze	How to use CodeWarrior to program for Net Yaroze game console
Targeting Nucleus	How to use CodeWarrior to program for the Nucleus RTOS
Targeting OS-9	How to use CodeWarrior to program for the OS-9 RTOS
Targeting Palm OS	How to use CodeWarrior to program for PalmPilot
Targeting PlayStation OS	How to use CodeWarrior to program for the PlayStation game console
Targeting PowerPC Embedded Systems	How to use CodeWarrior to program for PPC embedded processors
Targeting VxWorks	How to use CodeWarrior to program for the VxWorks RTOS
Targeting Win32	How to use CodeWarrior to program for Windows