F2: Artículos de soporte de Microsoft

Compilación de 24 artículos de MicrosoftDocs/SupportArticles-docs, commit aee5deb0299f00851f06ac2db644cb3198728a87. Contenido de Microsoft publicado bajo la licencia Creative Commons Attribution 4.0 International (CC BY 4.0). Se convirtió de Markdown a PDF y se quitaron imágenes y enlaces; el texto no se modificó.

Artículo 1: Outlook 2016 hangs at Processing at start-up

1.0 Overview

Original KB number: 3188434

1.1 Symptoms

You start Microsoft Outlook 2016, and it hangs at the Processing stage on the startup screen. Outlook never fully starts.

1.2 Resolution

This issue was fixed in the following updates:

- Office build 16.0.7369.2015 for Office 2016 Click-to-Run editions.
- March 2017 update for Microsoft Installer (.msi)-based edition of Office 2016.

1.3 Workaround Method 1 - Manually configure Outlook 2016 to always run maximized

1. Exit Outlook 2016.
2. Determine which icon you use to start Outlook, and access the Properties for that shortcut:

- Icon on the Desktop
- Right-click the Outlook icon on the Desktop, and then select Properties.
- Icon pinned to the taskbar

1. Right-click the Outlook icon on the taskbar, right-click Outlook 2016, and then select Properties.

- Icon pinned to the Start menu

1. Right-click the Outlook tile pinned to the Start menu, point to More, and then select Open file location.
2. Right-click Outlook 2016 in the File Explorer window that opens, and then select Properties.
3. In the Outlook 2016 Properties dialog box, select Maximized for Run.
4. Select OK.

1.4 Workaround Method 2 - Use Group Policy to configure Outlook 2016 to always run maximized

1. Start the Group Policy Management Console.

Note:

Because you may be applying the policy setting to an organizational unit and not to the whole domain, the steps may also vary in this aspect of applying a policy setting. Therefore, check your Windows documentation for more information.

2. In the Group Policy Management Console, under User Configuration, expand Preferences, expand Windows Settings, and then select Shortcuts.
3. Create a new shortcut with the following properties:

Name: Outlook 2016

Location: All Users Desktop

Target path: \

Arguments: /recycle

Start in: \

Run: Maximized

Icon file path: \

Note:

The path of Outlook.exe may vary, depending on the Office installation type and bitness of Windows and Office, as follows.

Office installation type | Bitness of Windows and Office | Default path of Office

Click-to-Run | Same | C:\Program Files\Microsoft Office\root\Office16\

Click-to-Run | Different | C:\Program Files (x86)\Microsoft Office\root\Office16\

MSI | Same | C:\Program Files\Microsoft Office\Office16\

MSI | Different | C:\Programs Files (x86)\Microsoft Office\Office16\

Same Bitness: Office 32-bit running on Windows 32-bit or Office 64-bit running on Windows 64-bit

Different Bitness: Office 32-bit running on Windows 64-bit

4. Copy the shortcut that you created, and then paste it to duplicate it.
5. Double-click the shortcut that you pasted, and then change the Location to All Users Start Menu. Select OK.
6. Copy the shortcut that you created, and then paste it to duplicate it.
7. Double-click the shortcut that you pasted, and then change the Location to All Users Programs. Select OK.

Note:

If a user has an Outlook 2016 shortcut pinned to their taskbar, this will not replace it. The user can unpin the shortcut from their taskbar and then re-pin it from one of the other locations after the policy is in effect.

1.5 Workaround Method 3 - Manually delete the Outlook Frame value from the registry

Important:

Follow the steps in this section carefully. Serious problems might occur if you modify the registry incorrectly. Before you modify it, back up the registry for restoration in case problems occur.

1. Exit Outlook 2016.
2. Use one of the following procedures to start Registry Editor.

- Windows 10, Windows 8.1, and Windows 8: Press Windows Key+R to open a Run dialog box. Type

regedit.exe, and then select OK.

- Windows 7: Select Start, type regedit.exe in the search box, and then press Enter.

3. In Registry Editor, locate and then select the following subkey in the registry:

HKEY_CURRENT_USER\SOFTWARE\Microsoft\Office\16.0\Outlook\Office Explorer

4. In the details pane, select the Frame value.
5. On the Edit menu, select Delete.
6. Select Yes to confirm that you want to delete this value.
7. Exit Registry Editor.
8. Start Outlook 2016.

Note:

You may have to follow these steps again if the issue occurs repeatedly. If you find the issue occurs frequently, it might be better to use a different method to work around the issue.

1.6 Workaround Method 4 - Create a .reg file to reset the Outlook Frame value in the registry

Important:

Follow the steps in this section carefully. Serious problems might occur if you modify the registry incorrectly. Before you modify it, back up the registry for restoration in case problems occur.

1. Start Notepad.
2. Copy the following text and paste it into Notepad:

Windows Registry Editor Version 5.00

[HKEY_CURRENT_USER\SOFTWARE\Microsoft\Office\16.0\Outlook\Office Explorer]

"Frame"=hex:

3. On the File menu, select Save As.
4. Browse to a convenient location to create the .reg file, such as the Desktop.
5. For Save as type, select All Files (.).
6. Enter a file name and the file name extension .reg, such as Reset Outlook Frame.reg.
7. Select Save.
8. When the issue occurs, exit Outlook and then double-click the .reg file to reset the Outlook Frame value to work around the issue.

1.7 Workaround Method 5 - Use Group Policy to delete the Outlook Frame value from the registry

Important:

Follow the steps in this section carefully. Serious problems might occur if you modify the registry incorrectly. Before you modify it, back up the registry for restoration in case problems occur.

1. Start the Group Policy Management Console.

Note:

Because you may be applying the policy setting to an organizational unit and not to the whole domain, the steps may vary in this aspect of applying a policy setting. Check your Windows documentation for more information.

2. In the Group Policy Management Console, under User Configuration, expand Preferences, expand Windows Settings, and then select Registry.

3. Create a registry item that has the following properties:

Action: Delete

Hive: HKEY_CURRENT_USER

Key Path: SOFTWARE\Microsoft\Office\16.0\Outlook\Office Explorer

Value Name: Frame

4. Select OK.

1.8 Workaround Method 6 - Use a logon script to delete the Outlook Frame value from the registry

Important:

Follow the steps in this section carefully. Serious problems might occur if you modify the registry incorrectly. Before you modify it, back up the registry for restoration in case problems occur.

Include the following PowerShell command in your logon script:

```
remove-itemproperty 'HKCU:\SOFTWARE\Microsoft\Office\16.0\Outlook\Office Explorer' -Name Frame
```

Artículo 2: Outlook not responding error or Outlook freezes

2.0 Overview

2.1 Symptoms

When you open a file or send an email message in Microsoft Outlook 2010 or later versions, Outlook freezes. Or, you receive the following error message:

Outlook not responding

2.2 Cause

This problem occurs for one or more of the following reasons:

- You don't install the latest updates.
- Outlook is in use by another process.
- Outlook is loading external content, such as images in an email message.
- A previously installed add-in is interfering with Outlook.
- Your mailboxes are too large.
- Your AppData folder is redirected to a network location.
- You have to repair your Microsoft 365 programs.
- Outlook data files are corrupted or damaged.
- Your installed antivirus software is outdated, or it conflicts with Outlook.
- Your user profile has become corrupted.
- Another program conflicts with Outlook.

Many of these items can be automatically checked by the Classic Outlook Advanced Diagnostics troubleshooter.

Note:

- The troubleshooter doesn't work in new Outlook for Windows.

- To run the troubleshooter, make sure that you're using the same Windows device that classic Outlook is installed on. Additionally, make sure that your device is running Windows 10 or a later version.

To run the troubleshooter, follow these steps:

1. Select the following button to start the troubleshooter.

[!div class="nextstepaction"]

Classic Outlook Advanced Diagnostics troubleshooter

If you receive a pop-up window that displays "This site is trying to open Get Help.", select Open.

1. Follow the instructions in the Get Help app to run the troubleshooter.

After the troubleshooter finishes, it displays the results and provides additional information about how to resolve the issue.

2.3 Resolution

To resolve this problem, make sure that your computer meets the Outlook 2016 system requirements, Outlook 2013 system requirements) or Outlook 2010 system requirements).

Note:

These steps are provided in a specific order based on commonality and complexity. Follow these steps in the given order.

Step 1 - Install the latest updates

The Office installation on your computer might not be up to date. The reason might be because Windows Update isn't configured on your computer to automatically download and install recommended updates. By installing important, recommended, and optional updates, you can often correct problems by replacing out-of-date files and fixing vulnerabilities. To install the latest updates, select the link for your version of Windows, and then follow the steps in the article:

- Install Windows updates in Windows 10
- Windows Update FAQ for Windows 8.1
- Install Windows updates in Windows 7
- Install Windows updates in Windows Vista
- Install Windows updates in Windows XP

Make sure that the latest updates for Outlook are installed. For more information, see How to install the latest applicable updates for Microsoft Outlook (US English only).

Step 2 - Make sure that Outlook isn't in use by another process

Performance may be decreased if you use the Outlook AutoArchive feature or sync to Outlook with a mobile device. These processes can use a large number of resources.

If Outlook is in use by another process, this information is displayed in the status bar at the bottom of the screen. If you try to perform other actions while Outlook is in use, Outlook may not respond. Let the task in process finish its job before you try another action.

Step 3 - Check the problem caused by external content

To resolve this issue, use one of the following methods:

- Prevent Outlook to download external contents. To do so, go to File > Options > Trust Center > Automatic Download, select the following two options:
- Don't download pictures or other content automatically in HTML e-mail option.
- Warn me before downloading content when editing, forwarding, or replying e-mail.
- Avoid sending such an email with external source.

Step 4 - Investigate possible add-in issues

Although add-ins can enhance your user experience, they can occasionally interfere or conflict with Outlook. Try to start Outlook without any add-ins running.

How to start Outlook without add-ins

1. Do the following, as appropriate for your operating system:

- If you're running Windows 8, swipe in from the right edge of the screen, and then tap Search. (If you're using a mouse, point to the upper-right corner of the screen, move the mouse pointer down, and then select Search.) Type Run in the search box, and then tap or select Run.

- If you're running Windows 10, Windows 7 or Windows Vista, select Start.

- If you're running Windows XP, select Start, and then select Run.

2. Type Outlook.exe /safe, and then select OK.

3. If the problem is resolved, select Options on the File menu, and then select Add-Ins.

4. Select COM Add-ins, and then select Go.

5. Clear all the check boxes in the list, and then select OK.

6. Restart Outlook.

If the problem doesn't occur after you restart Outlook, one of the add-ins is likely the cause of the problem. Restore the add-ins one at a time until the problem does occur to determine which add-in is causing the problem.

Step 5 - Check whether your mailbox is too large

As your mailbox size increases, more resources are required to open each folder. If you have a large number of items in any single folder, you may experience performance issues during certain operations. For more information, see Outlook performance issues when there are too many items or folders in a cached mode .ost or .pst file.

We recommend that you move several items in your larger folders to separate folders, or that you archive those items by using the AutoArchive feature.

How to create a folder

1. On the Folder tab, select New Folder in the New group.

2. In the Name box, enter a name for the folder.

3. In the Select where to place the folder list, select the location for the new folder.

Note:

The new folder becomes a subfolder of the folder you select.

4. Select OK.

To manage your mailbox by reducing the size of the Outlook data file, see Reduce the size of Outlook Data Files (.pst and .ost).

To manage your mailbox by using the AutoArchive feature, see AutoArchive settings explained.

Step 6 - Check whether your AppData folder is being redirected to a network location

Outlook stores certain data, such as email signatures and the spelling checker dictionary, in the AppData folder. If the network is performing slowly, Outlook must wait for read and write operations to the AppData directory to finish.

How to disable redirection of the AppData directory

1. Exit Outlook.

2. Start Registry Editor. To do so, use one of the following procedures, as appropriate for your version of Windows:

- Windows 10 or Windows 8: Press Windows Key+R to open a Run dialog box. Type regedit.exe and then press OK.

- Windows 7: Select Start, type regedit.exe in the search box, and then press Enter.

3. In Registry Editor, locate and then select the following subkey:

HKEY_CURRENT_USER\Software\Microsoft\Windows\CurrentVersion\Explorer\User Shell Folders

4. Locate and then double-click the AppData value.

5. In the Value data box, type the following path, and then select OK:

%USERPROFILE%\AppData\Roaming

6. Exit Registry Editor.

Step 7 - Repair Office programs

You can automatically repair your Office program files to resolve such problems as Outlook freezing or not responding.

How to automatically repair Office

1. Exit any Microsoft Office programs that are running.

2. Open Control Panel, and then open Programs and Features (if you're running Windows 10, Windows 8, or Windows 7).

3. In the list of installed programs, right-click Microsoft Office 2016, Microsoft Office 2013, or Microsoft Office 2010, and then select Repair.

Step 8 - Repair Outlook data files

When you install Outlook, an Inbox repair tool (scanpst.exe) is also installed on your PC. The Inbox repair tool can resolve problems by scanning your Outlook data files, and repairing errors. To use the Inbox repair tool, exit Outlook, and then follow the steps in Repair Outlook Data Files (.pst and .ost).

Step 9 - Check whether antivirus software is up-to-date or conflicts with Outlook

If your antivirus software isn't up-to-date, Outlook may not function correctly.

How to check whether antivirus software is up to date

To keep up with new viruses as they're created, antivirus software vendors periodically provide updates that you can download from the Internet. Download the latest updates by visiting your antivirus software vendor's website.

For a list of antivirus software vendors, see Consumer antivirus software providers for Windows.

How to check whether antivirus software conflicts with Outlook

If your antivirus software includes integration with Outlook, you may experience performance issues. You can disable all Outlook integration within the antivirus software. Or, you can disable any antivirus software add-ins that are installed in Outlook.

Important:

When you change your antivirus settings, it may make your PC vulnerable to viral, fraudulent, or malicious attacks. We don't recommend that you try to change your antivirus settings. Use this workaround at your own risk.

You may have to contact your antivirus software vendor to determine how to configure the software to exclude any integration with Outlook or to exclude scanning in Outlook.

Note:

If you also plan to perform file-level virus scanning of .pst, .ost, Offline Address Book (.oab), or other Outlook files while Outlook is in use, see Plan antivirus scanning for Outlook 2010) or Planning considerations for deploying Outlook 2016 for Windows.

Step 10 - Create a user profile in Outlook

To create a user profile, follow these steps:

1. In Control Panel, select Programs, select User Accounts, and then select Mail to open Mail items.
2. Select Show Profiles.
3. Select the profile that you want to remove, and then select Remove.
4. Select Add.
5. In the Profile Name dialog box, type a name for the profile.
6. Specify the user name, the primary SMTP address, and the password. Then, select Next.
7. You may receive the following prompt:

Allow this website to configure settings?

In this prompt, select the Don't ask me about this again checkbox, and then select Allow.

Step 11 - Perform a Selective Startup (advanced users)

When you start Windows normally, several applications and services start automatically and then run in the background. These applications and services can interfere with Outlook. A Selective Startup or "clean boot" process can help you identify problems that are caused by application conflicts.

If you use the Selective Startup option in System Configuration, you can turn services and startup programs on or off individually to check whether the problem occurs the next time that you start your computer. In System Configuration, if you select a check box, the related service or startup program runs when you restart the computer. If the check box is cleared, the service or startup program doesn't run when you restart the computer.

Follow this procedure to use the process of elimination to identify the problem in Windows 10, Windows 8, Windows 7, or Windows Vista.

Note:

For more information about performing a clean boot, see How to perform a clean boot in Windows.

How to do a Selective startup

1. In Control Panel, select System and Security, select Administrative Tools, and then double-click System Configuration.

Note:

If you're prompted for an administrator password or for confirmation, type the password or provide confirmation.

2. Select the General tab, select Selective startup, and then clear the Load system services and the Load

startup items check boxes.

3. Select the Load system services check box, select OK, and then select Restart.

4. If the problem reoccurs after you restart the computer, do one or both of the following tasks, as necessary.

To determine which system service is causing the problem

1. In System Configuration, select the Services tab, select Disable all, select the check box for the first service that is listed, and then restart the computer.

Note:

If the problem doesn't reoccur, then you can eliminate the first service as the cause of the problem.

2. With the first service selected, select the second service check box, and then restart the computer.

3. Repeat this process until you reproduce the problem.

Note:

If you can't reproduce the problem, you can eliminate system services as the cause of the problem.

To determine which startup item is causing the problem

1. In System Configuration, select the General tab, and then select the Load startup items check box.

2. Select the Startup tab, select Disable all, select the check box for the first startup item that is listed, and then restart the computer.

Note:

If the problem doesn't reoccur, you can eliminate the first startup item as the cause of the problem.

3. While the first startup item is selected, select the second startup item check box, and then restart the computer. Repeat this process until you reproduce the problem.

Step 12 - Create a Windows user profile (advanced users)

Your user profile is a collection of settings that let you customize the computer appearance and performance. It contains settings for desktop backgrounds, screen savers, sound settings, and other features. User profiles help make sure that your personal preferences are used when you log on to Windows.

To determine whether this problem is caused by a corrupted user profile, create a user profile to see whether the problem still occurs when you use the new profile.

How to repair a corrupted user profile in Windows 8

Step 1 - Create a user account

To create a user profile, you must first create a user account. When the new account is created, a profile is also created.

1. Swipe in from the right edge of the screen, and then tap Search. (If you're using a mouse, point to the upper-right corner of the screen, move the mouse pointer down, and then select Search.) Type Command Prompt in the search box, right-click Command Prompt, and then select Run as administrator.

Note:

If you're prompted for an administrator password or for confirmation, type the password or provide

confirmation.

2. Type net user UsernamePassword /add, and then press Enter.

Step 2 - Copy old files to the new user profile After you create the profile, you can copy the files from the existing profile**

Note:

You must have at least three user accounts on the computer to complete these steps. This includes the new account you created.

1. Sign in as a user other than the user that you just created or the user that you want to copy files from.
2. In Control Panel, select Appearance and Personalization, and then select Folder Options.
3. Select the View tab, and then select Show hidden files, folders, and drives.
4. Clear the Hide protected operating system files check box, select Yes to confirm, and then select OK.
5. Open File Explorer. To do this, Swipe in from the right edge of the screen, and then tap Search. (If you're using a mouse, point to the upper-right corner of the screen, move the mouse pointer down, and then select Search.) Enter File Explorer in the search box, tap or select Apps, and then tap or select File Explorer. Type Command Prompt in the search box, right-click Command Prompt, and then select Run as administrator.
6. Locate the C:\Users\Old_Username folder, in which C is the drive that Windows is installed on, and Old_Username is the name of the profile that you want to copy files from.
7. Select all the files and folders in this folder, except the following files:

- Ntuser.dat
- Ntuser.dat.log
- Ntuser.ini

8. On the Edit menu, select Copy.

Note:

If you don't see the Edit menu, press Alt.

9. Locate the C:\Users\New_Username folder, in which C is the drive that Windows is installed on, and New_Username is the name of the user profile that you created earlier in this method.
10. On the Edit menu, select Paste.
11. Sign out, and then sign in as the new user.

Note:

If you have email messages in an email program, you must import your email messages and addresses to the new user profile before you delete the old profile. If everything is working correctly, you can now delete the old profile.

2.4 Next step

If the information in this article does not help resolve your problem in Outlook 2016, Outlook 2013 or Outlook 2010, see the following resources for more information:

- Perform a search to find more online articles about this specific error
- Visit the Microsoft Community online to post your question about this error
- Find the appropriate phone number to contact Microsoft Support

2.5 References

- Fix a corrupted user profile in Window 7
- Create a user account in Windows

Artículo 3: Cannot start Outlook in cached mode

3.0 Overview

Original KB number: 3046189

3.1 Symptom

When you start Microsoft Outlook in cached mode, you receive the following error message:

Cannot start Microsoft Outlook. Cannot open the Outlook window. The set of folders cannot be opened. There is not enough memory available to perform the operation.

Note:

This error message is also displayed when you try to create a new Outlook profile that is configured to use cached mode.

3.2 Cause

This problem occurs because the hidden PR_OST_OSTID property in your mailbox is larger than 32 kilobytes (KB).

This property is located on Top of Information Store in the default store. Every time that you create a new cached mode profile for the mailbox, approximately 20 bytes of data is added to this property. Eventually, the size of the data in the property exceeds approximately 32,720 bytes, and you start to receive the error.

3.3 Resolution

To resolve this problem, remove the data in the PR_OST_OSTID binary property. To do this, follow these steps:

1. Download and extract the MFCMAPI tool.
2. Launch Mfcmapi.exe, and then select OK to move through the introduction screen.
3. On the Tools menu, select Options.
4. Enable the following options, and then select OK:
- Use the MDB_ONLINE flag when calling OpenMsgStore
- Use the MAPI_NO_CACHE flag when calling OpenEntry
5. On the Session menu, select Logon.
6. Select the Outlook cached mode profile for the mailbox, and then select OK.
7. Double-click the email address that represents the mailbox in question.
8. In the navigation pane, expand Root Container, and then select Top of Information Store.
9. In the right-side pane, locate the PR_OST_OSTID property.

Note:

You may see PR_OST_OSTID under the Property names column or the Other names column. If it is found under the Property names column, the value under the Tag column is 0x7C040102. If PR_OST_OSTID is found under the Other names column, the value under the Tag column is 0x7C04000A.

1. If the value under the Tag column is 0x7C040102, then double-click PR_OST_OSTID to open the Property Editor.

2. If the value under the Tag column is 0x7C04000A, then right-click PR_OST_OSTID, select Edit as stream, and then select Binary.

10. Right-click the data in the Binary section of Property Editor, and then select Select All.
11. Right-click the selected data in the Binary section, and then select Delete.
12. Select OK.
13. Exit the MFCMAPI tool, and then start Outlook.

3.4 More information

There are several scenarios in which this situation might occur:

1. Many users sign in to the mailbox repeatedly. (For example, many users sign in to a mailbox that is used to answer public or service communications.)
2. Many users open a shared resource mailbox when Download shared folders is enabled in the Outlook profile.
3. Someone is creating new cached mode profiles for their mailbox repeatedly. (This occurs only rarely.)

Artículo 4: Error 0x8004010F when sending or receiving email

4.0 Overview

Original KB number: 2659085

4.1 Summary

This issue is caused by the corrupted Outlook profile. You can try to create a new profile to resolve the issue.

4.2 Symptoms

When you try to send or to receive email in Outlook 2010, you may receive one of these error messages:

0x8004010F: Outlook data file cannot be accessed.

or

0x8004010F: The operation failed. An object could not be found.

4.3 Resolution

To resolve error 0x8004010F, identify the current location of your default Outlook data file, and then create a new Outlook profile. To do this follow these steps:

Step 1 - Locate the default Outlook data file

1. Select Start, and then select Control Panel.
2. In Control Panel, select Mail.
3. In the Mail Setup - Outlook dialog box, select Show Profiles.
4. Select your current Outlook profile, and then select Properties.
5. In the Mail Setup - Outlook dialog box, select Data Files.
6. Select the Data Files tab in the Account Settings dialog box, and then note the name and location of the default data file for your profile (a check mark will denote the default data file).
7. Select Close.

Step 2 - Create a new Outlook profile

[!VIDEO https://videoplayercdn.osi.office.net/embed/7ef2bbef-531d-4165-809f-7b928486d318]

Method 1 - Use auto account setup to create an IMAP or POP3 email account

Important:

If your email server supports both IMAP and POP3, auto account setup will create an IMAP account by default. You will need to follow the manual steps in order to create a POP3 account. However, if your email server supports ONLY a POP3, auto account setup will create a POP3 account.

1. Select Start, and then select Control Panel.
2. In the Mail Setup - Outlook dialog box, select Show Profiles.
3. On the General tab in the Mail dialog box, select Add.
4. In the New Profile dialog box, type a new profile name, and then select OK.

5. In the Add Account dialog box, type your email account information, and then select Next.
6. After your account is successfully configured, select Finish.

Method 2 - Manually create an IMAP or POP3 email account

1. Select Start, and then select Control Panel.
2. In the Mail Setup - Outlook dialog box, select Show Profiles.
3. On the General tab in the Mail dialog box, select Add.
4. In the New Profile dialog box, type a new profile name, and then select OK.
5. In the Add Account dialog box, select Manually configure server settings or additional server types, and then select Next.
6. In the Choose Service dialog box, select Internet E-mail, and then select Next.
7. In the Internet E-mail Settings dialog box, type your account details.
8. Select Test Account Settings to test your account.

Note:

Contact your Internet service provider if you are unsure of the correct account details.

9. Select Existing Outlook Data File, and then select Browse.
10. In the Open Outlook Data File dialog box, browse to and then select the Outlook data file you previously located. Select OK.
11. Select Next.
12. In the Test Account Settings dialog box, select Close.
13. Select Finish.

Step 3 - Configure your new Outlook profile as the default profile

If you want to set the new Outlook profile as the default profile, follow these steps:

1. On the General tab of the Mail dialog box, select Always use this profile.
2. Select the drop-down under Always use this profile, and then select the new profile.
3. Select OK to close the Mail dialog box.

4.4 More information

If you have several non default .pst files and need to include them in your Outlook profile, follow these steps:

1. Start Outlook.
2. On the File tab, select Open.
3. Select Open Outlook Data File.
4. Browse to the folder location that contains your other .pst file, select it, and then select OK.

The newly added .pst file will appear in the Navigation pane.

Artículo 5: Outlook send receive errors HTTP 0 HTTP 404 HTTP 500

5.0 Overview

5.1 Symptoms

When you are using Microsoft Outlook 2010 or Microsoft Outlook 2013, you receive the following error in the Outlook status bar:

Send/Receive Error

When you select the error, the Outlook Send/Receive Progress dialog opens and displays one or more of the following errors:

Task 'SharePoint' reported error (0x80040102) : 'Outlook cannot connect to the SharePoint List (site name - list name). The server may not be reachable from your location. Contact the SharePoint site administrator for more information. HTTP 0.'

Task 'SharePoint' reported error (0x8004010F) : 'The SharePoint List (site name - list name) cannot be found. If the problem continues, contact the SharePoint site administrator. HTTP 404.'

Task 'SharePoint' reported error (0x80004005) : 'An error occurred in this SharePoint List (site name - list name). Try updating the folder again. If the problem continues, contact the SharePoint site administrator. HTTP 500.

The server returned the following error message: Exception of type

'Microsoft.SharePoint.SoapServer.SoapServerException' was thrown.'

5.2 Cause

The SharePoint list no longer exists or you cannot connect to it.

5.3 Resolution

If you no longer have to synchronize with the specific SharePoint list mentioned in the error, follow these steps to remove the SharePoint list from Outlook:

1. Select File, and then select Account Settings.
2. Select Account Settings, and then select SharePoint Lists.
3. In the Account Settings dialog box, double-click the SharePoint list for which you received the error.
4. Clear the check on Display this list on other computers with the account: and then select OK.
5. Make sure that the SharePoint list for which you received the error is still selected, and then select Remove.
6. Close the Account Settings dialog box.

Note:

If you have multiple Outlook clients connected to the same email account, you may have to wait until the changes are synchronized to your other Outlook clients. If the SharePoint List is still listed on the other Outlook clients, repeat these steps on each of those clients.

Artículo 6: Clear the Teams client cache

6.0 Overview

6.1 Summary

This article lists the types of issues for which you shouldn't clear the Teams cache and provides the steps to delete the cache both in Teams for Windows and Teams for Mac when appropriate.

6.2 Is clearing the Teams cache the right option to resolve your issue?

Important:

We don't recommend that you clear the cache for issues with Microsoft Teams chats or channels such as missing messages, chat history not loading, a channel or team not appearing, or notifications and unread counts being wrong. Clearing the Teams cache doesn't fix these issues but deletes the diagnostic logs that are needed to find the cause.

You can clear the Teams cache as a targeted step for a small number of problems with the local client. However, it is not a general first step for all issues that you see in the Teams app. After you clear the cache, restart Teams. The restart process after you clear the cache might take longer than usual because the Teams cache files have to be rebuilt.

6.3 Clear the cache in Teams for Windows

Classic Teams

1. If Teams is still running, right-click the Teams icon on the taskbar, and then select Quit.
1. Open the Run dialog box by pressing the Windows logo key :::image type="icon" source="media/clear-teams-cache/windows-logo-key.png"::: +R.
1. In the Run dialog box, enter the following path, and then select OK:

```
%appdata%\Microsoft\Teams
```

1. Delete all files and folders in the directory.
1. Restart Teams.

New Teams

Method 1: Reset the app

Note:

When you reset the Teams app, the app data is deleted. This data includes any personalization settings that you configured.

1. Type settings in the search box, and then select the Settings app from the results.
1. Select Apps > Installed apps, and then type Microsoft Teams in the search box.
1. Locate the New Microsoft Teams app from the results, select the More options button (...) on the right, and then select Advanced options.
1. In the Reset section, select Reset.
1. Restart Teams.

Method 2: Delete the files

1. If Teams is still running, right-click the Teams icon on the taskbar, and then select Quit.
1. Open the Run dialog box by pressing the Windows logo key :::image type="icon" source="media/clear-teams-cache/windows-logo-key.png"::: +R.
1. In the Run dialog box, enter the following path, and then select OK.

```
%userprofile%\appdata\local\Packages\MSTeams_8wekyb3d8bbwe\LocalCache\Microsoft\MSTeams
```

1. Delete all files and folders in the directory.
1. Restart Teams.

6.4 Clear the cache in Teams for macOS

Classic Teams

1. If Teams is still running, right-click the Teams icon in the dock, and then select Quit or press Command (?)-Q.
1. In the Finder, open the /Applications/Utilities folder, and then double-click Terminal.
1. Enter the following command, and then press Return:

```
rm -r ~/Library/Application\ Support/Microsoft/Teams
```

1. Restart Teams.

New Teams

1. If Teams is still running, right-click the Teams icon in the dock, and then select Quit or press Command (?)-Q.
1. In the Finder, open the /Applications/Utilities folder, and then double-click Terminal.
1. Enter the following commands, and press Return after each command:

```
rm -rf ~/Library/Group Containers/UBF8T346G9.com.microsoft.teams
rm -rf ~/Library/Containers/com.microsoft.teams2
```

1. Restart Teams.

Artículo 7: Fix screen sharing video display lag issue in Teams

7.0 Overview

7.1 Summary

When you share a video or other high-motion content during a Microsoft Teams call, attendees might see lag or dropped frames. Teams normally uses a low screen-sharing frame rate to keep static content sharp. This article explains how to enable high-motion screen sharing in Teams 1.6.00.12455 and later, and explains that a higher frame rate might reduce the shared content's resolution.

7.2 Symptoms

During a call in Microsoft Teams, when you share a video or other content that requires a higher frame rate for optimal viewing, the display for the other attendees appears to lag and frames are intermittently dropped.

7.3 Cause

By default, the frame rate for screen sharing in Teams is set to a low frame rate. This is because commonly shared content, such as an Excel workbook or Word document, is static. The low frame rate makes sure that attendees see the highest possible resolution of the shared content.

However, the default setting can be problematic when a user shares a video. The video may appear to lag because of the low frame rate.

7.4 Resolution

In Teams 1.6.00.12455 and later versions, you can use a keyboard shortcut to enable high-motion screen sharing. Follow these steps:

1. Start sharing your screen in Teams.
1. Select the Teams app, and then select Ctrl+Alt+Shift+T.

The resolution of the shared content might drop to accommodate the higher frame rate. This depends on several factors, such as device capability and available bandwidth.

Note:

The keyboard shortcut will be deprecated soon. There is a new presenter control toolbar that enables a user to optimize for video when screen sharing. For more information, see Share content in Microsoft Teams meetings.

7.5 More information

After you run the keyboard shortcut, you won't see any visual indication that high-motion viewing is enabled for you. The keyboard shortcut is a toggle. If you use it two times, the Teams app will return to the default behavior of not forcing high-motion screen sharing.

To check the frame rate for the content that's shared, follow these steps:

1. In the Teams meeting, select the More menu option.

1. On the More menu, select Settings, and then select Call health.

1. To see the frame rate, resolution, and other details about the screen-sharing session, scroll to the Screen Sharing section.

Artículo 8: Troubleshoot Windows Update Error 0x80070005

8.0 Overview

8.1 Summary

Windows Update error 0x80070005 (E_ACCESSDENIED) occurs if the update process can't access required files, folders, or registry entries. This error typically indicates a permissions problem that affects the Windows component store, the Software Distribution folder, or related system resources.

This article provides steps to resolve this issue on supported versions of Windows client, Windows Server, and Microsoft Azure Virtual Machines (VMs).

8.2 Symptoms

You install a Windows update, but the installation fails, and you see error code 0x80070005 (E_ACCESSDENIED) reported.

To get more information, review the following resources:

1. Review the WindowsUpdate.log file or the CBS.log file. Look for entries that resemble the following example:

```
Error                         CBS     Failed to create file. [HRESULT = 0x80070005 - E_ACCESSDENIED]
Error                 CBS    Failed to internally open package. [HRESULT = 0x80070005 - E_ACCESSDENIED]
```

1. Review the Windows Update log. To generate a static copy of the log file, open a Windows PowerShell Command Prompt window, and then run the following cmdlet:

```
Get-WindowsUpdateLog
```

Search the output for 0x80070005 entries. For more information about the log file, see Windows Update log files.

8.3 Cause

This error occurs if one of the following conditions exists:

- The TrustedInstaller service account doesn't have permissions on the %windir%\WinSxS folder or the %windir%\SoftwareDistribution folder.
- The permissions on the registry subkey HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Component Based Servicing aren't correct.
- A third-party antivirus or security tool locked update-related files or folders.
- The SYSTEM account doesn't have the Full Control permission on the %windir% folder.
- A Group Policy setting or a management agent restricted write access to system directories.

Note:

%windir% represents the Windows system folder. The default folder name and location is "C:\Windows."

8.4 Resolution

Important:

Before you troubleshoot this issue, back up the operating system disk. For information about this process for VMs, see About Azure Virtual Machine restore.

Step 1: Reset the permissions on the component store

To reset the default permissions on the Windows component store, open an administrative Command Prompt window, and then run the following commands:

```
icacls "%windir%\WinSxS" /reset /t /c /q
icacls "%windir%\SoftwareDistribution" /reset /t /c /q
```

After you run these commands, restart the computer, and try again to install the update. If the update still doesn't install, go to step 2.

Step 2: Make sure that TrustedInstaller owns the WinSxS folder

To designate that the TrustedInstaller account owns the WinSxS folder, run the following command at the command prompt:

```
icacls "%windir%\WinSxS" /setowner "NT SERVICE\TrustedInstaller" /t /c /q
```

After you run these commands, restart the computer, and try again to install the update. If the update still doesn't install, go to step 3.

Step 3: Reset Windows Update components

If the error persists, reset all Windows Update components. At the command prompt, run the following commands:

```
net stop wuauserv
net stop bits
net stop cryptSvc
ren %windir%\SoftwareDistribution SoftwareDistribution.old
ren %windir%\System32\catroot2 catroot2.old
net start cryptSvc
net start bits
net start wuauserv
```

After you run these commands, restart the computer, and try again to install the update. If the update still doesn't install, go to step 4.

Step 4: Repair the component store

To repair the component store, run the following command at the command prompt:

```
DISM /Online /Cleanup-Image /RestoreHealth
```

Note:

By default, DISM uses Windows Update as a repair source. For information about how to specify a different repair source, see Repair a Windows Image.

After you run this command, restart the computer, and try again to install the update. If the update still doesn't install, go to step 5.

Step 5: Check system file integrity

To verify the integrity of the system files, run the following command at the command prompt:

```
sfc /scannow
```

If this command identifies issues, see Use the System File Checker tool to repair missing or corrupted system files.

After this command finishes without errors, restart the computer. Try again to install the update. If it still doesn't install, go to step 6.

Step 6: Check for third-party interference

To make sure that third-party applications or drivers don't interfere in the update process, follow these steps:

1. On the affected computer, temporarily disable real-time antivirus protection.

1. To list the file system filter drivers, run the following command at the command prompt:

```
fltmc
```

1. If the list includes a non-Microsoft filter driver, temporarily unload it by running the following command:

```
fltmc unload <DriverName>
```

Note:

In this command, \ represents the name of the driver as listed by the fltmc command.

1. After the tool finishes, restart the computer, and try again to install the update. If the update still doesn't install, take one of the following actions:

- If the list includes more than one non-Microsoft filter driver, repeat the fltmc unload command to unload each of these drivers, and then try again to install the update.

- If the affected computer is a VM, go to step 7.

- Contact Microsoft Support for assistance.

Step 7: Use the Run Command reset tool (Azure)

If the previous steps don't resolve the issue on an Azure VM, try the Azure VM Windows Update Reset Tool. You can run the tool directly from the VM's Azure portal page by using Operations > Run command. When you use this method, you don't have to sign in to the VM.

This tool resets the Windows Update servicing stack. This action clears memory-related lock states in the update agent.

After you run the tool, try again to install the update. If the update still doesn't install, go to step 8.

Step 8: Use a repair VM (Azure)

If the reset tool doesn't fix the issue, or the VM can't start:

1. Create a repair VM by using Azure VM repair commands.

1. Attach the affected operating system disk to the repair VM.

1. To reset the default permissions on the Windows component store, open an administrative Command Prompt window, and then run the following commands:

```
icacls "%windir%\WinSxS" /reset /t /c /q
icacls "%windir%\SoftwareDistribution" /reset /t /c /q
```

1. To designate that the TrustedInstaller account owns the WinSxS folder, run the following command at the command prompt:

```
icacls "%windir%\WinSxS" /setowner "NT SERVICE\TrustedInstaller" /t /c /q
```

1. Make sure that you have an offline operating system image available, and then run the following command at the command prompt:

```
DISM /Image:<Drive>:\ /Cleanup-Image /RestoreHealth
```

Note:

- In this command, \ represents the drive letter of the affected operating system disk.

- By default, DISM uses Windows Update as a repair source. For information about how to specify a different repair source, see Repair a Windows Image.

1. To make sure that third-party applications or drivers don't interfere in the update process, follow these steps:

1. On the affected computer, temporarily disable real-time antivirus protection.

1. To list the file system filter drivers, run the following command at the command prompt:

```
fltmc
```

1. If the list includes non-Microsoft filter drivers, temporarily unload them by running the following command for each non-Microsoft driver in the list:

```
fltmc unload <DriverName>
```

Note:

In this command, \ represents the name of the driver as listed by the fltmc command.

1. Reattach the repaired disk to the original VM.

1. Try again to install the update. If the update still doesn't install, contact Microsoft Support for assistance.

Artículo 9: Common Windows Update errors

9.0 Overview

Try our Virtual Agent - It can help you quickly identify and fix common Windows Update issues.

The following tables provide information about common Windows Update-related errors that you might encounter, and include steps to help you mitigate the errors.

Applies to: Windows 10, Windows 11

9.1 0x8024402F

Message | Description | Mitigation

WU_E_PT_ECP_SUCCEEDED_WITH_ERRORS | External .cab file processing completed with some errors | This error might be caused by the Lightspeed Rocket for web filtering software. Add the IP addresses of the devices that you want to receive updates to the exceptions list of Lightspeed Rocket.

9.2 0x80242006

Message | Description | Mitigation

WU_E_UH_INVALIDMETADATA | A handler operation couldn't be completed because the update contains invalid metadata. | Rename the software redistribution folder, and try to download the updates again: Rename the following folders to \.BAK: -%systemroot%\\system32\\catroot2* Type the following commands at a command prompt. Press ENTER after you type each command.Ren %systemroot%\SoftwareDistribution\DataStore DataStore.bakRen %systemroot%\SoftwareDistribution\Download Download.bakRen %systemroot%\system32\catroot2 catroot2.bak

9.3 0x80070BC9

Message | Description | Mitigation

ERROR_FAIL_REBOOT_REQUIRED | The requested operation failed. Restart the system to roll back changes made. | Make sure that you don't have any policies that control the start behavior of the Windows Installer service. This service should be managed by the operating system. The default Startup type of the Windows Installer service is Manual.

9.4 0x80200053

Message | Description | Mitigation

BG_E_VALIDATION_FAILED | NA | Make sure that there are no firewalls that might filter downloads. Such filtering could cause incorrect responses to be received by the Windows Update client.

9.5 0x80072EFD or 0x80072EFE or 0x80D02002

Message | Description | Mitigation

TIME_OUT_ERRORS | The operation timed out | Make sure that no firewall rules or proxies block Microsoft download URLs. Take a network monitor trace to understand the situation better. \

9.6 0X8007000D

Message | Description | Mitigation

ERROR_INVALID_DATA | Indicates data that isn't valid was downloaded or corruption occurred. | Try to redownload the update, and then start the installation.

9.7 0x8024A10A

Message | Description | Mitigation

USO_E_SERVICE_SHUTTING_DOWN | Indicates that the Windows Update Service is shutting down. | This error can occur after a long time of inactivity. The system doesn't respond, causing the service to be idle and, eventually, shut down. Make sure that the system remains active, and the connections remain established to complete the installation.

9.8 0x80240020

Message | Description | Mitigation

WU_E_NO_INTERACTIVE_USER | The operation didn't finish because no interactive user is signed in. | Sign in to the device to start the installation, and allow the device to restart.

9.9 0x80242014

Message | Description | Mitigation

WU_E_UH_POSTREBOOTSTILLPENDING | The post-restart operation for the update is still in progress. | Some Windows updates require the device to be restarted. Restart the device to complete update the installation.

9.10 0x80246017

Message | Description | Mitigation

WU_E_DM_UNAUTHORIZED_LOCAL_USER | The download failed because the local user was denied authorization to download the content. | Ensure that the user attempting to download and install updates has been provided with sufficient privileges to install updates (Local Administrator).

9.11 0x8024000B

Message | Description | Mitigation

WU_E_CALL_CANCELLED | Operation was canceled. | The operation was canceled by the user or service. You might also receive this error message if we can't filter the results.

9.12 0x8024000E

Message | Description | Mitigation

WU_E_XML_INVALID | Windows Update Agent found information in the update's XML data that isn't valid. | Certain drivers contain more metadata information in Update.xml. Orchestrator might interpret that condition as data that isn't valid. Make sure that you have the latest Windows Update Agent installed on the device.

9.13 0x8024D009

Message | Description | Mitigation

WU_E_SETUP_SKIP_UPDATE | An update to the Windows Update Agent was skipped due to a directive in the Wuident.cab file. | You might encounter this error if WSUS isn't sending the self-update to the clients.For more information to resolve the issue, see KB920659.

9.14 0x80244007

Message | Description | Mitigation

WU_E_PT_SOAPCLIENT_SOAPFAULT | SOAP client failed because there was a SOAP fault for reasons of WU_E_PT_SOAP_* error codes. | This issue occurs because Windows can't renew the cookies for Windows Update. For more information to resolve the issue, see 0x80244007 error when Windows tries to scan for updates on a WSUS server.

9.15 0x80070422

Message | Description | Mitigation

ERROR_SERVICE_DISABLED | This issue occurs when the Windows Update service stops working or isn't running. | Check whether the Windows Update service is running.

9.16 0x800f0821

Message | Description | Mitigation

CBS_E_ABORT; client abort, IDABORT returned by ICbsUIHandler method except Error() | CBS transaction timeout exceeded. | A servicing operation is taking a long time to finish. The servicing stack watchdog timer expires. Extending the timeout mitigates the issue. Increase the resources on the device. If it's a virtual machine, increase virtual CPU and memory to speed up operations. Make sure that the device has installed the update in KB4493473 or later.

9.17 0x800f0825

Message | Description | Mitigation

CBS_E_CANNOT_UNINSTALL; Package can't be uninstalled. | Typically this error occurs because of component store corruption that was caused by a component in a partially installed state. | Repair the component store by using the Dism RestoreHealth command, or manually repair by using a payload from the partially installed component. In an elevated Command Prompt window, run these commands:Dism.exe /Online /Cleanup-Image /RestorehealthSfc.exe /Scannow Restart the device.

9.18 0x800F0920

Message | Description | Mitigation

CBS_E_HANG_DETECTED; A failure to respond was detected while processing the operation. | Subsequent error logged after getting 0x800f0821 | A servicing operation is taking a long time to finish. The servicing stack watchdog timer expires and assumes that the system stopped responding. Extending the timeout value mitigates the issue. Increase the resources on the device. If it's a virtual machine, increase virtual CPU and memory to speed up operations. Make sure that the device has update KB4493473 or later installed.

9.19 0x800f081f

Message | Description | Mitigation

CBS_E_SOURCE_MISSING; source for package or file not found, ResolveSource() unsuccessful | Component Store corruption | Repair the component store by running the Dism RestoreHealth command, or manually repair by using the payload from the partially installed component. In an elevated Command Prompt window, run these commands:Dism.exe /Online /Cleanup-Image /RestorehealthSfc.exe /Scannow Restart the device.

9.20 0x800f0831

Message | Description | Mitigation

CBS_E_STORE_CORRUPTION; CBS store is corrupted. | Corruption in the Windows Component Store. | Repair the component store by runnning Dism RestoreHealth or manually repair by using the payload from the partially installed component. In an elevated Command Prompt window, run these commands:Dism.exe /Online /Cleanup-Image /RestorehealthSfc.exe /Scannow Restart the device.

9.21 0x80070005

Message | Description | Mitigation

E_ACCESSDENIED; General access denied error | File system or registry key permissions have been changed and the servicing stack doesn't have the required level of access. | This error generally means that access was denied. Go to %Windir%\\logs\\CBS, open the last CBS.log, search for , error, and match with the timestamp. After you find the error, scroll up, and try to determine what caused the access denial. It could be access denied to a file, registry key. Determine which object needs the right permissions, and

change the permissions as appropriate. For more information, see Troubleshoot Windows Update error 0x80070005.

9.22 0x80070570

Message | Description | Mitigation

ERROR_FILE_CORRUPT; The file or directory is corrupted and unreadable. | Component Store corruption | Repair the component store by running Dism RestoreHealth, or manually repair by using the payload from the partially installed component. In an elevated Command Prompt window, run these commands:Dism.exe /Online /Cleanup-Image /RestorehealthSfc.exe /Scannow Restart the device. For more information, see Troubleshoot Windows Update error 0x80070570.

9.23 0x80070003

Message | Description | Mitigation

ERROR_PATH_NOT_FOUND; The system can't find the path specified. | The servicing stack can't access a specific path. | Indicates an invalid path to an executable. Go to %Windir%\\logs\\CBS, open the last CBS.log, and search for , error. Then, match the results to the timestamp.

9.24 0x80070020

Message | Description | Mitigation

ERROR_SHARING_VIOLATION | Numerous causes. CBS log analysis required. | This error is caused by non-Microsoft filter drivers, such as antivirus. 1. Perform a clean restart, and retry the installation 2. Download the sysinternal tool Process Monitor. 3. Run Procmon.exe. The tool starts data capture automatically. 4. Install the update package again. 5. Keep the Process Monitor main window in focus, and press CTRL+E or select the magnifying glass to stop data capture. 6. Select File > Save > All Events > PML, and choose a path to save the .PML file. 7. Go to %windir%\\logs\\cbs, open the last Cbs.log file, and search for the error entry. After you locate the error line, you should see which file is accessed during the installation and is causing the sharing violation error. 8. In Process Monitor, filter for path, and insert the file name (it should resemble "path" "contains" "filename from CBS"). 9. Try to stop or uninstall the process that's causing the error.

9.25 0x80073701

Message | Description | Mitigation

ERROR_SXS_ASSEMBLY_MISSING; The referenced assembly couldn't be found. | Typically, a component store corruption caused when a component is in a partially installed state. | Repair the component store by running Dism RestoreHealth command, or manually repair it by using the payload from the partially installed component. In an elevated Command Prompt window, run these commands:Dism.exe /Online /Cleanup-Image /RestorehealthSfc.exe /Scannow Restart the device.

9.26 0x8007371b

Message | Description | Mitigation

ERROR_SXS_TRANSACTION_CLOSURE_INCOMPLETE; One or more required members of the transaction aren't present. | Component Store corruption. | Repair the component store by running the Dism RestoreHealth command, or manually repair it by using the payload from the partially installed component. In an elevated Command Prompt window, run these commands:Dism.exe /Online /Cleanup-Image /RestorehealthSfc.exe /Scannow Restart the device.

9.27 0x80072EFE

Message | Description | Mitigation

WININET_E_CONNECTION_ABORTED; The connection with the server was closed abnormally | BITS is unable to transfer the file successfully. | Encountered if BITS is broken or if the file that's being transferred can't be written to the destination folder on the client. This error is caused by connection errors while checking or downloading updates. At a command prompt, run: BITSADMIN /LIST /ALLUSERS /VERBOSE Search for the 0x80072EFE error code. You should see a reference to an HTTP code and a specific file. Using a browser, try to download the file manually. Make sure that you use your organization's proxy settings. If the download fails, work with your proxy manager to achieve successful communication. Also, check with your network team for this specific URL access.

9.28 0x80072F8F

Message | Description | Mitigation

WININET_E_DECODING_FAILED; Content decoding has failed | TLS 1.2 isn't configured correctly on the client. | This error generally means that the Windows Update Agent can't decode the received content. Install and configure TLS 1.2 by installing the update that's provided in KB3140245.

9.29 0x80072EE2

Message | Description | Mitigation

WININET_E_TIMEOUT; The operation timed out | Unable to scan for updates due to a connectivity issue to Windows Update, Configuration Manager, or WSUS. | This error generally means that the Windows Update Agent was unable to connect to the update servers or your own source, such as WSUS, Configuration Manager, or Microsoft Intune. Check with your network team to ensure that the device can reach the update sources. For more info, see Troubleshoot software update scan failures in Configuration Manager. If you're using the public Microsoft update servers, check that your device can access the following Windows Update endpoints: http://windowsupdate.microsoft.com https://.windowsupdate.microsoft.com https://update.microsoft.com https://.update.microsoft.com https://windowsupdate.com https://.windowsupdate.com https://download.windowsupdate.com https://.download.windowsupdate.com https://download.microsoft.com https://.download.windowsupdate.com https://wustat.windows.com https://.wustat.windows.com https://ntservicepack.microsoft.com

9.30 0x80240022

Message | Description | Mitigation

WU_E_ALL_UPDATES_FAILED; Operation failed for all the updates. | Multiple root causes for this error. | The most common issue is that antivirus software is blocking access to certain folders (like SoftwareDistribution). CBS.log analysis has to determine the file or folder that's being protected.

9.31 0x8024401B

Message | Description | Mitigation

WU_E_PT_HTTP_STATUS_PROXY_AUTH_REQ; Same as HTTP status 407 - proxy authentication is required. | Unable to authenticate through a proxy server. | Either the Winhttp proxy or WinInet proxy settings aren't configured correctly. This error generally means that the Windows Update Agent can't connect to the update servers or your own update source, such as WSUS, Configuration Manager, or Microsoft Intune, due to a proxy error. Verify the proxy settings on the client. The Windows Update Agent uses WinHTTP to scan for available updates. When there's a proxy server between the client and the update source, the proxy settings must be configured correctly on the clients to enable them to communicate by using the source's FQDN. Check with your network and proxy teams to verify that the device can access the update source without the proxy requiring user authentication.

9.32 0x80244022

Message | Description | Mitigation

WU_E_PT_HTTP_STATUS_SERVICE_UNAVAILABLE; Same as HTTP status 503 - the service is temporarily overloaded. | Unable to connect to the configured update source. | Network troubleshooting is needed to resolve the connectivity issue. Check with your network and proxy teams to verify that the device can access the update source without the proxy requiring user authentication.

9.33 0x80070490

Message | Description | Mitigation

ERROR_NOT_FOUND | This error occurs during driver installation as part of the update. | This issue occurs because details such as the architecture for a driver that's being updated are missing in the registry. Manually add the missing inf file Arch value in the Driver operations registry by following these steps:1. Open regedit, and navigate to HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ComponentBasedServicing\DriverOperations\0\2(SequenceID)2. Review the Identity value to determine the value that's missing.3. Manually add the missing value by referring to the information in the Identity value. For example, Name: Arch; Type: REG_SZ (String Value); Data: amd64.4. Proceed with installing the failing update.

9.34 0x800f0922

Message | Description | Mitigation

CBS_E_INSTALLERS_FAILED | The July cumulative update failed to be installed on Windows Server 2016 | In the CBS.log, you might find that updates sometimes roll back when License and Product key tokens fail to be updated. This issue can be resolved by adding write permissions for the "User" and "Network Service" accounts to the C:\\Windows\\System32\\spp\\ folder.

9.35 0x80070bc9

Message | Description | Mitigation

ERROR_FAIL_REBOOT_REQUIRED | The TrustedInstaller service startup type is set to Manual by a Group Policy Object (GPO). Group Policy prevented the startup to complete pending operations. | The TrustedInstaller service changes the startup type from Manual to Automatic if it encounters an update that has to process a transaction after a restart. If the value is reverted to Manual before the restart, the transaction can't be applied. This transaction will be pending and block all other update installations.To fix this issue, change the TrustedInstaller policy to Automatic, and restart the computer. If this change doesn't fix the issue, start the computer to WinRE to revert the pending actions. For example, dism /Image:C:\ /Cleanup-Image /RevertPendingActions. If this action also has no effect, start the computer to WinRE, rename \WinSxS\Pending.xml, and then remove the PendingXMLIdentifier from COMPONENTS Hive.

9.36 0x800706be

Message | Description | Mitigation

Failed to install cumulative updates | Windows Server 2016 Std failed to install cumulative packages by using the .msu package. No error is returned. When installing the packages with dism.exe, it returned the error 0x800706be. | The last cumulative update didn't install, and it was corrupted. To resolve this issue, navigate to the registry key for the corrupted update package. Change the "current state" value to 000020 hex (32 dec) - resolved, or 000040 hex (64 dec) - staged, or 000070 hex (112 dec) - installed.

9.37 Data collection

If you need assistance from Microsoft support, we recommend that you collect the information by following the steps that are provided in Gather information by using TSS for deployment-related issues.

Artículo 10: How to speed up a Windows 8.1 computer

10.0 Overview

No matter how good you are about keeping your computer clean and up-to-date, they tend to slow down after time. Fortunately, there are a lot of ways to help speed them up? without upgrading your hardware.

Applies to: Windows 8.1

Original KB number: 3064207

Note:

If you are an advanced user, you can download a free tool from the Microsoft website that shows you all of the programs and processes that run when you start Windows, including the ones that Windows requires to operate successfully. Use this tool only if you are comfortable restoring Windows after an error occurs.

10.1 Uninstall extra antivirus programs

If you use more than one antivirus or antispyware program at the same time, your device may experience decreased performance, become unstable, or restart unexpectedly. To remedy the issue, you should select one Internet security program to run on your device. You should then uninstall the other programs.

Caution:

Make sure you have an Internet security program running on your device before you uninstall other security programs.

Some Internet security applications do not uninstall completely. You may need to download and run a cleanup utility for your previous security application to completely remove it.

If you use another antispyware program together with Microsoft Security Essentials, we recommend that you turn off real-time scanning in the other program. For more information, see the documentation supplied by that antispyware program.

To remove an antivirus or antispyware program, follow these instructions:

1. Swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down).
2. Tap or select Search.
3. Type appwiz.cpl in the Search box.
4. Tap or select Appwiz.cpl below the Search box.
5. In the list of installed programs, uninstall the Internet security programs you don't need.
6. Restart your device.

10.2 Close programs in the notification area running with startup

If your device takes a long time to start up, one of the causes could be having a large number of startup apps or a few apps that have a high impact on startup time.

Some of these programs add an icon to the notification area on the taskbar to show that they are running with startup.

To stop a program that has one of these icons from automatically running on startup, follow these instructions:

1. Point to each icon in the icon tray to see the program name.
2. To ensure that you can see icons for all running programs, swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down), and tap or select Search.
3. Type show hidden icons in the Search box.
4. Tap or select Show or hide inactive icons on the taskbar.
5. Check Always show all icons and notifications on the taskbar.

Note:

You must open any program that you do not want to run on startup and change the setting.

10.3 View Startup items

To see what programs run at startup and disable any, follow these instructions:

1. Press and hold or right-click in the blank area on Taskbar and select Task Manager.
2. Tap or select More details in the lower-left corner of Task Manager.
3. Under the Startup tab in Task Manager, you can view a list of applications that start automatically every time you turn on your device and sign in to Windows.
4. If you see any programs in this list that you do not want to run when Windows starts, tap or select the application and then tap or select Disable.

Note:

Disabling a program from running at startup doesn't stop the program from running if you need it. If you tap or select the program after startup, it will start and run normally.

10.4 Change a program

Sometimes, by adding or removing certain program options, you can prevent a program from running at startup.

If you can't stop the program from running on startup and the program does not have the option to change the configuration, you must talk to the program manufacturer for a solution.

To change the configuration of a program, follow these instructions:

1. Swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down).

2. Tap or select Search.
3. Type appwiz.cpl in the Search box.
4. Tap or select Appwiz.cpl below the Search box.
5. Tap or select a program, and then tap or select Uninstall, Change, or Repair.

If prompted, type an administrator password or confirmation.

10.5 Clean up disk errors

Over time, your device may create errors on its hard drive. These errors can slow your device. The Check Disk program identifies and cleans any errors.

To run Check Disk, follow these instructions:

1. Swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down).
2. Tap or select Search.
3. Type computer in the Search box.
4. Tap or select This PC below the Search box.
5. Press and hold or right-click the drive you want to repair, and then tap or select Properties.
6. Tap or select the Tools tab.
7. Under Error checking, tap or select Check. Depending upon the size of your hard disk, this may take several minutes. For best results, don't use your device for any other tasks while it's checking for errors. If prompted, type an administrator password or confirmation.
8. You may need to restart your device after error checking is complete.

10.6 Defragment your hard disk

One of the best ways to help improve your device's performance is by optimizing the hard drive. Optimize Drives, previously known as Disk Defragmenter, is a Windows feature that helps optimize different types of drives. The feature runs automatically on a weekly schedule, but you can also run Optimize Drives manually.

To run Optimize Drives manually, follow these instructions:

1. Swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down).
2. Tap or select Search.
3. Type computer in the Search box.
4. Tap or select This PC below the Search box.
5. Press and hold or right-click the drive you want to repair, and then tap or select Properties.
6. Tap or select the Tools tab.
7. Tap or select Optimize under Optimize and defragment drive.
8. Under Status, tap or select the drive you want to optimize. (The Media type column tells you what type of drive you're optimizing.)
9. To determine if the drive needs to be optimized, tap or select Analyze.

Note:

If prompted, type an administrator password or confirmation.

10. After Windows finishes analyzing the drive, check the Current status column to see whether you need to optimize the drive. If the drive is more than 10 percent fragmented, you should optimize it.

11. Tap or select Optimize.

Note:

- Optimizing a drive can take anywhere from several minutes to several hours to finish, depending on the size of the drive and degree of optimization required. You can still use your device during the optimization process.

- If the drive is being used by another program or is formatted using a file system other than NTFS, FAT, or FAT32, it can't be optimized.

- Network drives can't be optimized.

- If a drive doesn't appear in Optimize Drives, it might be because it contains an error. Try to repair the drive first, then return to Optimize Drives to try again.

To change the optimization schedule, follow these instructions:

1. Swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down).

2. Tap or select Search.

3. Type computer in the Search box.

4. Tap or select This PC below the Search box.

5. Press and hold or right-click the drive you want to repair, and then tap or select Properties.

6. Tap or select the Tools tab.

7. Tap or select Optimize under Optimize and defragment drive.

8. Tap or select Change settings. If prompted, type an administrator password or confirmation.

9. Select one of the following:

- To turn off scheduled optimization, clear the Run on a schedule check box.

- To change the frequency of scheduled optimization, tap or select the drop-down list next to Frequency, and then tap or select Daily, Weekly, or Monthly. The default schedule for optimization is weekly and runs during Automatic Maintenance.

- To select the drives you want to include or exclude in scheduled optimization, tap or select Choose next to Drives. Select or clear the check boxes next to the drives and then tap or select OK. You can also clear the Automatically optimize new drives check box if you don't want new drives added to scheduled optimization. If Windows can't optimize a drive, it won't offer the drive as an option for Automatic Maintenance.

10. Tap or select OK.

10.7 Clean your hard disk

Disk Cleanup reduces the number of unnecessary files on your drives by deleting temporary files and system files, emptying the Recycle Bin, and removing a variety of other items that you may no longer need.

To clean your hard disk, follow these instructions:

1. Swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down).
2. Tap or select Search.
3. Type free up disk space in the Search box.
4. Tap or select Free up disk space by deleting unnecessary files below the Search box.
5. In the Drives list, tap or select the drive that you want to clean up.
6. Tap or select OK.
7. In the message that appears, tap or select Delete files.

To clean up system files associated with your account, follow these instructions:

1. In the Drives list, tap or select the drive that you want to clean up and then tap or select OK.
2. In the Disk Cleanup dialog box, tap or select Clean up system files.

Note:

If prompted, type an administrator password or confirmation.

3. The More Options tab is available when you opt to clean up system files from your device. This tab includes two additional options for freeing up space:

- Programs and Features. This option opens Programs and Features in Control Panel, where you can uninstall programs that you no longer use. The Size column in Programs and Features shows how much space each program uses.

- System Restore and Shadow Copies. System Restore uses restore points to return your system files to an earlier point in time. If your device is running normally, you can save space by deleting earlier restore points.

10.8 Turn off visual effects

If Windows is running slowly, you can speed it up by disabling certain visual effects. You can select which visual effects to turn off one by one or you can let Windows select for you.

To turn off visual effects, follow these instructions:

1. Swipe in from the right edge of the screen (if using a mouse, point to the upper-right corner of the screen and move the mouse pointer down).
2. Tap or select Search.
3. Type Performance Information and Tools in the Search box.
4. Tap or select Adjust the appearance and performance of Windows below the Search box.
5. Under Visual Effects tab, check on Adjust for best performance, and then tap or select OK. (For a less drastic option, select Let Windows choose what's best for my computer.

10.9 Run fewer programs at the same time

Sometimes you can improve system performance by changing your computing behavior. Running four or more programs while leaving multiple browser windows and email messages open may be more than your device can handle.

If you find your device slowing down, decide whether you really need to keep all of your programs and windows open at the same time. Also, find a way to remind yourself to reply to email messages later instead of keeping them open until you reply.

10.10 Use ReadyBoost

ReadyBoost can speed up your device by using storage space on flash memory cards and USB flash drives. If you have a storage device that will work with ReadyBoost, you'll see an option to use ReadyBoost when you plug it into your device. If you select this option, you can select how much memory to use.

10.11 Adjust indexing options

Windows uses an index to perform very fast searches of the most common files on your device. If it's taking too long to search for things on your device, you can narrow your search to focus on the files and folders that you most commonly use.

10.12 Adjust power plan

A power plan is a collection of hardware and system settings (such as display, sleep, and so on) that manages how your device uses power. The power plans you can use depend on the kind of device you have.

Artículo 11: Stop code error or bug check troubleshooting

11.0 Overview

Try our Virtual Agent - It can help you quickly identify and fix common Windows boot issues

Note:

If you're not a support agent or IT professional, you'll find more helpful information about stop code error messages in Troubleshoot stop code errors.

Applies to: Supported versions of Windows Server and Windows Client

11.1 What causes stop errors?

When Windows encounters a condition that compromises safe system operation, the system stops. Examples include something failing that could compromise security or lead to corruption of the operating system (OS) and/or user data. When the machine stops in order to prevent the operating system from moving forward in these conditions, it is called a bug check (or bugcheck). It is also commonly referred to as a system crash, a kernel error, or a stop code error. On preview releases of Windows, the screen color can be green, leading to the green screen of death (GSOD).

There's no simple explanation for the cause of stop errors. Many different factors can be involved. Our analysis of the root causes of crashes indicates that:

- 70% are caused by third-party driver code.
- 10% are caused by hardware issues.
- 5% are caused by Microsoft code.
- 15% have unknown causes, because the memory is too corrupted to analyze.

Note:

The root cause of stop errors is rarely a user-mode process. While a user-mode process (such as Notepad or Slack) may trigger a stop error, it's usually exposing the underlying issue in a driver, hardware, or operating system.

11.2 General troubleshooting steps

To troubleshoot stop error messages, follow these general steps:

1. Review the stop error code that you find in the event logs. Search online for the specific stop error codes to see whether there are any known issues, resolutions, or workarounds for the problem.
2. Make sure that you install the latest Windows updates, cumulative updates, and rollup updates. To verify the update status, refer to the appropriate update history for your system. For example:
   - Windows 10, version 21H2
   - Windows 10, version 21H1
   - Windows 10, version 20H2
3. Make sure that the BIOS and firmware are up-to-date.
4. Run any relevant hardware and memory tests.

5. Run Microsoft Safety Scanner or any other virus detection program that includes checks of the MBR for infections.

6. Make sure that there's sufficient free space on the hard disk. The exact requirement varies, but we recommend 10-15 percent free disk space.

7. Contact the respective hardware or software vendor to update the drivers and applications in the following scenarios:

- The error message indicates that a specific driver is causing the problem.

- You're seeing an indication of a service that is starting or stopping before the crash occurred. In this situation, determine whether the service behavior is consistent across all instances of the crash.

- You have made any software or hardware changes.

Note:

If there are no updates available from a specific manufacturer, we recommend that you disable the related service.

For more information, see How to perform a clean boot in Windows.

You can disable a driver by following the steps in How to temporarily deactivate the kernel mode filter driver in Windows.

You may also want to consider the option of rolling back changes or reverting to the last-known working state. For more information, see Roll back a device driver to a previous version).

Memory dump collection

To configure the system for memory dump files, follow these steps:

1. Select the Taskbar search box, type Advanced system settings, and then press Enter.

2. On the Advanced tab on the System Properties box, select the Settings button that appears in the section Startup and Recovery.

3. In the new window, select the drop-down below the option Write debugging information.

4. Choose Automatic memory dump.

5. Select OK.

6. Restart the computer for the setting to take effect.

7. If the server is virtualized, disable auto reboot after the memory dump file is created. This disablement lets you take a snapshot of the server in-state and also if the problem recurs.

The memory dump file is saved at the following locations:

Dump file type | Location

(none) | %SystemRoot%\\MEMORY.DMP (inactive, or grayed out)

Small memory dump file (256 kb) | %SystemRoot%\\Minidump

Kernel memory dump file | %SystemRoot%\\MEMORY.DMP

Complete memory dump file | %SystemRoot%\\MEMORY.DMP

Automatic memory dump file | %SystemRoot%\\MEMORY.DMP

Active memory dump file | %SystemRoot%\\MEMORY.DMP

You can use the Microsoft Crash Dump File Checker (DumpChk) tool to verify that the memory dump files aren't corrupted or invalid. For more information, see the following video:

[!VIDEO https://www.youtube.com/embed/xN7tOfgNKag]

For more information on how to use Dumpchk.exe to check your dump files, see the following articles:

- Using DumpChk
- Download DumpChk

Pagefile settings

For more information on pagefile settings, see the following articles:

- Introduction to page files
- How to determine the appropriate page file size for 64-bit versions of Windows
- Generate a kernel or complete crash dump

Memory dump analysis

Finding the root cause of the crash may not be easy. Hardware problems are especially difficult to diagnose because they may cause erratic and unpredictable behavior that can manifest itself in various symptoms.

When a stop error occurs, you should first isolate the problematic components, and then try to cause them to trigger the stop error again. If you can replicate the problem, you can usually determine the cause.

You can use the tools such as Windows Software Development Kit (SDK) and symbols to diagnose dump logs. The next section discusses how to use this tool.

11.3 Advanced troubleshooting steps

Note:

Advanced troubleshooting of crash dumps can be very challenging if you aren't experienced with programming and internal Windows mechanisms. We have attempted to provide a brief insight here into some of the techniques used, including some examples. However, to really be effective at troubleshooting a crash dump, you should spend time becoming familiar with advanced debugging techniques. For a video overview, Debugging kernel mode crashes and hangs. Also see the advanced references listed below.

Advanced debugging references

- Advanced Windows Debugging, first edition book
- Debugging Tools for Windows (WinDbg, KD, CDB, NTSD)

Debugging steps

1. Verify that the computer is set up to generate a complete memory dump file when a crash occurs. For more information, see Method 1: Memory dump.
2. Locate the memory.dmp file in your Windows directory on the computer that is crashing, and copy that file to another computer.
3. On the other computer, download the Windows 10 SDK.
4. Start the install and choose Debugging Tools for Windows. The WinDbg tool is installed.
5. Go to the File menu and select Symbol File Path to open the WinDbg tool and set the symbol path.
1. If the computer is connected to the internet, enter the Microsoft public symbol server:

https://msdl.microsoft.com/download/symbols and select OK. This method is recommended.

2. If the computer isn't connected to the internet, specify a local symbol path.

6. Select Open Crash Dump, and then open the memory.dmp file that you copied.

7. Under Bugcheck Analysis, select !analyze -v. The command !analyze -v is entered in the prompt at the bottom of the page.

8. A detailed bug check analysis appears.

9. Scroll down to the STACK_TEXT section. There will be rows of numbers with each row followed by a colon and some text. That text should tell you what DLL is causing the crash. If applicable, it also says what service is crashing the DLL.

10. For more information about how to interpret the STACK_TEXT output, see Using the !analyze Extension.

There are many possible causes of a bug check and each case is unique. In the example provided above, the important lines that can be identified from the STACK_TEXT are 20, 21, and 22:

Note:

HEX data is removed here and lines are numbered for clarity.

```
1  : nt!KeBugCheckEx
2  : nt!PspCatchCriticalBreak+0xff
3  : nt!PspTerminateAllThreads+0x1134cf
4  : nt!PspTerminateProcess+0xe0
5  : nt!NtTerminateProcess+0xa9
6  : nt!KiSystemServiceCopyEnd+0x13
7  : nt!KiServiceLinkage
8  : nt!KiDispatchException+0x1107fe
9  : nt!KiFastFailDispatch+0xe4
10 : nt!KiRaiseSecurityCheckFailure+0x3d3
11 : ntdll!RtlpHpFreeWithExceptionProtection$filt$0+0x44
12 : ntdll!_C_specific_handler+0x96
13 : ntdll!RtlpExecuteHandlerForException+0xd
14 : ntdll!RtlDispatchException+0x358
15 : ntdll!KiUserExceptionDispatch+0x2e
16 : ntdll!RtlpHpVsContextFree+0x11e
17 : ntdll!RtlpHpFreeHeap+0x48c
18 : ntdll!RtlpHpFreeWithExceptionProtection+0xda
19 : ntdll!RtlFreeHeap+0x24a
20 : FWPolicyIOMgr!FwBinariesFree+0xa7c2
21 : mpssvc!FwMoneisDiagEdpPolicyUpdate+0x1584f
22 : mpssvc!FwEdpMonUpdate+0x6c
23 : ntdll!RtlpWnfWalkUserSubscriptionList+0x29b
```

```
24 : ntdll!RtlpWnfProcessCurrentDescriptor+0x105
25 : ntdll!RtlpWnfNotificationThread+0x80
26 : ntdll!TppExecuteWaitCallback+0xe1
27 : ntdll!TppWorkerThread+0x8d0
28 : KERNEL32!BaseThreadInitThunk+0x14
29 : ntdll!RtlUserThreadStart+0x21
```

This issue is because of the mpssvc service, which is a component of the Windows Firewall. The problem was repaired by disabling the firewall temporarily and then resetting firewall policies.

For more examples, see Debugging examples.

11.4 Video resources

The following videos illustrate various troubleshooting techniques for analyzing dump files.

- Analyze dump file
- Installing debugging tool for Windows (x64 and x86)
- Debugging kernel mode crash memory dumps
- Special pool

11.5 Advanced troubleshooting using Driver Verifier

We estimate that about 75 percent of all stop errors are caused by faulty drivers. The Driver Verifier tool provides several methods to help you troubleshoot. These include running drivers in an isolated memory pool (without sharing memory with other components), generating extreme memory pressure, and validating parameters. If the tool encounters errors in the execution of driver code, it proactively creates an exception. It can then further examine that part of the code.

Warning:

Driver Verifier consumes lots of CPU and can slow down the computer significantly. You may also experience additional crashes. Verifier disables faulty drivers after a stop error occurs, and continues to do this until you can successfully restart the system and access the desktop. You can also expect to see several dump files created.

Don't try to verify all the drivers at one time. This action can degrade performance and make the system unusable. It also limits the effectiveness of the tool.

Use the following guidelines when you use Driver Verifier:

- Test any "suspicious" drivers. For example, drivers that were recently updated or that are known to be problematic.
- If you continue to experience non-analyzable crashes, try enabling verification on all third-party and unsigned drivers.
- Enable concurrent verification on groups of 10-20 drivers.
- Additionally, if the computer can't boot into the desktop because of Driver Verifier, you can disable the tool by starting in Safe mode. This solution is because the tool can't run in Safe mode.

For more information, see Driver Verifier.

11.6 Common Windows stop errors

This section doesn't contain a list of all error codes, but since many error codes have the same potential resolutions, your best bet is to follow the steps below to troubleshoot your error. For a complete list of stop error codes, see Bug Check Code Reference.

The following sections list general troubleshooting procedures for common stop error codes.

VIDEO_ENGINE_TIMEOUT_DETECTED or VIDEO_TDR_TIMEOUT_DETECTED

Stop error code 0x00000141, or 0x00000117

Contact the vendor of the listed display driver to get an appropriate update for that driver.

DRIVER_IRQL_NOT_LESS_OR_EQUAL

Stop error code 0x0000000D1

Apply the latest updates for the driver by applying the latest cumulative updates for the system through the Microsoft Update Catalog website. Update an outdated network driver. Virtualized VMware systems often run "Intel(R) PRO/1000 MT Network Connection" (e1g6032e.sys). You can download this driver from the Intel Download Drivers & Software website. Contact the hardware vendor to update the network driver for a resolution. For VMware systems, use the VMware integrated network driver instead of Intel's e1g6032e.sys. For example, use VMware types VMXNET, VMXNET2, or VMXNET3.

PAGE_FAULT_IN_NONPAGED_AREA

Stop error code 0x000000050

If a driver is identified in the stop error message, contact the manufacturer for an update. If no updates are available, disable the driver, and monitor the system for stability. Run chkdsk /f /r to detect and repair disk errors. Restart the system before the disk scan begins on a system partition. Contact the manufacturer for any diagnostic tools that they may provide for the hard disk subsystem. Try to reinstall any application or service that was recently installed or updated. It's possible that the crash was triggered while the system was starting applications and reading the registry for preference settings. Reinstalling the application can fix corrupted registry keys. If the problem persists, and you have run a recent system state backup, try to restore the registry hives from the backup.

SYSTEM_SERVICE_EXCEPTION

Stop error code c000021a {Fatal System Error} The Windows SubSystem system process terminated unexpectedly with a status of 0xc0000005. The system has been shut down.

Use the System File Checker tool to repair missing or corrupted system files. The System File Checker lets users scan for corruptions in Windows system files and restore corrupted files. For more information, see Use the System File Checker tool.

NTFS_FILE_SYSTEM

Stop error code 0x000000024

This stop error is commonly caused by corruption in the NTFS file system or bad blocks (sectors) on the hard disk. Corrupted drivers for hard disks (SATA or IDE) can also adversely affect the system's ability to

read and write to disk. Run any hardware diagnostics that are provided by the manufacturer of the storage subsystem. Use the scan disk tool to verify that there are no file system errors. To do this step, right-click the drive that you want to scan, select Properties, select Tools, and then select the Check now button. Update the NTFS file system driver (Ntfs.sys). Apply the latest cumulative updates for the current operating system that's experiencing the problem.

KMODE_EXCEPTION_NOT_HANDLED

Stop error code 0x0000001E

If a driver is identified in the stop error message, disable or remove that driver. Disable or remove any drivers or services that were recently added.

If the error occurs during the startup sequence, and the system partition is formatted by using the NTFS file system, you might be able to use safe mode to disable the driver in Device Manager. To disable the driver, follow these steps:

1. Go to Settings > Update & security > Recovery.
2. Under Advanced startup, select Restart now.
3. After your PC restarts to the Choose an option screen, select Troubleshoot > Advanced options > Startup Settings > Restart.
4. After the computer restarts, you'll see a list of options. Press 4 or F4 to start the computer in safe mode. If you intend to use the internet while in safe mode, press 5 or F5 for the Safe Mode with Networking option.

DPC_WATCHDOG_VIOLATION

Stop error code 0x00000133

This stop error code is caused by a faulty driver that doesn't complete its work within the allotted time frame in certain conditions. To help mitigate this error, collect the memory dump file from the system, and then use the Windows Debugger to find the faulty driver. If a driver is identified in the stop error message, disable the driver to isolate the problem. Check with the manufacturer for driver updates. Check the system log in Event Viewer for other error messages that might help identify the device or driver that's causing stop error 0x133. Verify that any new hardware that's installed is compatible with the installed version of Windows. For example, you can get information about required hardware at Windows 10 Specifications. If Windows Debugger is installed, and you have access to public symbols, you can load the c:\\windows\\memory.dmp file into the debugger. Then refer to Determining the source of Bug Check 0x133 (DPC_WATCHDOG_VIOLATION) errors on Windows Server 2012 to find the problematic driver from the memory dump.

USER_MODE_HEALTH_MONITOR

Stop error code 0x0000009E

This stop error indicates that a user-mode health check failed in a way that prevents graceful shutdown. Windows restores critical services by restarting or enabling application failover to other servers. The Clustering Service incorporates a detection mechanism that may detect unresponsiveness in user-mode components.

This stop error usually occurs in a clustered environment, and the indicated faulty driver is RHS.exe. Check

the event logs for any storage failures to identify the failing process. Try to update the component or process that's indicated in the event logs. You should see the following event recorded:

- Event ID: 4870
- Source: Microsoft-Windows-FailoverClustering
- Description: User mode health monitoring has detected that the system isn't being responsive. The Failover cluster virtual adapter has lost contact with the Cluster Server process with a process ID '%1', for '%2' seconds. Recovery action is taken. Review the Cluster logs to identify the process and investigate which items might cause the process to hang.

For more information, see "0x0000009E" Stop error on cluster nodes in a Windows Server-based multi-node failover cluster environment Also, see the following Microsoft video What to do if a 9E occurs.

11.7 Debugging examples

Example 1

This bug check is caused by a driver hang during upgrade, resulting in a bug check D1 in NDIS.sys, which is a Microsoft driver. The IMAGE_NAME tells you the faulting driver, but since this driver is s Microsoft driver, it can't be replaced or removed. The resolution method is to disable the network device in device manager and try the upgrade again.

```
2: kd> !analyze -v
*******************************************************************************
*                                                                             *
*                        Bugcheck Analysis                                    *
*                                                                             *
*******************************************************************************
DRIVER_IRQL_NOT_LESS_OR_EQUAL (d1)
An attempt was made to access a pageable (or completely invalid) address at an
interrupt request level (IRQL) that is too high.  This is usually
caused by drivers using improper addresses.
If kernel debugger is available get stack backtrace.
Arguments:
Arg1: 000000000011092a, memory referenced
Arg2: 0000000000000002, IRQL
Arg3: 0000000000000001, value 0 = read operation, 1 = write operation
Arg4: fffff807aa74f4c4, address which referenced memory
Debugging Details:
------------------
KEY_VALUES_STRING: 1
STACKHASH_ANALYSIS: 1
TIMELINE_ANALYSIS: 1
```

```
DUMP_CLASS: 1
DUMP_QUALIFIER: 400
SIMULTANEOUS_TELSVC_INSTANCES:  0
SIMULTANEOUS_TELWP_INSTANCES:  0
BUILD_VERSION_STRING:  16299.15.amd64fre.rs3_release.170928-1534
SYSTEM_MANUFACTURER:  Alienware
SYSTEM_PRODUCT_NAME:  Alienware 15 R2
SYSTEM_SKU:  Alienware 15 R2
SYSTEM_VERSION:  1.2.8
BIOS_VENDOR:  Alienware
BIOS_VERSION:  1.2.8
BIOS_DATE:  01/29/2016
BASEBOARD_MANUFACTURER:  Alienware
BASEBOARD_PRODUCT:  Alienware 15 R2
BASEBOARD_VERSION:  A00
DUMP_TYPE:  2
BUGCHECK_P1: 11092a
BUGCHECK_P2: 2
BUGCHECK_P3: 1
BUGCHECK_P4: fffff807aa74f4c4
WRITE_ADDRESS: fffff80060602380: Unable to get MiVisibleState
Unable to get NonPagedPoolStart
Unable to get NonPagedPoolEnd
Unable to get PagedPoolStart
Unable to get PagedPoolEnd
000000000011092a
CURRENT_IRQL:  2
FAULTING_IP:
NDIS!NdisQueueIoWorkItem+4 [minio\ndis\sys\miniport.c @ 9708]
fffff807`aa74f4c4 48895120        mov     qword ptr [rcx+20h],rdx
CPU_COUNT: 8
CPU_MHZ: a20
CPU_VENDOR:  GenuineIntel
CPU_FAMILY: 6
CPU_MODEL: 5e
CPU_STEPPING: 3
CPU_MICROCODE: 6,5e,3,0 (F,M,S,R)  SIG: BA'00000000 (cache) BA'00000000 (init)
BLACKBOXPNP: 1 (!blackboxpnp)
```

```
DEFAULT_BUCKET_ID:  WIN8_DRIVER_FAULT
BUGCHECK_STR:  AV
PROCESS_NAME:  System
ANALYSIS_SESSION_HOST:  SHENDRIX-DEV0
ANALYSIS_SESSION_TIME:  01-17-2019 11:06:05.0653
ANALYSIS_VERSION: 10.0.18248.1001 amd64fre
TRAP_FRAME:  ffffa884c0c3f6b0 -- (.trap 0xffffa884c0c3f6b0)
NOTE: The trap frame doesn't contain all registers.
Some register values may be zeroed or incorrect.
rax=fffff807ad018bf0 rbx=0000000000000000 rcx=000000000011090a
rdx=fffff807ad018c10 rsi=0000000000000000 rdi=0000000000000000
rip=fffff807aa74f4c4 rsp=ffffa884c0c3f840 rbp=000000002408fd00
r8=ffffb30e0e99ea30  r9=0000000001d371c1 r10=0000000020000080
r11=0000000000000000 r12=0000000000000000 r13=0000000000000000
r14=0000000000000000 r15=0000000000000000
iopl=0         nv up ei ng nz na pe nc
NDIS!NdisQueueIoWorkItem+0x4:
fffff807`aa74f4c4  48895120                mov           qword  ptr  [rcx+20h],rdx
ds:00000000`0011092a=????????????????
Resetting default scope
LAST_CONTROL_TRANSFER:  from fffff800603799e9 to fffff8006036e0e0
STACK_TEXT:
ffffa884`c0c3f568    fffff800`603799e9    :    00000000`0000000a    00000000`0011092a
00000000`00000002           00000000`00000001           :           nt!KeBugCheckEx
[minkernel\ntos\ke\amd64\procstat.asm @ 134]
ffffa884`c0c3f570    fffff800`60377d7d    :    fffff78a`4000a150    ffffb30e`03fba001
ffff8180`f0b5d180        00000000`000000ff        :        nt!KiBugCheckDispatch+0x69
[minkernel\ntos\ke\amd64\trap.asm @ 2998]
ffffa884`c0c3f6b0    fffff807`aa74f4c4    :    00000000`00000002    ffff8180`f0754180
00000000`00269fb1          ffff8180`f0754180          :          nt!KiPageFault+0x23d
[minkernel\ntos\ke\amd64\trap.asm @ 1248]
ffffa884`c0c3f840    fffff800`60256b63    :    ffffb30e`0e18f710    ffff8180`f0754180
ffffa884`c0c3fa18        00000000`00000002        :        NDIS!NdisQueueIoWorkItem+0x4
[minio\ndis\sys\miniport.c @ 9708]
ffffa884`c0c3f870    fffff800`60257bfd    :    00000000`00000008    00000000`00000000
00000000`00269fb1      ffff8180`f0754180      :      nt!KiProcessExpiredTimerList+0x153
[minkernel\ntos\ke\dpcsup.c @ 2078]
ffffa884`c0c3f960    fffff800`6037123a    :    00000000`00000000    ffff8180`f0754180
00000000`00000000         ffff8180`f0760cc0         :         nt!KiRetireDpcList+0x43d
```

```
[minkernel\ntos\ke\dpcsup.c @ 1512]
ffffa884`c0c3fb60    00000000`00000000    :    ffffa884`c0c40000    ffffa884`c0c39000
00000000`00000000           00000000`00000000           :           nt!KiIdleLoop+0x5a
[minkernel\ntos\ke\amd64\idle.asm @ 166]
RETRACER_ANALYSIS_TAG_STATUS:  Failed in getting KPCR for core 2
THREAD_SHA1_HASH_MOD_FUNC:  5b59a784f22d4b5cbd5a8452fe39914b8fd7961d
THREAD_SHA1_HASH_MOD_FUNC_OFFSET:  5643383f9cae3ca39073f7721b53f0c633bfb948
THREAD_SHA1_HASH_MOD:  20edda059578820e64b723e466deea47f59bd675
FOLLOWUP_IP:
NDIS!NdisQueueIoWorkItem+4 [minio\ndis\sys\miniport.c @ 9708]
fffff807`aa74f4c4 48895120        mov     qword ptr [rcx+20h],rdx
FAULT_INSTR_CODE:  20518948
FAULTING_SOURCE_LINE:  minio\ndis\sys\miniport.c
FAULTING_SOURCE_FILE:  minio\ndis\sys\miniport.c
FAULTING_SOURCE_LINE_NUMBER:  9708
FAULTING_SOURCE_CODE:
9704:     _In_ _Points_to_data_      PVOID                       WorkItemContext
9705:     )
9706: {
9707:
> 9708:     ((PNDIS_IO_WORK_ITEM)NdisIoWorkItemHandle)->Routine = Routine;
9709:                   ((PNDIS_IO_WORK_ITEM)NdisIoWorkItemHandle)->WorkItemContext    =
WorkItemContext;
9710:
9711:     IoQueueWorkItem(((PNDIS_IO_WORK_ITEM)NdisIoWorkItemHandle)->IoWorkItem,
9712:                     ndisDispatchIoWorkItem,
9713:                     CriticalWorkQueue,
SYMBOL_STACK_INDEX:  3
SYMBOL_NAME:  NDIS!NdisQueueIoWorkItem+4
FOLLOWUP_NAME:  ndiscore
MODULE_NAME: NDIS
IMAGE_NAME:  NDIS.SYS
DEBUG_FLR_IMAGE_TIMESTAMP:  0
IMAGE_VERSION:  10.0.16299.99
DXGANALYZE_ANALYSIS_TAG_PORT_GLOBAL_INFO_STR:  Hybrid_FALSE
DXGANALYZE_ANALYSIS_TAG_ADAPTER_INFO_STR:  GPU0_VenId0x1414_DevId0x8d_WDDM1.3_Active;
STACK_COMMAND:  .thread ; .cxr ; kb
BUCKET_ID_FUNC_OFFSET:  4
```

```
FAILURE_BUCKET_ID:  AV_NDIS!NdisQueueIoWorkItem
BUCKET_ID:  AV_NDIS!NdisQueueIoWorkItem
PRIMARY_PROBLEM_CLASS:  AV_NDIS!NdisQueueIoWorkItem
TARGET_TIME:  2017-12-10T14:16:08.000Z
OSBUILD:  16299
OSSERVICEPACK:  98
SERVICEPACK_NUMBER: 0
OS_REVISION: 0
SUITE_MASK:  784
PRODUCT_TYPE:  1
OSPLATFORM_TYPE:  x64
OSNAME:  Windows 10
OSEDITION:  Windows 10 WinNt TerminalServer SingleUserTS Personal
OS_LOCALE:
USER_LCID:  0
OSBUILD_TIMESTAMP:  2017-11-26 03:49:20
BUILDDATESTAMP_STR:  170928-1534
BUILDLAB_STR:  rs3_release
BUILDOSVER_STR:  10.0.16299.15.amd64fre.rs3_release.170928-1534
ANALYSIS_SESSION_ELAPSED_TIME:  8377
ANALYSIS_SOURCE:  KM
FAILURE_ID_HASH_STRING:  km:av_ndis!ndisqueueioworkitem
FAILURE_ID_HASH:  {10686423-afa1-4852-ad1b-9324ac44ac96}
FAILURE_ID_REPORT_LINK:
https://go.microsoft.com/fwlink/?LinkID=397724&FailureHash=10686423-afa1-4852-ad1b-932
4ac44ac96
Followup:     ndiscore
---------
```

Example 2

In this example, a non-Microsoft driver caused page fault, so we don't have symbols for this driver. However, looking at IMAGE_NAME and or MODULE_NAME indicates it's WwanUsbMP.sys that caused the issue. Disconnecting the device and retrying the upgrade is a possible solution.

```
1: kd> !analyze -v
*******************************************************************************
*                                                                             *
*                        Bugcheck Analysis                                    *
*                                                                             *
*******************************************************************************
```

```
PAGE_FAULT_IN_NONPAGED_AREA (50)
Invalid system memory was referenced.  This can't be protected by try-except.
Typically the address is just plain bad or it is pointing at freed memory.
Arguments:
Arg1: 8ba10000, memory referenced.
Arg2: 00000000, value 0 = read operation, 1 = write operation.
Arg3: 82154573, If non-zero, the instruction address which referenced the bad memory
address.
Arg4: 00000000, (reserved)
Debugging Details:
------------------
*** WARNING: Unable to verify timestamp for WwanUsbMp.sys
*** ERROR: Module load completed but symbols could not be loaded for WwanUsbMp.sys
KEY_VALUES_STRING: 1
STACKHASH_ANALYSIS: 1
TIMELINE_ANALYSIS: 1
DUMP_CLASS: 1
DUMP_QUALIFIER: 400
BUILD_VERSION_STRING:  16299.15.x86fre.rs3_release.170928-1534
MARKER_MODULE_NAME:  IBM_ibmpmdrv
SYSTEM_MANUFACTURER:  LENOVO
SYSTEM_PRODUCT_NAME:  20AWS07H00
SYSTEM_SKU:  LENOVO_MT_20AW_BU_Think_FM_ThinkPad T440p
SYSTEM_VERSION:  ThinkPad T440p
BIOS_VENDOR:  LENOVO
BIOS_VERSION:  GLET85WW (2.39 )
BIOS_DATE:  09/29/2016
BASEBOARD_MANUFACTURER:  LENOVO
BASEBOARD_PRODUCT:  20AWS07H00
BASEBOARD_VERSION:  Not Defined
DUMP_TYPE:  2
BUGCHECK_P1: ffffffff8ba10000
BUGCHECK_P2: 0
BUGCHECK_P3: ffffffff82154573
BUGCHECK_P4: 0
READ_ADDRESS: 822821d0: Unable to get MiVisibleState
8ba10000
FAULTING_IP:
```

```
nt!memcpy+33 [minkernel\crts\crtw32\string\i386\memcpy.asm @ 213
82154573 f3a5            rep movs dword ptr es:[edi],dword ptr [esi]
MM_INTERNAL_CODE:  0
CPU_COUNT: 4
CPU_MHZ: 95a
CPU_VENDOR:  GenuineIntel
CPU_FAMILY: 6
CPU_MODEL: 3c
CPU_STEPPING: 3
CPU_MICROCODE: 6,3c,3,0 (F,M,S,R)  SIG: 21'00000000 (cache) 21'00000000 (init)
BLACKBOXBSD: 1 (!blackboxbsd)
BLACKBOXPNP: 1 (!blackboxpnp)
DEFAULT_BUCKET_ID:  WIN8_DRIVER_FAULT
BUGCHECK_STR:  AV
PROCESS_NAME:  System
CURRENT_IRQL:  2
ANALYSIS_SESSION_HOST:  SHENDRIX-DEV0
ANALYSIS_SESSION_TIME:  01-17-2019 10:54:53.0780
ANALYSIS_VERSION: 10.0.18248.1001 amd64fre
TRAP_FRAME:  8ba0efa8 -- (.trap 0xffffffff8ba0efa8)
ErrCode = 00000000
eax=8ba1759e ebx=a2bfd314 ecx=00001d67 edx=00000002 esi=8ba10000 edi=a2bfe280
eip=82154573 esp=8ba0f01c ebp=8ba0f024 iopl=0         nv up ei pl nz ac pe nc
cs=0008  ss=0010  ds=0023  es=0023  fs=0030  gs=0000             efl=00010216
nt!memcpy+0x33:
82154573 f3a5            rep movs dword ptr es:[edi],dword ptr [esi]
Resetting default scope
LOCK_ADDRESS:  8226c6e0 -- (!locks 8226c6e0)
Cannot get _ERESOURCE type
Resource @ nt!PiEngineLock (0x8226c6e0)    Available
1 total locks
PNP_TRIAGE_DATA:
Lock address  : 0x8226c6e0
Thread Count  : 0
Thread address: 0x00000000
Thread wait   : 0x0
LAST_CONTROL_TRANSFER:  from 82076708 to 821507e8
STACK_TEXT:
```

8ba0ede4 82076708 00000050 8ba10000 00000000 nt!KeBugCheckEx [minkernel\ntos\ke\i386\procstat.asm @ 114]

8ba0ee40 8207771e 8ba0efa8 8ba10000 8ba0eea0 nt!MiSystemFault+0x13c8 [minkernel\ntos\mm\mmfault.c @ 4755]

8ba0ef08 821652ac 00000000 8ba10000 00000000 nt!MmAccessFault+0x83e [minkernel\ntos\mm\mmfault.c @ 6868]

8ba0ef08 82154573 00000000 8ba10000 00000000 nt!_KiTrap0E+0xec [minkernel\ntos\ke\i386\trap.asm @ 5153]

8ba0f024 86692866 a2bfd314 8ba0f094 0000850a nt!memcpy+0x33 [minkernel\crts\crtw32\string\i386\memcpy.asm @ 213]

8ba0f040 866961bc 8ba0f19c a2bfd0e8 00000000 NDIS!ndisMSetPowerManagementCapabilities+0x8a [minio\ndis\sys\miniport.c @ 7969]

8ba0f060 866e1f66 866e1caf adfb9000 00000000 NDIS!ndisMSetGeneralAttributes+0x23d [minio\ndis\sys\miniport.c @ 8198]

8ba0f078 ac50c15f a2bfd0e8 0000009f 00000001 NDIS!NdisMSetMiniportAttributes+0x2b7 [minio\ndis\sys\miniport.c @ 7184]

WARNING: Stack unwind information not available. Following frames may be wrong.

8ba0f270 ac526f96 adfb9000 a2bfd0e8 8269b9b0 WwanUsbMp+0x1c15f

8ba0f3cc 866e368a a2bfd0e8 00000000 8ba0f4c0 WwanUsbMp+0x36f96

8ba0f410 867004b0 a2bfd0e8 a2bfd0e8 a2be2a70 NDIS!ndisMInvokeInitialize+0x60 [minio\ndis\sys\miniport.c @ 13834]

8ba0f7ac 866dbc8e a2acf730 866b807c 00000000 NDIS!ndisMInitializeAdapter+0xa23 [minio\ndis\sys\miniport.c @ 601]

8ba0f7d8 866e687d a2bfd0e8 00000000 00000000 NDIS!ndisInitializeAdapter+0x4c [minio\ndis\sys\initpnp.c @ 931]

8ba0f800 866e90bb adfb64d8 00000000 a2bfd0e8 NDIS!ndisPnPStartDevice+0x118 [minio\ndis\sys\configm.c @ 4235]

8ba0f820 866e8a58 adfb64d8 a2bfd0e8 00000000 NDIS!ndisStartDeviceSynchronous+0xbd [minio\ndis\sys\ndispnp.c @ 3096]

8ba0f838 866e81df adfb64d8 8ba0f85e 8ba0f85f NDIS!ndisPnPIrpStartDevice+0xb4 [minio\ndis\sys\ndispnp.c @ 1067]

8ba0f860 820a7e98 a2bfd030 adfb64d8 8ba0f910 NDIS!ndisPnPDispatch+0x108 [minio\ndis\sys\ndispnp.c @ 2429]

8ba0f878 8231f07e 8ba0f8ec adf5d4c8 872e2eb8 nt!IofCallDriver+0x48 [minkernel\ntos\io\iomgr\iosubs.c @ 3149]

8ba0f898 820b8569 820c92b8 872e2eb8 8ba0f910 nt!PnpAsynchronousCall+0x9e [minkernel\ntos\io\pnpmgr\irp.c @ 3005]

8ba0f8cc 820c9a76 00000000 820c92b8 872e2eb8 nt!PnpSendIrp+0x67 [minkernel\ntos\io\pnpmgr\irp.h @ 286]

8ba0f914 8234577b 872e2eb8 adf638b0 adf638b0 nt!PnpStartDevice+0x60

```
[minkernel\ntos\io\pnpmgr\irp.c @ 3187]
8ba0f94c    82346cc7    872e2eb8    adf638b0    adf638b0    nt!PnpStartDeviceNode+0xc3
[minkernel\ntos\io\pnpmgr\start.c @ 1712]
8ba0f96c    82343c68    00000000    a2bdb3d8    adf638b0    nt!PipProcessStartPhase1+0x4d
[minkernel\ntos\io\pnpmgr\start.c @ 114]
8ba0fb5c    824db885    8ba0fb80    00000000    00000000    nt!PipProcessDevNodeTree+0x386
[minkernel\ntos\io\pnpmgr\enum.c @ 6129]
8ba0fb88     8219571b     85852520     8c601040     8226ba90     nt!PiRestartDevice+0x91
[minkernel\ntos\io\pnpmgr\enum.c @ 4743]
8ba0fbe8   820804af   00000000   00000000   8c601040   nt!PnpDeviceActionWorker+0xdb4b7
[minkernel\ntos\io\pnpmgr\action.c @ 674]
8ba0fc38     8211485c     85852520     421de295     00000000     nt!ExpWorkerThread+0xcf
[minkernel\ntos\ex\worker.c @ 4270]
8ba0fc70    82166785    820803e0    85852520    00000000    nt!PspSystemThreadStartup+0x4a
[minkernel\ntos\ps\psexec.c @ 7756]
8ba0fc88     82051e07     85943940     8ba0fcd8     82051bb9     nt!KiThreadStartup+0x15
[minkernel\ntos\ke\i386\threadbg.asm @ 82]
8ba0fc94   82051bb9   8b9cc600   8ba10000   8ba0d000   nt!KiProcessDeferredReadyList+0x17
[minkernel\ntos\ke\thredsup.c @ 5309]
8ba0fcd8    00000000    00000000    00000000    00000000    nt!KeSetPriorityThread+0x249
[minkernel\ntos\ke\thredobj.c @ 3881]
RETRACER_ANALYSIS_TAG_STATUS:  Failed in getting KPCR for core 1
THREAD_SHA1_HASH_MOD_FUNC:  e029276c66aea80ba36903e89947127118d31128
THREAD_SHA1_HASH_MOD_FUNC_OFFSET:  012389f065d31c8eedd6204846a560146a38099b
THREAD_SHA1_HASH_MOD:  44dc639eb162a28d47eaeeae4afe6f9eeccced3d
FOLLOWUP_IP:
WwanUsbMp+1c15f
ac50c15f 8bf0            mov     esi,eax
FAULT_INSTR_CODE:  f33bf08b
SYMBOL_STACK_INDEX:  8
SYMBOL_NAME:  WwanUsbMp+1c15f
FOLLOWUP_NAME:  MachineOwner
MODULE_NAME: WwanUsbMp
IMAGE_NAME:  WwanUsbMp.sys
DEBUG_FLR_IMAGE_TIMESTAMP:  5211bb0c
DXGANALYZE_ANALYSIS_TAG_PORT_GLOBAL_INFO_STR:  Hybrid_FALSE
DXGANALYZE_ANALYSIS_TAG_ADAPTER_INFO_STR:
GPU0_VenId0x1414_DevId0x8d_WDDM1.3_NotActive;GPU1_VenId0x8086_DevId0x416_WDDM1.3_Activ
e_Post;
```

```
STACK_COMMAND:  .thread ; .cxr ; kb
BUCKET_ID_FUNC_OFFSET:  1c15f
FAILURE_BUCKET_ID:  AV_R_INVALID_WwanUsbMp!unknown_function
BUCKET_ID:  AV_R_INVALID_WwanUsbMp!unknown_function
PRIMARY_PROBLEM_CLASS:  AV_R_INVALID_WwanUsbMp!unknown_function
TARGET_TIME:  2018-02-12T11:33:51.000Z
OSBUILD:  16299
OSSERVICEPACK:  15
SERVICEPACK_NUMBER: 0
OS_REVISION: 0
SUITE_MASK:  272
PRODUCT_TYPE:  1
OSPLATFORM_TYPE:  x86
OSNAME:  Windows 10
OSEDITION:  Windows 10 WinNt TerminalServer SingleUserTS
OS_LOCALE:
USER_LCID:  0
OSBUILD_TIMESTAMP:  2017-09-28 18:32:28
BUILDDATESTAMP_STR:  170928-1534
BUILDLAB_STR:  rs3_release
BUILDOSVER_STR:  10.0.16299.15.x86fre.rs3_release.170928-1534
ANALYSIS_SESSION_ELAPSED_TIME:  162bd
ANALYSIS_SOURCE:  KM
FAILURE_ID_HASH_STRING:  km:av_r_invalid_wwanusbmp!unknown_function
FAILURE_ID_HASH:  {31e4d053-0758-e43a-06a7-55f69b072cb3}
FAILURE_ID_REPORT_LINK:
https://go.microsoft.com/fwlink/?LinkID=397724&FailureHash=31e4d053-0758-e43a-06a7-55f
69b072cb3
Followup:     MachineOwner
---------
ReadVirtual: 812d1248 not properly sign extended
```

11.8 References

Bug check code reference

Artículo 12: Windows-based computer freeze troubleshooting

12.0 Overview

This article describes how to troubleshoot freeze issues on Windows-based computers and servers. It also provides methods for collecting data that will help administrators or software developers diagnose, identify, and fix these issues.

Note:

The third-party products that this article discusses are manufactured by companies that are independent of Microsoft. Microsoft makes no warranty, implied or otherwise, about the performance or reliability of these products.

Applies to: Windows 10

12.1 Identify the problem

- Which computer is freezing? For example, the affected computer is a physical server or a virtual server.
- What operation happened when it froze? For example, this issue occurs when you shut down.
- How often do the errors occur? For example, this issue occurs every night at 7 PM.
- On how many computers does this freeze occur? For example, all computers or only one computer.

12.2 Troubleshoot the freeze issues

To troubleshoot the freeze issues, check the current status of your computer, and follow one of the following methods.

For the computer that's still running in a frozen state

If the physical computer or the virtual machine is still freezing, use one or more of the following methods for troubleshooting:

- Try to access the computer through a remote desktop connection.
- Use a domain account or local administrator account to sign in to the computer with the hardware manufacturer's remote access solution. For example, Dell Remote Access Card (DRAC), HP Integrated Lights-Out (iLo), or IBM Remote supervisor adapter (RSA).
- Test ping to the computer. Look for dropped packets and high network latency.
- Access administrative shares, for example \\\\ServerName\\c$.
- Press Ctrl+Alt+Delete and check the response.
- Try to use Windows remote administration tools. For example, Computer Management, Server Manager, and Wmimgmt.msc.

For the computer that's no longer frozen

If the physical computer or virtual machine froze, but is now running in a good state, use one or more of the following methods for troubleshooting.

For a physical computer

- Review the System and Application logs from the computer that's having the issue. Check the event logs for the relevant Event ID:

- Application event log: Application Error, which suggests a crash or relevant system process
- System Event logs, Service Control Manager Error event IDs for critical system services
- Error Event IDs 2019/2020 with source Srv/Server
- Generate a System Diagnostics report by running perfmon /report.

For a virtual machine

- Review the System and Application logs from the computer that is having the issue.
- Generate a System Diagnostics report by running perfmon /report.
- Check the system's history in virtual management monitoring tools.

12.3 Collect data for the freeze issues

To collect data for a server freeze, check the following table, and use one or more of the suggested methods.

Computer type and state | Data collection method

A physical computer that's running in a frozen state | Use a memory dump file to collect data. Or use method 2, 3, or 4. These methods are listed later in this section.

A physical computer that is no longer frozen | Use method 1, 2, 3, or 4. These methods are listed later in this section. And use Pool Monitor to collect data.

A virtual machine that's running in a frozen state | Hyper-V or VMware: Use a memory dump file to collect data for the virtual machine that's running in a frozen state. XenServer: Use method 1, 2, 3, or 4. These methods are listed later in this section.

A virtual machine that is no longer frozen | Use method 1, 2, 3, or 4. These methods are listed later in this section.

Method 1: Memory dump

Important:

Follow the steps in this section carefully. Serious problems might occur if you modify the registry incorrectly. Before you modify it, back up the registry for restoration in case problems occur.

A complete memory dump file records all the contents of system memory when the computer stops unexpectedly. A complete memory dump file may contain data from processes that were running when the memory dump file was collected.

If the computer is no longer frozen and now is running in a good state, use the following steps to enable memory dump so that you can collect memory dump when the freeze issue occurs again. If the virtual machine is still running in a frozen state, use the following steps to enable and collect memory dump.

Note:

If you have a restart feature that's enabled on the computer, such as the Automatic System Restart (ASR) feature in Compaq computers, disable it. This setting is usually found in the BIOS. With this feature enabled, if the BIOS doesn't detect a heartbeat from the operating system, it will restart the computer. The restart can interrupt the dump process.

1. Make sure that the computer is set up to get a complete memory dump file.

1. Go to Run and enter Sysdm.cpl, and then press Enter.

2. In System Properties, on the Advanced tab, select Performance > Settings > Advanced. Select Change to check or change the virtual memory.

3. Go back to System Properties > Advanced > Settings in Startup and Recovery.

4. In the Write Debugging Information section, select Complete Memory Dump.

5. Select Overwrite any existing file.

6. Make sure that there's a paging file (pagefile.sys) on the system drive and that it's at least 100 MB over the installed RAM (Initial and Maximum Size).

7. Make sure that there's more available space on the system drive than there's physical RAM.

2. To allow the system to generate a dump file by using the keyboard, enable the CrashOnCtrlScroll registry value.

1. Open the Registry Editor, and then locate the following registry keys:

- HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\i8042prt\Parameters

- HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\kbdhid\Parameters

2. Create the following CrashOnCtrlScroll registry entry in the two registry keys:

- Value Name: CrashOnCtrlScroll

- Data Type: REG_DWORD

- Value: 1

3. Close the Registry Editor and restart the computer.

3. On some physical computers running earlier versions of Windows, you may generate a nonmakeable interruption (NMI) from a web interface feature such as DRAC, iLo, or RSA. However, by default, this setting will stop the system without creating a memory dump.

Note:

For currently supported versions of Windows, the NMICrashDump registry key is no longer required. An NMI causes a Stop error that follows a memory dump data collection.

4. When the computer exhibits the problem, hold down the right Ctrl key, and press the Scroll Lock key two times to generate a memory dump file.

Note:

By default, the dump file is located in the following path: %SystemRoot%\\MEMORY.DMP.

Method 2: Data sanity check

Use the Dump Check Utility (Dumpchk.exe) to read a memory dump file. It can also verify that the file was created correctly and isn't corrupted or invalid.

- Using DumpChk

- Download DumpChk

Learn how to use Dumpchk.exe to check your dump files:

[!VIDEO https://www.youtube.com/embed/xN7tOfgNKag]

Method 3: Performance Monitor

You can use Windows Performance Monitor to examine how programs that you run affect your computer's

performance, both in real time and by collecting log data for later analysis. To create performance counter and event trace log collections on local and remote systems, run the following commands in a command prompt as administrator:

```
Logman create counter LOGNAME_Long -u DOMAIN\USERNAME * -f bincirc -v mmddhhmm -max
500        -c        "\\COMPUTERNAME\LogicalDisk(*)\*"        "\\COMPUTERNAME\Memory\*"
"\\COMPUTERNAME\Network      Interface(*)\*"      "\\COMPUTERNAME\Paging      File(*)\*"
"\\COMPUTERNAME\PhysicalDisk(*)\*"                        "\\COMPUTERNAME\Process(*)\*"
"\\COMPUTERNAME\Redirector\*"    "\\COMPUTERNAME\Server\*"    "\\COMPUTERNAME\System\*"
"\\COMPUTERNAME\Terminal          Services\*"          "\\COMPUTERNAME\Processor(*)\*"
"\\COMPUTERNAME\Cache\*" -si 00:05:00
Logman create counter LOGNAME_Short -u DOMAIN\USERNAME * -f bincirc -v mmddhhmm -max
500        -c        "\\COMPUTERNAME\LogicalDisk(*)\*"        "\\COMPUTERNAME\Memory\*"
"\\COMPUTERNAME\Network      Interface(*)\*"      "\\COMPUTERNAME\Paging      File(*)\*"
"\\COMPUTERNAME\PhysicalDisk(*)\*"                        "\\COMPUTERNAME\Process(*)\*"
"\\COMPUTERNAME\Redirector\*"    "\\COMPUTERNAME\Server\*"    "\\COMPUTERNAME\System\*"
"\\COMPUTERNAME\Terminal          Services\*"          "\\COMPUTERNAME\Processor(*)\*"
"\\COMPUTERNAME\Cache\*" -si 00:00:10
```

Then, you can start or stop the log by running the following commands:

```
logman start LOGNAME_Long / LOGNAME_Short
logman stop LOGNAME_Long / LOGNAME_Short
```

The Performance Monitor log is located in the path: C:\\PERFLOGS.

Other methods to collect data

Use memory dump to collect data for the physical computer that's running in a frozen state

Warning:

Follow the steps in this section carefully. Serious problems might occur if you modify the registry incorrectly. Before you modify it, back up the registry for restoration in case problems occur.

If the physical computer is still running in a frozen state, follow these steps to enable and collect memory dump:

1. Make sure that the computer is set up to get a complete memory dump file and that you can access it through the network.

Note:

If it isn't possible to access the affected computer through the network, try to generate a memory dump file through NMI. The result of the action may not collect a memory dump file if some of the following settings aren't qualified.

1. Try to access the desktop of the computer by any means.

Note:

In case accessing the OS isn't possible, try to remotely access Registry Editor on the computer. You can then check the type of memory dump file and page file with which the computer is currently configured.

2. From a remote computer that's preferably in the same network and subnet, go to Registry Editor >

Connect Network Registry. Then, connect to the affected computer, and verify the following settings:

- HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\CrashControl\CrashDumpEnabled

Make sure that the CrashDumpEnabled) registry entry is 1.

- HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\CrashControl\NMICrashDump

On some physical servers, if the NMICrashDump registry entry exists and its value is 1, you may take advantage of the NMI from the remote management provider such as DRAC, iLo, and RSA.

- HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Session Manager\Memory Management\PagingFiles and ExistingPageFiles

If the value of the Pagefile registry entry is system-managed, the size won't be reflected in the registry. For example, ?:\pagefile.sys)

If the page file is customized, the size will be reflected in the registry, such as ?:\pagefile.sys 1024 1124. In this example, 1024 is the initial size and 1124 is the max size.

Note:

If the size isn't reflected in the Registry, try to access an administrative share where the page file is located. For example, \\\\ServerName\\C$.

3. Make sure that there's a paging file (pagefile.sys) on the system drive of the computer, and it's at least 100 MB over the installed RAM.

4. Make sure that there's more free space on the hard disk drives of the computer than there's physical RAM.

2. Enable the CrashOnCtrlScroll registry value on the computer to allow the system to generate a dump file by using the keyboard.

1. From a remote computer preferably in the same network and subnet, go to Registry Editor > Connect Network Registry. Connect to the affected computer and locate the following registry keys:

- HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\i8042prt\Parameters

- HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\kbdhid\Parameters

2. Create the following CrashOnCtrlScroll registry entry in the two registry keys:

Value Name: CrashOnCtrlScroll

Data Type: REG_DWORD

Value: 1

3. Close the Registry Editor and restart the computer.

3. When the computer exhibits the problem, hold down the right Ctrl key, and press the Scroll Lock key two times to generate a memory dump.

Note:

By default, the dump file is located in the path: %SystemRoot%\\MEMORY.DMP.

Use Pool Monitor to collect data for the physical computer that is no longer frozen

Pool Monitor shows you the number of allocations and outstanding bytes of allocation by type of pool and the tag that is passed into calls of ExAllocatePoolWithTag.

For more information, see Using PoolMon to Find a Kernel-Mode Memory Leak and PoolMon Examples.

Use memory dump to collect data for the virtual machine that's running in a frozen state

Use the one of the following methods for the application on which the virtual machine is running.

Microsoft Hyper-V

You can also use the built-in NMI feature through a Debug-VM cmdlet to debug and get a memory dump.

To debug the virtual machines on Hyper-V, run the following cmdlet in Windows PowerShell:

```
Debug-VM -Name "VM Name" -InjectNonMaskableInterrupt -ComputerName Hostname
```

VMware

You can use VMware snapshots or suspend state and extract a memory dump file equivalent to a complete memory dump file. Use VMware's Checkpoint To Core Tool (vmss2core) to convert both suspend (.vmss) and snapshot (.vmsn) state files to a dump file. Then analyze the file by using the standard Windows debugging tools.

Note:

When working with Microsoft Support, you should use VMware's Checkpoint To Core Tool (vmss2core) to convert VMware snapshots to a dump file before uploading them to Microsoft. If you experience any issues with the snapshot conversion, contact VMware for support.

Citrix XenServer

The memory dump process occurs by pressing the Right Ctrl+Scroll Lock+Scroll Lock keyboard combination. For more information, see Method 1 of How to Trigger a Memory Dump from a Windows Virtual Machine Running on XenServer from Citrix.

12.4 Space limitations on the system drive in Windows Server

On a Windows Server, you may not have enough free disk space to generate a complete memory dump file on the system volume.

There's a second option if the system drive doesn't have sufficient space. You can use the DedicatedDumpFile registry entry. For more information, see Configure the destination path for a memory dump.

For more information, see How to use the DedicatedDumpFile registry value to overcome space limitations on the system drive.

Artículo 13: Printer Not Responding

13.0 Overview

This article provides solutions to an issue where a printer isn't responding.

When a printer isn't responding, it generally means that the printer can't communicate with the computer device or the server. This issue occurs for several reasons, for example:

- Network communication problem with the device
- Unstable printer state or error state
- Driver outdated or corrupt

To resolve the issue, perform the following verifications in order:

13.1 1. Check the printer connection

Ensure that the printer is properly connected to your computer or network:

- For wired printers, make sure the cable is securely plugged in.
- For wireless printers, verify that the printer is connected to a functioning Wi-Fi network.

13.2 2. Check if the printer is in a problematic state

Check the printer's display panel or the printer status on your computer. If the printer is in a Stopped state, add the Status Reason column to see if there's an error, such as Out of toner or Off-line.

13.3 3. Check the printer properties

Right-click the printer icon and select Properties. Select the General tab and check the device status message. It might indicate a problem or provide an error code to check online or in the printer manual.

13.4 4. Restart the printer

Turn off the printer, wait about 30 seconds, and then turn it back on. This action can often resolve temporary issues.

13.5 5. Run the printer troubleshooter

Run the built-in printer troubleshooter on your Windows computer. To do so, go to Settings > System > Troubleshoot > Other troubleshooters, and then select Run next to Printer.

13.6 6. Reinstall the printer driver

Right-click your printer in Device Manager and select Uninstall device. Then, restart your computer and reinstall the driver.

If the driver is the latest original equipment manufacturer (OEM) version, try switching to a generic in-box driver.

13.7 7. Check the Print Spooler service state

Restart the Print Spooler service to clear any stuck print jobs by using one of the following methods. For more information, see Printing issues caused by the Print Spooler service not running.

Manually restart the service

In the Services application, right-click Print Spooler in the list, and select Restart.

Use Command Prompt

Type cmd in the search bar, right-click Command Prompt, and select Run as administrator to open Command Prompt as an administrator. Run the following commands and press Enter after each one:

```
-net stop spooler
-net start spooler
```

Use Windows PowerShell

Type powershell in the search bar, right-click Windows PowerShell, and select Run as administrator to open PowerShell as an administrator. Run the following cmdlet and press Enter:

```
Restart-Service -Name spooler
```

13.8 8. Verify the printer queue status

If there are any stuck print jobs, clear the queue and resubmit the print job.

To delete any files stuck in the queue, follow these steps:

1. Stop the Print Spooler service.
2. Open File Explorer and navigate to C:\\Windows\\System32\\spool\\PRINTERS.
3. Delete all files (.shd files) in this folder. These files are the print jobs that are stuck in the queue.
4. Restart the Print Spooler service.

13.9 9. Update the printer firmware

Check the manufacturer's website for any firmware updates available for your printer.

13.10 Data collection

If you need assistance from Microsoft support, we recommend you collect the information by following the steps mentioned in Gather information by using TSS for user experience-related issues.

Artículo 14: Error codes for dial-up or VPN connections

14.0 Overview

This article lists the error codes that you may receive when you make a dial-up connection or a VPN connection.

Original KB number: 824864

Note:

Error codes with numbers higher than 900 will only be seen if you are trying to connect to a Routing and Remote Access Server that is running Windows 2000 or later.

14.1 Error codes

The following list contains the error codes for dial-up connections or VPN connections:

- 600

An operation is pending.

- 601

The port handle is invalid.

- 602

The port is already open.

- 603

Caller's buffer is too small.

- 604

Wrong information specified.

- 605

Cannot set port information.

- 606

The port is not connected.

- 607

The event is invalid.

- 608

The device does not exist.

- 609

The device type does not exist.

- 610

The buffer is invalid.

- 611

The route is not available.

- 612

The route is not allocated.

- 613

Invalid compression specified.

- 614

Out of buffers.

- 615

The port was not found.

- 616

An asynchronous request is pending.

- 617

The port or device is already disconnecting.

- 618

The port is not open.

- 619

The port is disconnected.

- 620

There are no endpoints.

- 621

Cannot open the phone book file.

- 622

Cannot load the phone book file.

- 623
- Cannot find the phone book entry.

- 624

Cannot write the phone book file.

- 625

Invalid information found in the phone book.

- 626

Cannot load a string.

- 627

Cannot find key.

- 628

The port was disconnected.

- 629

The port was disconnected by the remote machine.

- 630

The port was disconnected due to hardware failure.

- 631

The port was disconnected by the user.

- 632

The structure size is incorrect.

- 633

The port is already in use or is not configured for Remote Access dialout.

- 634

Cannot register your computer on the remote network.

- 635

Unknown error.

- 636

The wrong device is attached to the port.

- 637

The string could not be converted.

- 638

The request has timed out.

- 639

No asynchronous net available.

- 640

A NetBIOS error has occurred.

- 641

The server cannot allocate NetBIOS resources needed to support the client.

- 642

One of your NetBIOS names is already registered on the remote network.

- 643

A network adapter at the server failed.

- 644

You will not receive network message popups.

- 645

Internal authentication error.

- 646

The account is not permitted to log on at this time of day.

- 647

The account is disabled.

- 648

The password has expired.

- 649

The account does not have Remote Access permission.

- 650

The Remote Access server is not responding.

- 651

Your modem (or other connecting device) has reported an error.

- 652

Unrecognized response from the device.

- 653

A macro required by the device was not found in the device .INF file section.

- 654

A command or response in the device .INF file section refers to an undefined macro

- 655

The \ macro was not found in the device .INF file section.

- 656

The \ macro in the device .INF file section contains an undefined macro

- 657

The device .INF file could not be opened.

- 658

The device name in the device .INF or media .INI file is too long.

- 659

The media .INI file refers to an unknown device name.

- 660

The device .INF file contains no responses for the command.

- 661

The device .INF file is missing a command.

- 662

Attempted to set a macro not listed in device .INF file section.

- 663

The media .INI file refers to an unknown device type.

- 664

Cannot allocate memory.

- 665

The port is not configured for Remote Access.

- 666

Your modem (or other connecting device) is not functioning.

- 667

Cannot read the media .INI file.

- 668

The connection dropped.

- 669

The usage parameter in the media .INI file is invalid.

- 670

Cannot read the section name from the media .INI file.

- 671

Cannot read the device type from the media .INI file.

- 672

Cannot read the device name from the media .INI file.

- 673

Cannot read the usage from the media .INI file.

- 674

Cannot read the maximum connection BPS rate from the media .INI file.

- 675

Cannot read the maximum carrier BPS rate from the media .INI file.

- 676

The line is busy.

- 677

A person answered instead of a modem.

- 678

There is no answer.

- 679

Cannot detect carrier.

- 680

There is no dial tone.

- 681

General error reported by device.

- 682

ERROR WRITING SECTIONNAME

- 683

ERROR WRITING DEVICETYPE

- 684

ERROR WRITING DEVICENAME

- 685

ERROR WRITING MAXCONNECTBPS

- 686

ERROR WRITING MAXCARRIERBPS

- 687

ERROR WRITING USAGE

- 688

ERROR WRITING DEFAULTOFF

- 689

ERROR READING DEFAULTOFF

- 690

ERROR EMPTY INI FILE

- 691

Access denied because username and/or password is invalid on the domain.

- 692

Hardware failure in port or attached device.

- 693

ERROR NOT BINARY MACRO

- 694

ERROR DCB NOT FOUND

- 695

ERROR STATE MACHINES NOT STARTED

- 696

ERROR STATE MACHINES ALREADY STARTED

- 697

ERROR PARTIAL RESPONSE LOOPING

- 698

A response keyname in the device .INF file is not in the expected format.

- 699

The device response caused buffer overflow.

- 700

The expanded command in the device .INF file is too long.

- 701

The device moved to a BPS rate not supported by the COM driver.

- 702

Device response received when none expected.

- 703

ERROR INTERACTIVE MODE

- 704

ERROR BAD CALLBACK NUMBER

- 705

ERROR INVALID AUTH STATE

- 706

ERROR WRITING INITBPS

- 707

X.25 diagnostic indication.

- 708

The account has expired.

- 709

Error changing password on domain.

- 710

Serial overrun errors were detected while communicating with your modem.

- 711

RasMan initialization failure. Check the event log.

- 712

Biplex port is initializing. Wait a few seconds and redial.

- 713

No active ISDN lines are available.

- 714

Not enough ISDN channels are available to make the call.

- 715

Too many errors occurred because of poor phone line quality.

- 716

The Remote Access IP configuration is unusable.

- 717

No IP addresses are available in the static pool of Remote Access IP addresses.

- 718

PPP timeout.

- 719

PPP terminated by remote machine.

- 720

No PPP control protocols configured.

- 721

Remote PPP peer is not responding.

- 722

The PPP packet is invalid.

- 723

The phone number, including prefix and suffix, is too long.

- 724

The IPX protocol cannot dial-out on the port because the computer is an IPX router.

- 725

The IPX protocol cannot dial-in on the port because the IPX router is not installed.

- 726

The IPX protocol cannot be used for dial-out on more than one port at a time.

- 727

Cannot access TCPCFG.DLL.

- 728

Cannot find an IP adapter bound to Remote Access.

- 729

SLIP cannot be used unless the IP protocol is installed.

- 730

Computer registration is not complete.

- 731

The protocol is not configured.

- 732

The PPP negotiation is not converging.

- 733

The PPP control protocol for this network protocol is not available on the server.

- 734

The PPP link control protocol terminated.

- 735

The requested address was rejected by the server.

- 736

The remote computer terminated the control protocol.

- 737

Loopback detected.

- 738

The server did not assign an address.

- 739

The remote server cannot use the Windows NT encrypted password.

- 740

The TAPI devices configured for Remote Access failed to initialize or were not installed correctly.

- 741

The local computer does not support encryption.

- 742

The remote server does not support encryption.

- 743

The remote server requires encryption.

- 744

Cannot use the IPX net number assigned by the remote server. Check the event log.

- 745

ERROR_INVALID_SMM

- 746

ERROR_SMM_UNINITIALIZED

- 747

ERROR_NO_MAC_FOR_PORT

- 748

ERROR_SMM_TIMEOUT

- 749

ERROR_BAD_PHONE_NUMBER

- 750

ERROR_WRONG_MODULE

- 751

The callback number contains an invalid character. Only the following 18 characters are allowed: 0 to 9, T, P,

W, (,), -, @, and space

- 752

A syntax error was encountered while processing a script.

- 753

The connection could not be disconnected because it was created by the multi-protocol router.

- 754

The system could not find the multi-link bundle.

- 755

The system cannot perform automated dial because this connection has a custom dialer specified.

- 756

This connection is already being dialed.

- 757

Remote Access Services could not be started automatically. Additional information is provided in the event log.

- 758

Internet Connection Sharing is already enabled on the connection.

- 759

An error occurred while the existing Internet Connection Sharing settings were being changed.

- 760

An error occurred while routing capabilities were being enabled.

- 761

An error occurred while Internet Connection Sharing was being enabled for the connection.

- 762

An error occurred while the local network was being configured for sharing.

- 763

Internet Connection Sharing cannot be enabled. There is more than one LAN connection other than the connection to be shared.

- 764

No smart card reader is installed.

- 765

Internet Connection Sharing cannot be enabled. A LAN connection is already configured with the IP address that is required for automatic IP addressing.

- 766

A certificate could not be found. Connections that use the L2TP protocol over IPSec require the installation of a machine certificate, also known as a computer certificate.

- 767

Internet Connection Sharing cannot be enabled. The LAN connection selected as the private network has more than one IP address configured. Reconfigure the LAN connection with a single IP address before enabling Internet Connection Sharing.

- 768

The connection attempt failed because of failure to encrypt data.

- 769

The specified destination is not reachable.

- 770

The remote computer rejected the connection attempt.

- 771

The connection attempt failed because the network is busy.

- 772

The remote computer's network hardware is incompatible with the type of call requested.

- 773

The connection attempt failed because the destination number has changed.

- 774

The connection attempt failed because of a temporary failure. Try connecting again.

- 775

The call was blocked by the remote computer.

- 776

The call could not be connected because the remote computer has invoked the Do Not Disturb feature.

- 777

The connection attempt failed because the modem (or other connecting device on the remote computer is out of order.

- 778

It was not possible to verify the identity of the server.

- 779

To dial out using this connection, you must use a smart card.

- 780

An attempted function is not valid for this connection.

- 781

The connection requires a certificate, and no valid certificate was found. For further assistance, click More Info or search Help and Support Center for this error number.

- 782

Internet Connection Sharing (ICS and Internet Connection Firewall (ICF cannot be enabled because Routing and Remote Access has been enabled on this computer. To enable ICS or ICF, first disable Routing and

Remote Access. For more information about Routing and Remote Access, ICS, or ICF, see Help and Support.

- 783

Internet Connection Sharing cannot be enabled. The LAN connection selected as the private network is either not present, or is disconnected from the network. Ensure that the LAN adapter is connected before enabling Internet Connection Sharing.

- 784

You cannot dial using this connection at logon time, because it is configured to use a user name different than the one on the smart card. If you want to use it at logon time, you must configure it to use the user name on the smart card.

- 785

You cannot dial using this connection at logon time, because it is not configured to use a smart card. If you want to use it at logon time, you must edit the properties of this connection so that it uses a smart card.

- 786

The L2TP connection attempt failed because there is no valid machine certificate on your computer for security authentication.

- 787

The L2TP connection attempt failed because the security layer could not authenticate the remote computer.

- 788

The L2TP connection attempt failed because the security layer could not negotiate compatible parameters with the remote computer.

- 789

The L2TP connection attempt failed because the security layer encountered a processing error during initial negotiations with the remote computer.

- 790

The L2TP connection attempt failed because certificate validation on the remote computer failed.

- 791

The L2TP connection attempt failed because security policy for the connection was not found.

- 792

The L2TP connection attempt failed because security negotiation timed out.

- 793

The L2TP connection attempt failed because an error occurred while negotiating security.

- 794

The Framed Protocol RADIUS attribute for this user is not PPP.

- 795

The Tunnel Type RADIUS attribute for this user is not correct.

- 796

The Service Type RADIUS attribute for this user is neither Framed nor Callback Framed.

- 797

A connection to the remote computer could not be established because the modem was not found or was busy. For further assistance, click More Info or search Help and Support Center for this error number.

- 798

A certificate could not be found that can be used with this Extensible Authentication Protocol.

- 799

Internet Connection Sharing (ICS cannot be enabled due to an IP address conflict on the network. ICS requires the host be configured to use 192.168.0.1. Ensure that no other client on the network is configured to use 192.168.0.1.

- 800

Unable to establish the VPN connection. The VPN server may be unreachable, or security parameters may not be configured properly for this connection.

- 801

This connection is configured to validate the identity of the access server, but Windows cannot verify the digital certificate sent by the server.

- 802

The card supplied was not recognized. Check that the card is inserted correctly, and fits tightly.

- 803

The PEAP configuration stored in the session cookie does not match the current session configuration.

- 804

The PEAP identity stored in the session cookie does not match the current identity.

- 805

You cannot dial using this connection at logon time, because it is configured to use logged on user's credentials.

- 900

The router is not running.

- 901

The interface is already connected.

- 902

The specified protocol identifier is not known to the router.

- 903

The Demand-dial Interface Manager is not running.

- 904

An interface with this name is already registered with the router.

- 905

An interface with this name is not registered with the router.

- 906

The interface is not connected.

- 907

The specified protocol is stopping.

- 908

The interface is connected and hence cannot be deleted.

- 909

The interface credentials have not been set.

- 910

This interface is already in the process of connecting.

- 911

An update of routing information on this interface is already in progress.

- 912

The interface configuration in invalid. There is already another interface that is connected to the same interface on the remote router.

- 913

A Remote Access Client attempted to connect over a port that was reserved for Routers only.

- 914

A Demand Dial Router attempted to connect over a port that was reserved for Remote Access Clients only.

- 915

The client interface with this name already exists and is currently connected.

- 916

The interface is in a disabled state.

- 917

The authentication protocol was rejected by the remote peer.

- 918

There are no authentication protocols available for use.

- 919

The remote computer refused to be authenticated using the configured authentication protocol. The line has been disconnected.

- 920

The remote account does not have Remote Access permission.

- 921

The remote account has expired.

- 922

The remote account is disabled.

- 923

The remote account is not permitted to logon at this time of day.

- 924

Access was denied to the remote peer because username and/or password is invalid on the domain.

- 925

There are no routing enabled ports available for use by this demand dial interface.

- 926

The port has been disconnected due to inactivity.

- 927

The interface is not reachable at this time.

- 928

The Demand Dial service is in a paused state.

- 929

The interface has been disconnected by the administrator.

- 930

The authentication server did not respond to authentication requests in a timely fashion.

- 931

The maximum number of ports allowed for use in the multilinked connection has been reached.

- 932

The connection time limit for the user has been reached.

- 933

The maximum limit on the number of LAN interfaces supported has been reached.

- 934

The maximum limit on the number of Demand Dial interfaces supported has been reached.

- 935

The maximum limit on the number of Remote Access clients supported has been reached.

- 936

The port has been disconnected due to the BAP policy.

- 937

Because another connection of your type is in use, the incoming connection cannot accept your connection request.

- 938

No RADIUS servers were located on the network.

- 939

An invalid response was received from the RADIUS authentication server. Make sure that the case-sensitive secret password for the RADIUS server is set correctly.

- 940

You do not have permission to connect at this time.

- 941

You do not have permission to connect using the current device type.

- 942

You do not have permission to connect using the selected authentication protocol.

- 943

BAP is required for this user.

- 944

The interface is not allowed to connect at this time.

- 945

The saved router configuration is incompatible with the current router.

- 946

RemoteAccess has detected older format user accounts that will not be migrated automatically. To migrate these manually, run XXXX.

- 948

The transport is already installed with the router.

- 949

Received invalid signature length in packet from RADIUS server.

- 950

Received invalid signature in packet from RADIUS server.

- 951

Did not receive signature along with EAPMessage from RADIUS server.

- 952

Received packet with invalid length or Id from RADIUS server.

- 953

Received packet with attribute with invalid length from RADIUS server.

- 954

Received invalid packet from RADIUS server.

- 955

Authenticator does not match in packet from RADIUS server.

Artículo 15: Troubleshoot L2TP/IPSec VPN client connection

15.0 Overview

This article describes how to troubleshoot L2TP/IPSec virtual private network (VPN) connection issues.

Applies to: Windows 10 - all editions

Original KB number: 325034

15.1 Summary

You must have an Internet connection before you can make an L2TP/IPSec VPN connection. If you try to make a VPN connection before you have an Internet connection, you may experience a long delay, typically 60 seconds, and then you may receive an error message that says there was no response or something is wrong with the modem or other communication device.

When you troubleshoot L2TP/IPSec connections, it's useful to understand how an L2TP/IPSec connection proceeds. When you start the connection, an initial L2TP packet is sent to the server, requesting a connection. This packet causes the IPSec layer on your computer to negotiate with the VPN server to set up an IPSec protected session (a security association). Depending on many factors including link speed, the IPSec negotiations may take from a few seconds to around two minutes. When an IPSec security association (SA) has been established, the L2TP session starts. When it starts, you receive a prompt for your name and password (unless the connection has been set up to connect automatically in Windows Millennium Edition.) If the VPN server accepts your name and password, the session setup completes.

A common configuration failure in an L2TP/IPSec connection is a misconfigured or missing certificate, or a misconfigured or missing preshared key. If the IPSec layer can't establish an encrypted session with the VPN server, it will fail silently. As a result, the L2TP layer doesn't see a response to its connection request. There will be a long delay, typically 60 seconds, and then you may receive an error message that says there was no response from the server or there was no response from the modem or communication device. If you receive this error message before you receive the prompt for your name and password, IPSec didn't establish its session. If that occurs, examine your certificate or preshared key configuration, or send the isakmp log to your network administrator.

A second common problem that prevents a successful IPSec session is using a Network Address Translation (NAT). Many small networks use a router with NAT functionality to share a single Internet address among all the computers on the network. The original version of IPSec drops a connection that goes through a NAT because it detects the NAT's address-mapping as packet tampering. Home networks frequently use a NAT. This blocks using L2TP/IPSec unless the client and the VPN gateway both support the emerging IPSec NAT-Traversal (NAT-T) standard. For more information, see the "NAT Traversal" section.

If the connection fails after you receive the prompt for your name and password, the IPSec session has been established and there's probably something wrong with your name and password. Other server settings may also be preventing a successful L2TP connection. In this case, send the PPP log to your administrator.

15.2 NAT Traversal

With the IPSec NAT-T support in the Microsoft L2TP/IPSec VPN client, IPSec sessions can go through a NAT when the VPN server also supports IPSec NAT-T. IPSec NAT-T is supported by Windows Server 2003. IPSec NAT-T is also supported by Windows 2000 Server with the L2TP/IPSec NAT-T update for Windows XP and Windows 2000.

For third-party VPN servers and gateways, contact your administrator or VPN gateway vendor to verify that IPSec NAT-T is supported.

15.3 More information

The configuration utility also provides a check box that enables IPSec logging. If you can't connect, and your network administrator or support personnel have asked you to provide them a connection log, you can enable IPSec logging here. When you do so, the log (Isakmp.log) is created in the C:\Program Files\Microsoft IPSec VPN folder. When you create a connection, also enable logging for the PPP processing in L2TP. To do so:

1. Right-click the Dialup Networking folder, and then click Properties.
2. Click the Networking tab, and then click to select the Record a log file for this connection check box.

The PPP log file is C:\Windows\Ppplog.txt. It's located in the C:\Program Files\Microsoft IPSec VPN folder.

For more information, see Default Encryption Settings for the Microsoft L2TP/IPSec Virtual Private Network Client.

Artículo 16: Network connectivity is lost

16.0 Overview

This article provides a solution to an error that occurs when you use the Network Protection feature in Windows Defender Exploit Guard in Audit or Block mode and a virtual private network (VPN).

Applies to: Windows 10 - all editions

Original KB number: 4560203

16.1 Symptoms

When using the Network Protection feature in Windows Defender Exploit Guard in Audit or Block mode and a virtual private network (VPN), you lose network connectivity and receive the General Failure error message when pinging an IP address.

16.2 Cause

This issue occurs because the current (4.12.x.x) antimalware platform update supporting the Network Protection feature is missing.

16.3 Solution

Install the latest (4.18.x.x) antimalware platform update as described here:

- Update for Windows Defender antimalware platform.
- Manage Windows Defender Antivirus updates and apply baselines.
- SCCM-Endpoint Protection: Enabling "Platform Update" for Microsoft Defender AV via SCCM ADR (Part 4).

16.4 Workaround

Set the following Group Policy to Not Configured:

Computer Configuration > Administrative Templates > Windows components > Windows Defender Antivirus > Windows Defender Exploit Guard > Network protection > Prevent users and apps from accessing dangerous websites

Artículo 17: Wireless network connectivity issues troubleshooting

17.0 Overview

[!div class="nextstepaction"]

Try our Virtual Agent - It can help you quickly identify and fix common Wireless technology issues.

Note:

Home users: This article is intended for support agents and IT professionals. For general troubleshooting, see Fix Wi-Fi connection issues in Windows.

Applies to: Windows 11 and supported versions of Windows 10

17.1 Overview

Use this guide to diagnose and resolve Wi-Fi connectivity problems on Windows clients. The guide covers the most common scenarios, including a missing Wi-Fi adapter or control, networks that don't appear in the connection list, failed connections, authentication errors, intermittent disconnects, and unreliable roaming.

The guide follows a symptom-first approach. Start by identifying your scenario, collect baseline evidence, and then use the Wi-Fi autoconnect state machine and Event Tracing for Windows (ETW) analysis to isolate the component and connection stage where the problem occurs. The end of this guide includes examples of the output of various diagnostic tools.

Important:

Before you reset the network stack, delete wireless profiles, remove the adapter or driver, or restart the device, collect the baseline state and record the reproduction time. These actions can remove evidence or temporarily change the behavior.

17.2 Scenarios

Use this article for the following scenarios:

- The Wi-Fi adapter or Wi-Fi control is missing.
- Windows doesn't display expected wireless networks.
- A connection attempt fails during association or authentication.
- The device connects but disconnects intermittently.
- Roaming between access points is slow or unreliable.
- The issue starts after an operating system, driver, firmware, policy, sleep, or resume event.

Note:

The ETW examples demonstrate a general strategy for navigating wireless component events. Event text and component behavior can differ by Windows version, wireless adapter, driver model, access point, and authentication method.

Start with the reported symptom

Symptom | Start with | Evidence to collect

Wi-Fi adapter or Wi-Fi control is missing | Confirm whether the adapter is present and enabled, and whether

the WLAN AutoConfig (WlanSvc) service is running. If WlanSvc is stopped, the Wi-Fi control is hidden and the netsh wlan commands report that the service isn't running. Record recent operating system, driver, firmware, BIOS, sleep, or resume changes. | Device Manager status, WlanSvc service state, netsh wlan show drivers, netsh wlan show interfaces, and relevant System events.

Expected networks aren't displayed | Confirm the hardware and software radio state, WLAN AutoConfig service state, supported bands, and whether other clients can see the same network. | netsh wlan show interfaces, netsh wlan show networks mode=bssid, and the WLAN AutoConfig operational log.

Connection or authentication fails | Determine whether the failure occurs during association or authentication. For enterprise authentication, also use Advanced troubleshooting 802.1X authentication. | Wireless network report, WLAN AutoConfig operational log, profile and policy details, and the failure timestamp.

Connection drops or roaming is unreliable | Record the time, network name, access point, signal conditions, and whether the device roamed before the disconnect. Correlate the client trace with access point or controller logs. | Wireless network report, ETW trace, adapter and driver details, and infrastructure logs.

Issue started after an update or resume | Compare the current driver and firmware versions with the versions recommended by the device or adapter manufacturer. Determine whether the behavior reproduces before making further changes. | Update history, driver version and date, firmware or BIOS version, power-state transition, and ETW trace.

Wi-Fi remains associated but network access fails | Verify that Wi-Fi association completed successfully, and then continue with TCP/IP, DHCP, DNS, proxy, or firewall troubleshooting. | IP configuration, route, DNS, and network connectivity evidence.

Check for known issues and recent changes

Before you collect an advanced trace:

- Review Windows release health for known issues that affect the installed Windows version.
- Review the device manufacturer's support information for wireless driver, firmware, and BIOS updates or known compatibility issues.
- Record changes to Windows, the wireless driver, firmware, security software, VPN software, wireless profiles, authentication policy, and access point configuration.
- If the issue affects multiple clients, compare affected and unaffected devices before changing client configuration.

17.3 Data collection

Collect baseline information

Run the following commands from an elevated command prompt:

```
netsh wlan show drivers
netsh wlan show interfaces
netsh wlan show networks mode=bssid
netsh wlan show profiles
netsh wlan show wlanreport
```

The mode=bssid option adds the BSSID, signal strength, channel, and radio type for each visible network, which helps identify band, channel, and coverage problems.

The wlanreport command generates an HTML report that summarizes recent wireless sessions, disconnect reasons, adapter information, and related events. The command displays the report location when it completes.

Also collect the following information:

- The exact date and time of each connection attempt or disconnect.
- The wireless adapter model, driver version, and driver date.
- The Windows build and recent update history.
- The network name, authentication method, and whether the profile comes from Group Policy, mobile device management, or the user.
- Events from Event Viewer > Applications and Services Logs > Microsoft > Windows > WLAN-AutoConfig > Operational.

Note:

Wireless reports and traces can contain device, adapter, and network identifiers. Handle the files according to your organization's privacy and data-handling requirements.

Collect support diagnostics

If you plan to contact Microsoft Support, use the TroubleShootingScript (TSS) wireless scenario. Download and extract the toolset, open an elevated PowerShell session in the TSS folder, and then run:

```
.\TSS.ps1 -Scenario NET_WLAN
```

The first run prompts you to accept the End User License Agreement. If the script is blocked from running, set the execution policy for the current process by running Set-ExecutionPolicy -ExecutionPolicy RemoteSigned -Scope Process.

For download instructions and requirements, see Introduction to TroubleShootingScript toolset (TSS). For other networking scenarios, see Collect data to analyze and troubleshoot Windows networking scenarios.

Collect an ETW trace

For a reproducible issue that requires advanced analysis, enter the following commands at an elevated command prompt. The trace doesn't start if the output folder doesn't exist, so create the folder first:

```
if not exist c:\tmp md c:\tmp
netsh trace start wireless_dbg capture=yes overwrite=yes maxsize=4096 tracefile=c:\tmp\wireless.etl
```

Note:

wireless_dbg is a legacy scenario that netsh trace show scenarios doesn't list, but it remains available. To review the providers that it enables, run netsh trace show scenario name=wireless_dbg. For new support cases, prefer the TSS NET_WLAN scenario.

1. Reproduce the issue and record the time of the connection attempt or disconnect.
1. Stop the trace:

```
netsh trace stop
```

1. Convert the trace to text if required:

```
netsh trace convert c:\tmp\wireless.etl
```

The collection creates wireless.cab, wireless.etl, and, after conversion, wireless.txt. See the example ETW capture.

17.4 Troubleshooting

The following table provides a high-level view of the main Wi-Fi components in Windows.

Wi-Fi component | Description

:::image type="content" source="media/wireless-network-connectivity-issues-troubleshooting/windows-connection-manager.png" alt-text="Windows Connection Manager icon." border="false"::: | Windows Connection Manager (Wcmsvc) processes user connection requests and coordinates connectivity across available network interfaces.

:::image type="content" source="media/wireless-network-connectivity-issues-troubleshooting/wlan-autoconfig-service.png" alt-text="WLAN AutoConfig service icon." border="false"::: | The WLAN AutoConfig service (WlanSvc) scans for wireless networks and manages wireless profiles and connectivity.

:::image type="content" source="media/wireless-network-connectivity-issues-troubleshooting/media-specific-module.png" alt-text="Media Specific Module icon." border="false"::: | The Media Specific Module (MSM) manages connection security, association, and authentication state.

:::image type="content" source="media/wireless-network-connectivity-issues-troubleshooting/native-wifi-stack.png" alt-text="Native Wi-Fi stack icon." border="false"::: | The Native Wi-Fi stack consists of drivers and wireless APIs that interact with wireless miniports and the user-mode WLAN AutoConfig service.

:::image type="content" source="media/wireless-network-connectivity-issues-troubleshooting/wireless-miniport.png" alt-text="Wireless miniport icon." border="false"::: | The wireless miniport driver communicates between the Windows wireless stack and the adapter hardware.

The Wi-Fi connection state machine has the following states:

- Reset
- Ihv_Configuring
- Configuring
- Associating
- Authenticating
- Connected
- Roaming
- Wait_For_Disconnected
- Disconnected

Standard Wi-Fi connections tend to transition between states such as:

- Connecting

Reset --> Ihv_Configuring --> Configuring --> Associating --> Authenticating --> Connected

- Disconnecting

Connected --> Roaming --> Wait_For_Disconnected --> Disconnected --> Reset

Filtering the ETW trace with the TextAnalysisTool (TAT) is an easy first step to determine where a failed connection setup is breaking down. A useful Wi-Fi filter file is included at the bottom of this article.

Use the FSM transition trace filter to see the connection state machine. You can see an example of this filter applied in the TAT at the bottom of this page.

An example of a good connection setup is:

```
44676                    [2]0F24.1020::?2018?-?09?-?17                    10:22:14.658
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Disconnected to State:
Reset
45473                    [1]0F24.1020::?2018?-?09?-?17                    10:22:14.667
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Reset to State:
Ihv_Configuring
45597                    [3]0F24.1020::?2018?-?09?-?17                    10:22:14.708
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Ihv_Configuring to
State: Configuring
46085                    [2]0F24.17E0::?2018?-?09?-?17                    10:22:14.710
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Configuring to State:
Associating
47393                    [1]0F24.1020::?2018?-?09?-?17                    10:22:14.879
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Associating to State:
Authenticating
49465                    [2]0F24.17E0::?2018?-?09?-?17                    10:22:14.990
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Authenticating to State:
Connected
```

An example of a failed connection setup is:

```
44676                    [2]0F24.1020::?2018?-?09?-?17                    10:22:14.658
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Disconnected to State:
Reset
45473                    [1]0F24.1020::?2018?-?09?-?17                    10:22:14.667
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Reset to State:
Ihv_Configuring
45597                    [3]0F24.1020::?2018?-?09?-?17                    10:22:14.708
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Ihv_Configuring to
State: Configuring
46085                    [2]0F24.17E0::?2018?-?09?-?17                    10:22:14.710
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Configuring to State:
Associating
```

```
47393                    [1]0F24.1020::?2018?-?09?-?17                    10:22:14.879
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Associating to State:
Authenticating
49465                    [2]0F24.17E0::?2018?-?09?-?17                    10:22:14.990
[Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State: Authenticating to State:
Roaming
```

By identifying the state at which the connection fails, you can focus more specifically in the trace on logs prior to the last known good state.

Examining \[Microsoft-Windows-WLAN-AutoConfig\] logs prior to the bad state change should show evidence of error. Often, however, the error is propagated up through other wireless components.

In many cases the next component of interest is the MSM, which lies just below Wlansvc.

The important components of the MSM include:

- Security Manager (SecMgr) - handles all pre and post-connection security operations.
- Authentication Engine (AuthMgr) - Manages 802.1x auth requests

Each of these components has its own individual state machines that follow specific transitions.

Enable the FSM transition, SecMgr Transition, and AuthMgr Transition filters in TextAnalysisTool for more detail.

Further to the preceding example, the combined filters look like the following command example:

```
[2] 0C34.2FF0::08/28/17-13:24:28.693 [Microsoft-Windows-WLAN-AutoConfig]FSM Transition
from State:
Reset to State: Ihv_Configuring
[2] 0C34.2FF0::08/28/17-13:24:28.693 [Microsoft-Windows-WLAN-AutoConfig]FSM Transition
from State:
Ihv_Configuring to State: Configuring
[1] 0C34.2FE8::08/28/17-13:24:28.711 [Microsoft-Windows-WLAN-AutoConfig]FSM Transition
from State:
Configuring to State: Associating
[0] 0C34.275C::08/28/17-13:24:28.902 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer
8A:15:14:B6:25:10 SecMgr Transition INACTIVE (1) --> ACTIVE (2)
[0] 0C34.275C::08/28/17-13:24:28.902 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer
8A:15:14:B6:25:10 SecMgr Transition ACTIVE (2) --> START AUTH (3)
[4] 0EF8.0708::08/28/17-13:24:28.928 [Microsoft-Windows-WLAN-AutoConfig]Port (14) Peer
0x186472F64FD2 AuthMgr Transition ENABLED  --> START_AUTH
[3] 0C34.2FE8::08/28/17-13:24:28.902 [Microsoft-Windows-WLAN-AutoConfig]FSM Transition
from State:
Associating to State: Authenticating
[1] 0C34.275C::08/28/17-13:24:28.960 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer
8A:15:14:B6:25:10 SecMgr Transition START AUTH (3) --> WAIT FOR AUTH SUCCESS (4)
[4] 0EF8.0708::08/28/17-13:24:28.962 [Microsoft-Windows-WLAN-AutoConfig]Port (14) Peer
```

```
0x186472F64FD2 AuthMgr Transition START_AUTH  --> AUTHENTICATING
[2] 0C34.2FF0::08/28/17-13:24:29.751 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer 8A:15:14:B6:25:10 SecMgr Transition WAIT FOR AUTH SUCCESS (7) --> DEACTIVATE (11)
[2] 0C34.2FF0::08/28/17-13:24:29.7512788 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer 8A:15:14:B6:25:10 SecMgr Transition DEACTIVATE (11) --> INACTIVE (1)
[2] 0C34.2FF0::08/28/17-13:24:29.7513404 [Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State:
Authenticating to State: Roaming
```

Note:

In the next to last line, the SecMgr transition suddenly deactivates:

\[2\] 0C34.2FF0::08/28/17-13:24:29.7512788 \[Microsoft-Windows-WLAN-AutoConfig\]Port\[13\] Peer 8A:15:14:B6:25:10 SecMgr Transition DEACTIVATE (11) --> INACTIVE (1)

This transition eventually propagates to the main connection state machine and causes the Authenticating phase to devolve to Roaming state. As before, focus on tracing prior to this SecMgr behavior to determine the reason for the deactivation.

Enabling the Microsoft-Windows-WLAN-AutoConfig filter shows more detail leading to the DEACTIVATE transition:

```
[3] 0C34.2FE8::08/28/17-13:24:28.902 [Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State:
Associating to State: Authenticating
[1] 0C34.275C::08/28/17-13:24:28.960 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer 8A:15:14:B6:25:10 SecMgr Transition START AUTH (3) --> WAIT FOR AUTH SUCCESS (4)
[4] 0EF8.0708::08/28/17-13:24:28.962 [Microsoft-Windows-WLAN-AutoConfig]Port (14) Peer 0x186472F64FD2 AuthMgr Transition START_AUTH  --> AUTHENTICATING
[0]0EF8.2EF4::?08/28/17-13:24:29.549 [Microsoft-Windows-WLAN-AutoConfig]Received Security Packet: PHY_STATE_CHANGE
[0]0EF8.2EF4::08/28/17-13:24:29.549 [Microsoft-Windows-WLAN-AutoConfig]Change radio state for interface = Intel(R) Centrino(R) Ultimate-N 6300 AGN :  PHY = 3, software state = on , hardware state = off )
[0] 0EF8.1174::?08/28/17-13:24:29.705 [Microsoft-Windows-WLAN-AutoConfig]Received Security Packet: PORT_DOWN
[0] 0EF8.1174::?08/28/17-13:24:29.705 [Microsoft-Windows-WLAN-AutoConfig]FSM Current state Authenticating , event Upcall_Port_Down
[0] 0EF8.1174:: 08/28/17-13:24:29.705 [Microsoft-Windows-WLAN-AutoConfig]Received IHV PORT DOWN, peer 0x186472F64FD2
[2] 0C34.2FF0::08/28/17-13:24:29.751 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer 8A:15:14:B6:25:10 SecMgr Transition WAIT FOR AUTH SUCCESS (7) --> DEACTIVATE (11)
[2] 0C34.2FF0::08/28/17-13:24:29.7512788 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer 8A:15:14:B6:25:10 SecMgr Transition DEACTIVATE (11) --> INACTIVE (1)
```

```
[2]     0C34.2FF0::08/28/17-13:24:29.7513404     [Microsoft-Windows-WLAN-AutoConfig]FSM
Transition from State:
Authenticating to State: Roaming
```

The trail backwards reveals a Port Down notification:

\[0\] 0EF8.1174:: 08/28/17-13:24:29.705 \[Microsoft-Windows-WLAN-AutoConfig\]Received IHV PORT DOWN, peer 0x186472F64FD2

Port events indicate changes closer to the wireless hardware. You can follow the trail by continuing to see the origin of this indication.

Continuing down from the MSM, the Native Wi-Fi stack passes requests to the wireless miniport driver. The stack presents the wireless adapter to TCP/IP and other protocols as an Ethernet (802.3) interface, so 802.11 frames are translated to 802.3 packets before they reach the protocol stack.

Note:

The [Microsoft-Windows-NWiFi] events in this example come from the legacy Native 802.11 miniport driver model. Current adapters use the WLAN Device Driver Interface (WDI) or, on Windows 11, the Wi-Fi Class Extension (WiFiCx) driver model. The connection stages are equivalent, but driver-level event names and provider details differ.

Enable trace filter for [Microsoft-Windows-NWifi]:

```
[3] 0C34.2FE8::08/28/17-13:24:28.902 [Microsoft-Windows-WLAN-AutoConfig]FSM Transition
from State:
Associating to State: Authenticating
[1]  0C34.275C::08/28/17-13:24:28.960  [Microsoft-Windows-WLAN-AutoConfig]Port[13]  Peer
8A:15:14:B6:25:10 SecMgr Transition START AUTH (3) --> WAIT FOR AUTH SUCCESS (4)
[4] 0EF8.0708::08/28/17-13:24:28.962 [Microsoft-Windows-WLAN-AutoConfig]Port (14) Peer
0x8A1514B62510 AuthMgr Transition START_AUTH  --> AUTHENTICATING
[0]0000.0000::?08/28/17-13:24:29.127 [Microsoft-Windows-NWiFi]DisAssoc: 0x8A1514B62510
Reason: 0x4
[0]0EF8.2EF4::?08/28/17-13:24:29.549       [Microsoft-Windows-WLAN-AutoConfig]Received
Security Packet: PHY_STATE_CHANGE
[0]0EF8.2EF4::08/28/17-13:24:29.549   [Microsoft-Windows-WLAN-AutoConfig]Change   radio
state for interface = Intel(R) Centrino(R) Ultimate-N 6300 AGN :  PHY = 3, software
state = on , hardware state = off )
[0]    0EF8.1174::?08/28/17-13:24:29.705    [Microsoft-Windows-WLAN-AutoConfig]Received
Security Packet: PORT_DOWN
[0]  0EF8.1174::?08/28/17-13:24:29.705  [Microsoft-Windows-WLAN-AutoConfig]FSM  Current
state Authenticating , event Upcall_Port_Down
[0] 0EF8.1174:: 08/28/17-13:24:29.705 [Microsoft-Windows-WLAN-AutoConfig]Received IHV
PORT DOWN, peer 0x186472F64FD2
[2] 0C34.2FF0::08/28/17-13:24:29.751 [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer
8A:15:14:B6:25:10 SecMgr Transition WAIT FOR AUTH SUCCESS (7) --> DEACTIVATE (11)
```

```
[2]  0C34.2FF0::08/28/17-13:24:29.7512788  [Microsoft-Windows-WLAN-AutoConfig]Port[13] Peer 8A:15:14:B6:25:10 SecMgr Transition DEACTIVATE (11) --> INACTIVE (1)
[2]    0C34.2FF0::08/28/17-13:24:29.7513404    [Microsoft-Windows-WLAN-AutoConfig]FSM Transition from State:
Authenticating to State: Roaming
```

In the trace, you see the line:

```
[0]0000.0000::?08/28/17-13:24:29.127 [Microsoft-Windows-NWiFi]DisAssoc: 0x8A1514B62510 Reason: 0x4
```

This line is followed by PHY_STATE_CHANGE and PORT_DOWN events after the access point (AP) at 8A:15:14:B6:25:10 sends a disassociation.

Decode the Reason value before you form a theory. The value comes from the IEEE 802.11 disassociation frame that the AP sent, so it identifies the condition that the AP reported. In this example, Reason: 0x4 means disassociated due to inactivity, so the investigation should focus on AP or controller inactivity and session timers, client power-saving behavior, and whether client traffic stopped reaching the AP. Other reason codes indicate different conditions, such as invalid credentials, incompatible connection parameters, or an AP that can't accept more clients.

Because the AP supplies the reason code, correlate it with logging from the indicated AP or wireless controller before you change the client configuration.

More information

- netsh wlan
- Advanced troubleshooting 802.1X authentication
- Data collection for troubleshooting 802.1X authentication
- Collect data to analyze and troubleshoot Windows networking scenarios
- Windows release health

17.5 ETW capture example

Note:

The following capture is a historical example that illustrates the collection output and state transitions. Timestamps, adapter names, and individual event text differ on current Windows 11 devices.

```
C:\tmp>netsh trace start wireless_dbg capture=yes overwrite=yes maxsize=4096 tracefile=c:\tmp\wireless.etl
Trace configuration:
-------------------------------------------------------------------
Status:             Running
Trace File:         C:\tmp\wireless.etl
Append:             Off
Circular:           On
Max Size:           4096 MB
Report:             Off
```

```
C:\tmp>netsh trace stop
Correlating traces ... done
Merging traces ... done
Generating data collection ... done
The trace file and additional troubleshooting information have been compiled as "c:\tmp\wireless.cab".
File location = c:\tmp\wireless.etl
Tracing session was successfully stopped.
C:\tmp>netsh trace convert c:\tmp\wireless.etl
Input file:  c:\tmp\wireless.etl
Dump file:   c:\tmp\wireless.txt
Dump format: TXT
Report file: -
Generating dump ... done
C:\tmp>dir
Volume in drive C has no label.
Volume Serial Number is 58A8-7DE5
Directory of C:\tmp
01/09/2019  02:59 PM    [DIR]          .
01/09/2019  02:59 PM    [DIR]          ..
01/09/2019  02:59 PM         4,855,952 wireless.cab
01/09/2019  02:56 PM         2,752,512 wireless.etl
01/09/2019  02:59 PM         2,786,540 wireless.txt
3 File(s)     10,395,004 bytes
2 Dir(s)  46,648,332,288 bytes free
```

17.6 Wi-Fi filter file example

Copy and paste all the lines in the following code block, and save them into a text file named wifi.tat. Load the filter file into TextAnalysisTool by selecting File > Load Filters.

```
<?xml version="1.0" encoding="utf-8" standalone="yes"?>
<TextAnalysisTool.NET version="2018-01-03" showOnlyFilteredLines="False">
<filters>
<filter enabled="n" excluding="n" description="" foreColor="000000" backColor="d3d3d3" type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-OneX]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff" type="matches_text" case_sensitive="n" regex="n" text="[Unknown]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff" type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-EapHost]" />
```

```
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[]***" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-Winsock-AFD]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-WinHttp]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-WebIO]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-Winsock-NameResolution]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-TCPIP]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-DNS-Client]"
/>
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-NlaSvc]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-Iphlpsvc-Trace]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-DHCPv6-Client]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-Dhcp-Client]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-NCSI]" />
<filter     enabled="y"     excluding="n"     description=""     backColor="90ee90"
type="matches_text" case_sensitive="n" regex="n" text="AuthMgr Transition" />
<filter enabled="y" excluding="n" description="" foreColor="0000ff" backColor="add8e6"
type="matches_text" case_sensitive="n" regex="n" text="FSM transition" />
<filter enabled="y" excluding="n" description="" foreColor="000000" backColor="dda0dd"
type="matches_text" case_sensitive="n" regex="n" text="SecMgr transition" />
<filter enabled="y" excluding="n" description="" foreColor="000000" backColor="f08080"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-NWiFi]" />
<filter enabled="y" excluding="n" description="" foreColor="000000" backColor="ffb6c1"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-WiFiNetworkManager]" />
```

```
<filter enabled="y" excluding="n" description="" foreColor="000000" backColor="dda0dd"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-WLAN-AutoConfig]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text"                    case_sensitive="n"                    regex="n"
text="[Microsoft-Windows-NetworkProfile]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-WFP]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[Microsoft-Windows-WinINet]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="[MSNT_SystemTrace]" />
<filter enabled="y" excluding="y" description="" foreColor="000000" backColor="ffffff"
type="matches_text" case_sensitive="n" regex="n" text="Security]Capability" />
</filters>
</TextAnalysisTool.NET>
```

17.7 TextAnalysisTool example

In the following example, the View settings are configured to Show Only Filtered Lines.

Artículo 18: Error 0xC004F074 when you activate Windows

18.0 Overview

This article helps fix the error 0xC004F074 that occurs when you activate Windows.

Applies to: Supported versions of Windows Server and Windows Client

Original KB number: 974998

When you try to activate Windows, you may get error 0xC004F074 and one of the following error messages:

- > 0xC004F074 with description "The Key Management Server (KMS) is unavailable"
- > Error: 0xC004F074 The Software Licensing Service reported that the product could not be activated. No Key Management Service (KMS) could be contacted. Please see the Application Event Log for additional information.

18.1 The Key Management Server (KMS) is unavailable

When trying to activate Windows 7 or Microsoft Windows Server 2008 R2 KMS client machines, you may get this error message:

0xC004F074 with description "The Key Management Server (KMS) is unavailable"

At the same time, the following entries may get logged in the KMS Event Log on the KMS client and the KMS host.

In the application event log on the KMS client, you see the following event:

```
Log Name: Application
Source: Microsoft-Windows-Security-SPP
Date:
Event ID: 12288
Task Category: None
Level: Information
Keywords: Classic
User: N/A
Computer:
Description:
The client has sent an activation request to the key management service machine.
Info:
0xC004F06C, 0x00000000, <KMS Host FQDN>:1688, 36f27b39-2fd5-440b-be67-a09996d27a38,
2010/09/29 17:52, 0, 2, 41760, 68531fb9-5511-4989-97be-d11a0f55633f, 5
```

In the application event log on the KMS host, you see the following event:

```
Log Name: Key Management Service
Source: Microsoft-Windows-Security-Licensing-SLC
Date:
```

```
Event ID: 12290
Task Category: None
Level: Information
Keywords: Classic
User: N/A
Computer:
Description:
An activation request has been processed.
Info:
0xC004F06C,5,<KMS      Client      name>,36f27b39-2fd5-440b-be67-a09996d27a38,2010/9/29
21:46,0,2,41520,68531fb9-5511-4989-97be-d11a0f55633f
```

This error can occur for one of the following reasons:

- A support version mismatch between the KMS client and the KMS host machine
- A time difference between the KMS client and the KMS host machine

Support version mismatch between KMS client and KMS host machine

Most commonly, we're seeing this error when the KMS host is running on Windows Server 2003 or Windows Server 2008 and the KMS client is Windows 7 or Windows Server 2008 R2. An update is needed for the KMS host running on Windows Server 2003 and an update is needed for the KMS host running on Windows Server 2008 to be able to activate KMS clients that are Windows 7 or Windows Server 2008 R2.

If you're running Windows Server 2008 as your KMS host, you need this update hotfix 968912.

Time difference between KMS client and KMS host machine

The error 0xC004F06C listed in the info section may occur if the difference between system time on the client computer and the system time on the KMS host is more than 4 hours. We recommend that you use a Network Time Protocol (NTP) time source or the Active Directory service to synchronize the time between computers. Time is coordinated between the KMS host and the client computer in Coordinated Universal Time (UTC).

Make sure that the system time on the client and the KMS host is the same. The time zone set on the client computer doesn't affect the activation since it's based on UTC.

Run the w32tm /resync command to resync the time on the client.

18.2 No Key Management Service (KMS) could be contacted

When you try to activate Windows by using the Slmgr /ato command, you receive error code 0xC004F074 with the following error message:

Error: 0xC004F074 The Software Licensing Service reported that the product could not be activated. No Key Management Service (KMS) could be contacted. Please see the Application Event Log for additional information.

This error occurs for one of the following reasons:

- The Software Protection Platform Service (sppsvc service) on the KMS host has stopped running.

- There are networking issues between the KMS client and the KMS host server. For example, TCP 1688 traffic is blocked between the KMS client and the KMS host server.
- There's an incorrect or old KMS host server record in the Domain Name System (DNS).

Sppsvc service on the KMS host has stopped running

Check if the sppsvc service is running on the KMS server. If the service is stopped, start it.

Networking issues between the KMS client and the KMS host server

Open port 1688 between the KMS client and KMS host server, and use the Test-NetConnection PowerShell cmdlet to check if the port is open between the client and server. Here's an example:

```
Test-NetConnection -ComputerName <KMS Host Server> -Port 1688
ComputerName            : <KMS host server>
RemoteAddress           : <KMS host server IP address>
RemotePort              : 1688
InterfaceAlias          : Wi-Fi
SourceAddress           : <Client machine IP address>
PingSucceeded           : True
PingReplyDetails (RTT) : 0 ms
TcpTestSucceeded        : False
```

Review the TcpTestSucceeded output parameter. If it's False, it means that port 1688 is blocked between the KMS client and the KMS server.

Incorrect or old KMS host server record in DNS

Verify the KMS DNS record in the DNS pointing to an incorrect or old KMS server in the environment by using the following steps:

1. Open the DNS management console.
2. Select the _tcp folder under your domain name folder, and search for the _VLMCS SRV record.
3. Check if the correct KMS host server name is present in the _VLMCS SRV record.
4. Verify the host record of the KMS host server by going to the domain name folder and verifying the Host A record. Change the IP address to point to the new KMS server host if it's incorrect.

18.3 References

Resolve Windows activation error codes

18.4 Data collection

If you need assistance from Microsoft support, we recommend you collect the information by following the steps mentioned in Gather information by using TSS for deployment-related issues.

Artículo 19: Can't use Azure Multi-Factor Authentication to sign in to cloud services after you lose your phone or the phone number changes

19.0 Overview

Original product version: Cloud Services (Web roles/Worker roles), Microsoft Entra ID, Microsoft Intune, Azure Backup, Office 365 Identity Management

Original KB number: 2834954

19.1 Symptoms

Assume that you're a Microsoft cloud services admin who has Microsoft Azure Multi-Factor Authentication enabled. If you lose your phone or your phone number has changed, you can't sign in to your cloud services account (such as Office 365, Azure, or Microsoft Intune) because you didn't receive the text message or voice call from the Multi-Factor Authentication service.

19.2 Resolution

Ask another cloud services admin to reset your Multi-Factor Authentication settings. To do this, the admin should follow these steps:

1. Sign in to the cloud service portal as an admin.
2. Go to https://account.activedirectory.windowsazure.com/usermanagement/multifactorverification.aspx.
3. Select the check box for the admin account whose Multi-Factor Authentication settings you want to reset.
4. Select Manage user settings.
5. Select the Require selected users to provide contact methods again check box, and then select Save.

Artículo 20: Troubleshoot Azure Multi-Factor Authentication issues

20.0 Overview

This article contains information to help you troubleshoot common issues that you may encounter when you use Windows Multi-Factor Authentication for Microsoft Office 365 or Microsoft Azure.

Original product version: Cloud Services (Web roles/Worker roles), Microsoft Entra ID, Microsoft Intune, Azure Backup, Office 365 Identity Management

Original KB number: 2937344

20.1 Summary

Scenario | Content

You don't receive a text or voice call that contains the verification code for Azure Multi-Factor Authentication | 2834956

"Sorry! We can't process your request" error when you try to set up security verification settings for Azure Multi-Factor Authentication | 2909939

Can't use Azure Multi-Factor Authentication to sign in to cloud services after you lose your phone or the phone number changes | 2834954

"We did not receive the expected response" error message when you try to sign in by using Azure Multi-Factor Authentication | 2834968

"Account verification system is having trouble" error message when you try to sign in by using a work or school account | 2834966

Can't sign in to an Office app by using a work or school account | 2834958

You can't sign in to Office 365, Azure, or Intune | 2412085

Artículo 21: You don't receive a text or voice call that contains the verification code for Microsoft Entra multifactor authentication

21.0 Overview

Original product version: Cloud Services (Web roles/Worker roles), Microsoft Entra ID, Microsoft Intune, Azure Backup, Office 365 Identity Management

Original KB number: 2834956

21.1 Symptoms

Consider the following scenario:

- You're a global admin who has Microsoft Entra multifactor authentication (MFA) enabled
- You don't receive the text message or voice call that contains your verification code.

In this scenario, you can't sign in to your work or school account, such as Office 365, Azure, or Microsoft Intune.

21.2 Resolution

To fix this problem, follow these steps:

1. If you have set up other options for security verification, select Other verification options, and then try again by selecting a different option. Also, make sure that your phone numbers are correct in your user account settings.
2. Ask another global admin to confirm whether your phone numbers are set correctly in your user settings.

If steps 1 and 2 don't resolve the problem, your user account may be blocked from using Microsoft Entra multifactor authentication. To check whether your user account is blocked, ask a global admin for your Microsoft cloud service to perform the following steps:

If you have a Microsoft Entra multifactor authentication or Microsoft Entra ID P1 or P2 subscription

1. Go to the Azure portal, and then open Microsoft Entra ID.
2. If you want to change the default active directory, click Manage tenants, choose the active directory, and then click Switch.
3. Choose Users, open the profile of the user that has the problem.
4. Check whether the Block sign in is enabled. If yes, disable the option.

If you have Office 365 and don't have a Microsoft Entra multifactor authentication or Microsoft Entra ID P1 or P2 subscription, contact Office 365 Support.

Artículo 22: Error (We could not verify your account) when a new user tries to reset password in Azure, Office 365, or Intune

22.0 Overview

Original product version: Cloud Services (Web roles/Worker roles), Microsoft Entra ID, Microsoft Intune, Azure Backup, Office 365 Identity Management

Original KB number: 2951274

22.1 Symptoms

When a new user tries to reset password in Microsoft Azure, Microsoft Office 365, or Microsoft Intune, the user receives the following error message:

Reset your password

We could not verify your account

If you'd like, we can contact an administrator in your organization to reset your password for you..

22.2 Resolution

Assign a Microsoft Entra ID P1 or P2 license to the user. Users must have a Microsoft Entra ID P1 or P2 license to be able to reset their own password.

Artículo 23: The user name or password is incorrect error when running Azure Active Directory Sync tool Configuration Wizard

23.0 Overview

Original product version: Cloud Services (Web roles/Worker roles), Microsoft Entra ID, Microsoft Intune, Office 365 Identity Management

Original KB number: 2965539

23.1 Symptoms

When you run the Azure Active Directory Sync tool Configuration Wizard, you receive the following error message:

The user name or password is incorrect.

Additionally, event ID 611 is logged to the Application log in Event Viewer:

Event ID: 611

Level: Information

Source: Directory Synchronization

Description:

Password synchronization failed for domain: ChildDomain.Contoso.Com. Details:

Microsoft.Online.PasswordSynchronization.SynchronizationManagerException: Unable to open connection to domain: ChildDomain.Contoso.Com. Error: An exception occurred while attempting to locate a domain controller for domain ChildDomain.Contoso.Com. ---> Microsoft.Online.PasswordSynchronization.DirectoryReplicationServices.DrsCommunicationException: An exception occurred while attempting to locate a domain controller for domain ChildDomain.Contoso.Com. ---> System.Security.Authentication.AuthenticationException: The user name or password is incorrect.

---> System.Runtime.InteropServices.COMException: The user name or password is incorrect.

23.2 Cause

This problem occurs if the enterprise admin account credentials that are specified in the wizard are not unique in the Active Directory forest. Password mismatches between two or more identically named accounts in multi-domain forests can cause the wizard to fail.

Consider the following example scenario:

- Contoso\admin is the enterprise admin account that's specified in the Azure Active Directory Sync tool Configuration Wizard.
- Contoso\admin and Fabrikam\admin are two accounts that have the same name but that exist in different domains.
- Each account has a different password.

In this scenario, the password of Contoso\admin is used for all domains in the Active Directory forest during

the configuration process. For example, if the password is "Password1," "Password1" is used for Fabrikam\admin. This causes the wizard to fail.

23.3 Resolution

To resolve this problem, do one of the following:

- Create an enterprise admin account in which the value of the sAMAccountName attribute is unique and does not exist in each domain.
- Update the passwords of all accounts that have identical names so that the password is the same for all those accounts.

Artículo 24: MFA fails because five registered devices use authenticator apps

24.0 Overview

This article discusses how to resolve a scenario in which you can't set up multifactor authentication (MFA) because you already registered five devices to use authenticator apps.

24.1 Symptoms

When you try to set up MFA, you receive the following error message:

You cannot have more than 5 hardware tokens or authenticator apps. Please delete one or more of your authenticator apps and then add a new authenticator app. If you need to delete your hardware token, please contact your administrator. Disabling a hardware token will not allow you to add new authenticator app.

You have too many devices registered.

24.2 Cause

You previously set up five different phones or other devices to be registered for MFA by using an authenticator app. As a result, the maximum allowed number of device tokens (5) are already persisted in the StrongAuthenticationPhoneAppDetail property of your directory user object.

24.3 Solution 1: Delete the sign-in methods directly in a web browser

To delete the device tokens, you can delete the sign-in methods from your security settings directly within a web browser. However, if you aren't an administrator, or you aren't the only administrator for your Microsoft Entra ID, you must first have someone else (the administrator or another administrator user) set the requirement for re-registering MFA in the procedure in the following section.

Part 1: Have your administrator or another administrator user set the MFA re-registration requirement

Note:

This procedure isn't required if you're the only administrator for your Microsoft Entra ID.

1. In the Azure portal, search for and select Microsoft Entra ID.
1. In the Microsoft Entra navigation pane, locate the Manage heading, and then select Users.
1. In the list of Microsoft Entra users, select the Display name of the user.
1. In the navigation pane for the Microsoft Entra user, locate the Manage heading, and then select Authentication methods.
1. In the Microsoft Entra user menu, select Require re-register multifactor authentication.

Part 2: Delete some or all of your sign-in methods

You can delete the device tokens by deleting the corresponding sign-in methods. Follow these steps:

1. To view your sign-in methods, go to .

For example, the sign-in method list might include a phone method that's associated with a phone number,

and an authenticator app method that's associated with a particular device. For more information, see What authentication and verification methods are available in Microsoft Entra ID?

1. Delete any or all five of the sign-in methods that are listed.

Warning:

If you try to delete a passwordless sign-in method, you receive the following error message in a dialog box that contains the Sign in and Cancel buttons:

> Delete authenticator app

>

> To delete this authenticator app, you need to sign in with two-factor authentication.

To be able to delete the passwordless sign-in method, set up another two-factor authentication method (such as a phone call or an SMS text message) beforehand. Then, when you retry deleting the passwordless sign-in method, use that two-factor authentication method to sign in.

24.4 Solution 2: Delete the authenticator apps by using Microsoft Graph

Global Administrators can delete a user's authenticator app by using the Microsoft Graph API. In some instances, the Microsoft Graph API is the only available solution (for example, if you're using the security defaults). To use this solution, you or your Global Administrator should sign in to Graph Explorer as a Global Administrator, and then follow these steps:

1. In the query area of Graph Explorer, take the following actions:
1. In the HTTP methods list, select GET.
1. In the query box, enter https://graph.microsoft.com/beta/users//authentication/microsoftAuthenticatorMethods. Replace the placeholder of the user principal name (UPN) with the UPN of the user whose authentication app has to be deleted.
1. Select the Run query button.

Warning:

If you experience a permission error when run the query, follow these steps to get the necessary permission:

1. Select the Modify permissions tab.

1. Select the Open the permissions panel link.

1. In the permissions panel, expand the UserAuthenticationMethod node, and then select the UserAuthenticationMethod.ReadWrite.All permission.

1. Select the Consent button.

After you complete these steps, try again to run the query.

In the response pane, the Response header tab displays JSON code that shows the authenticator method information. In the following example code snippet, the user is associated with a total of one authenticator method:

```
{
```

```
"@odata.context":
"https://graph.microsoft.com/beta/$metadata#users('user%40contoso.com')/authentication
/microsoftAuthenticatorMethods",
"value": [
{
"id": "01234567-89ab-cdef-0123-456789abcdef",
"displayName": "SM-G973F",
"deviceTag": "SoftwareTokenActivated",
"phoneAppVersion": "6.2102.0762",
"createdDateTime": null
}
]
}
```


1. In the response pane's Response header tab, copy and save the id property (a GUID) of each authenticator method that you want to delete.

1. In the query area, set HTTP methods to DELETE, and set Query box to https://graph.microsoft.com/beta/users//authentication/microsoftAuthenticatorMethods/. Enter the UPN and authenticator GUID to replace the placeholder values.

1. Select the Run query button. If this deletion query successfully deletes the authenticator app, the status message "No Content - 204 - \" appears.

1. Repeat steps 2-4 for each of the authenticator apps that you want to delete.