

## CONTENTS

- Prerequisites
- Step 1 — Installing and Configuring Nginx-RTMP
- Step 2 — Sending Video to Your RTMP Server
- Step 3 — Streaming Video to Your Server via OBS (Optional)
- Step 4 — Adding Monitoring to Your Configuration (Optional)
- Step 5 — Creating Modern Streams for Browsers (Optional)
- Conclusion

## RELATED

[How To Install nginx on CentOS 6 with yum](#)  
[View ↗](#)

[Initial Server Setup with Ubuntu 12.04](#)  
[View ↗](#)

// Tutorial //

## How To Set Up a Video Streaming Server using Nginx-RTMP on Ubuntu 20.04

Published on January 7, 2022

Ubuntu Ubuntu 20.04 Nginx



By [Alex Garnett](#)  
 Senior DevOps Technical Writer



**Not using Ubuntu 20.04?**  
 Choose a different version or distribution.

Ubuntu 20.04 ▾

### Introduction

There are many use cases for streaming video. Service providers such as [Twitch](#) are very popular for handling the web discovery and community management aspects of streaming, and free software such as [OBS Studio](#) is widely used for combining video overlays from multiple different stream sources in real time. While these platforms are very powerful, in some cases you may want to be able to host a stream that does not rely on other service providers.

In this tutorial, you will learn how to configure the Nginx web server to host an independent RTMP video stream that can be linked and viewed in different applications. RTMP, the [Real-Time Messaging Protocol](#), defines the fundamentals of most internet video streaming. You will also learn how to host HLS and DASH streams that support more modern platforms using the same technology.

### Prerequisites

To complete this guide, you will need:

- An Ubuntu 20.04 server and a non-root user with sudo privileges. You can learn more about how to set up a user with these privileges in our [Initial Server Setup with Ubuntu 20.04](#) guide.
- Nginx installed, following [How To Install Nginx on Ubuntu 20.04](#).

This tutorial will use the placeholder domain name `your_domain` for URLs and hostnames. Substitute this with your own domain name or IP address as you work through the tutorial.


### Step 1 – Installing and Configuring Nginx-RTMP

Most modern streaming tools support the RTMP protocol, which defines the basic parameters of an internet video stream. The Nginx web server includes a module that allows you to provide an RTMP stream with minimal configuration from a dedicated URL, just like it provides HTTP access to web pages by default. The Nginx RTMP module isn't included automatically with Nginx, but on Ubuntu 20.04 and most other Linux distributions you can install it as an additional package.

Begin by running the following commands as a non-root user to update your package listings and install the Nginx module:

```
$ sudo apt update
$ sudo apt install libnginx-mod-rtmp
```

Copy



## Popular Topics

- Ubuntu
- Linux Basics
- JavaScript
- React
- Python
- Security
- MySQL
- Docker
- Kubernetes
- [Browse all topic tags](#)

[Free Managed Hosting →](#)[All tutorials →](#)

## Questions

- [Q&A Forum](#)
- [Ask a question](#)
- [DigitalOcean Support](#)

Installing the module won't automatically start providing a stream. You'll need to add a configuration block to your Nginx configuration file that defines where and how the stream will be available.

Using `nano` or your favorite text editor, open Nginx's main configuration file, `/etc/nginx/nginx.conf`, and add this configuration block to the end of the file:

```
$ sudo nano /etc/nginx/nginx.conf
```

Copy

```
/etc/nginx/nginx.conf

...
rtmp {
    server {
        listen 1935;
        chunk_size 4096;
        allow publish 127.0.0.1;
        deny publish all;

        application live {
            live on;
            record off;
        }
    }
}
```

- `listen 1935` means that RTMP will be listening for connections on port 1935, which is standard.
- `chunk_size 4096` means that RTMP will be sending data in 4KB blocks, which is also standard.
- `allow publish 127.0.0.1` and `deny publish all` mean that the server will only allow video to be published from the same server, to avoid any other users pushing their own streams.
- `application live` defines an application block that will be available at the `/live` URL path.
- `live on` enables live mode so that multiple users can connect to your stream concurrently, a baseline assumption of video streaming.
- `record off` disables Nginx-RTMP's recording functionality, so that all streams are not separately saved to disk by default.

Save and close the file. If you are using `nano`, press `ctrl+x`, then when prompted, `y` and Enter.

This provides the beginning of your RTMP configuration. By default, it listens on port `1935`, which means you'll need to open that port in your firewall. If you configured `ufw` as part of your initial server setup run the following command.

```
$ sudo ufw allow 1935/tcp
```

Copy

Now you can reload Nginx with your changes:

```
$ sudo systemctl reload nginx.service
```

Copy

You should now have a working RTMP server. In the next section, we'll cover streaming video to your RTMP server from both local and remote sources.

## Step 2 – Sending Video to Your RTMP Server

There are multiple ways to send video to your RTMP server. One option is to use `ffmpeg`, a popular command line audio-video utility, to play a video file directly on your server. If you don't have a video file already on the server, you can download one using `youtube-dl`, a command line tool for capturing video from streaming platforms like YouTube. In order to use `youtube-dl`, you'll need an up to date Python installation on your server as well.

First, install Python and its package manager, `pip`:

```
$ sudo apt install python3-pip
```

Copy

Next, use `pip` to install `youtube-dl`:

```
$ sudo pip install youtube-dl
```

Copy

Now you can use `youtube-dl` to download a video from YouTube. If you don't have one in mind, try this video, introducing DigitalOcean's App Platform:

```
$ youtube-dl https://www.youtube.com/watch?v=iom_nhyQIYk
```

Copy

You'll see some output as `youtube-dl` combines the video and audio streams it's downloading back into a single file – this is normal.

### Output

```
[youtube] iom_nhyQIYk: Downloading webpage
WARNING: Requested formats are incompatible for merge and will be merged into mkv.
[download] Destination: Introducing App Platform by Digitalocean-iom_nhyQIYk.f137.mp4
[download] 100% of 32.82MiB in 08:40
[download] Destination: Introducing App Platform by Digitalocean-iom_nhyQIYk.f251.webm
[download] 100% of 1.94MiB in 00:38
[ffmpeg] Merging formats into "Introducing App Platform by Digitalocean-iom_nhyQIYk.mkv"
Deleting original file Introducing App Platform by Digitalocean-iom_nhyQIYk.f137.mp4 (pass -k to
Deleting original file Introducing App Platform by Digitalocean-iom_nhyQIYk.f251.webm (pass -k to
```

You should now have a video file in your current directory with a title like `Introducing App Platform by DigitalOcean-iom_nhyQIYk.mkv`. In order to stream it, you'll want to install `ffmpeg`:

```
$ sudo apt install ffmpeg
```

Copy

And use `ffmpeg` to send it to your RTMP server:

```
$ ffmpeg -re -i "Introducing App Platform by DigitalOcean-iom_nhyQIYk.mkv" -c:v copy -c:a aac -ar 44100 -ac 1 -f flv rtmp://localhost/live/stream
```

Copy

This `ffmpeg` command is doing a few things to prepare the video for a streaming-friendly format. This isn't an `ffmpeg` tutorial, so you don't need to examine it too closely, but you can understand the various options as follows:

- `-re` specifies that input will be read at its native framerate.
- `-i "Introducing App Platform by DigitalOcean-iom_nhyQIYk.mkv"` specifies the path to our input file.
- `-c:v` is set to `copy`, meaning that you're copying over the video format you got from YouTube natively.
- `-c:a` has other parameters, namely `aac -ar 44100 -ac 1`, because you need to resample the audio to an RTMP-friendly format. `aac` is a widely supported audio codec, `44100` hz is a common frequency, and `-ac 1` specifies the first version of the AAC spec for compatibility purposes.
- `-f flv` wraps the video in an `flv` format container for maximum compatibility with RTMP.

The video is sent to `rtmp://localhost/live/stream` because you defined the `live` configuration block in Step 1, and `stream` is an arbitrarily chosen URL for this video.

**Note:** You can learn more about `ffmpeg` options from [ffmprovisr](#), a community-maintained catalog of `ffmpeg` command examples, or refer to the [official documentation](#).

While `ffmpeg` is streaming the video, it will print timecodes:

```
Output
frame= 127 fps= 25 q=-1.0 size= 405kB time=00:00:05.00 bitrate= 662.2kbits/s speed=frame=
```

Copy

This is standard `ffmpeg` output. If you were converting video to a different format, these might be helpful in order to understand how efficiently the video is being resampled, but in this case, you just want to see that it's being played back consistently. Using this sample video, you should get exact `fps= 25` increments.

While `ffmpeg` is running, you can connect to your RTMP stream from a video player. If you have `VLC`, `mpv`, or another media player installed locally, you should be able to view your stream by opening the URL `rtmp://your_domain/live/stream` in your media player. Your stream will terminate after `ffmpeg` has finished playing the video. If you want it to keep looping indefinitely, you can add `-stream_loop -1` to the beginning of your `ffmpeg` command.

**Note:** You can also stream directly to, for example, Facebook Live using `ffmpeg` without needing to use Nginx-RTMP at all by replacing `rtmp://localhost/live/stream` in your `ffmpeg` command with `rtmps://live-api.s.facebook.com:443/rtmp/your-facebook-stream-key`. YouTube uses URLs like `rtmp://a.rtmp.youtube.com/live2`. Other streaming providers that can consume RTMP streams should behave similarly.

Now that you've learned to stream static video sources from the command line, you'll learn how to stream video from dynamic sources using OBS on a desktop.

### Step 3 – Streaming Video to Your Server via OBS (Optional)

Streaming via `ffmpeg` is convenient when you have a prepared video that you want to play back, but live streaming can be much more dynamic. The most popular software for live streaming is [OBS](#), or Open Broadcaster Software – it is free, open source, and very powerful.

OBS is a desktop application, and will connect to your server from your local computer.

After installing OBS, configuring it means customizing which of your desktop windows and audio sources you want to add to your stream, and then adding credentials for a streaming service. This tutorial will not be covering your streaming configuration, as it is down to preference, and by default, you can have a working demo by just streaming your entire desktop. In order to set your streaming service credentials, open OBS' settings menu, navigate to the *Stream* option and input the following options:

```
Streaming Service: Custom
Server: rtmp://your_domain/live
Play Path/Stream Key: obs_stream
```

`obs_stream` is an arbitrarily chosen path – in this case, your video would be available at `rtmp://your_domain/live/obs_stream`. You do not need to enable authentication, but you do need to add an additional entry to the IP whitelist that you configured in Step 1.

Back on the server, open Nginx's main configuration file, `/etc/nginx/nginx.conf`, and add an additional `allow publish` entry for your local IP address. If you don't know your local IP address, it's

best to just go to a site like [What's my IP](#) which can tell you where you accessed it from:

```
$ sudo nano /etc/nginx/nginx.conf
```

Copy

```
/etc/nginx/nginx.conf
```

```
...  
    allow publish 127.0.0.1;  
    allow publish your_local_ip_address;  
    deny publish all;  
...
```

Save and close the file, then reload Nginx:

```
$ sudo systemctl reload nginx.service
```

Copy

You should now be able to close OBS' settings menu and click [Start Streaming](#) from the main interface! Try viewing your stream in a media player as before. Now that you've seen the fundamentals of streaming video in action, you can add a few other features to your server to make it more production-ready.

## Step 4 – Adding Monitoring to Your Configuration (Optional)

Now that you have Nginx configured to stream video using the Nginx-RTMP module, a common next step is to enable the RTMP statistics page. Rather than adding more and more configuration details to your main `nginx.conf` file, Nginx allows you to add per-site configurations to individual files in a subdirectory called `sites-available/`. In this case, you'll create one called `rtmp`:

```
$ sudo nano /etc/nginx/sites-available/rtmp
```

Copy

Add the following contents:

```
/etc/nginx/sites-available/rtmp
```

```
server {  
    listen 8080;  
    server_name localhost;  
  
    # rtmp stat  
    location /stat {  
        rtmp_stat all;  
        rtmp_stat_stylesheet stat.xsl;  
    }  
    location /stat.xsl {  
        root /var/www/html/rtmp;  
    }  
  
    # rtmp control  
    location /control {  
        rtmp_control all;  
    }  
}
```

Save and close the file. The `stat.xsl` file from this configuration block is used to style and display an RTMP statistics page in your browser. It is provided by the `libnginx-mod-rtmp` library that you installed earlier, but it comes zipped up by default, so you will need to unzip it and put it in the `/var/www/html/rtmp` directory to match the above configuration. Note that you can find additional information about any of these options in the [Nginx-RTMP documentation](#).

Create the `/var/www/html/rtmp` directory, and then uncompress the `stat.xsl.gz` file with the following commands:

```
$ sudo mkdir /var/www/html/rtmp  
$ sudo gunzip -c /usr/share/doc/libnginx-mod-rtmp/examples/stat.xsl.gz > /var/www/html/rtmp/sta
```

Copy

Finally, to access the statistics page that you added, you will need to open another port in your firewall. Specifically, the `listen` directive is configured with port `8080`, so you will need to add a rule to access Nginx on that port. However, you probably don't want others to be able to access your stats page, so it's best only to allow it for your own IP address. Run the following command:

```
$ sudo ufw allow from your_ip_address to any port http-alt
```

Copy

Next, you'll need to activate this new configuration. Nginx's convention is to create symbolic links (like shortcuts) from files in `sites-available/` to another folder called `sites-enabled/` as you decide to enable or disable them. Using full paths for clarity, make that link:

```
$ sudo ln -s /etc/nginx/sites-available/rtmp /etc/nginx/sites-enabled/rtmp
```

Copy

Now you can reload Nginx again to process your changes:

```
$ sudo systemctl reload nginx.service
```

Copy

You should now be able to go to `http://your_domain:8080/stat` in a browser to see the RTMP statistics page. Visit and refresh the page while streaming video and watch as the stream statistics change.

You've now seen how to monitor your video stream and push it to third party providers. In the final section, you'll learn how to provide it directly in a browser without the use of third party streaming platforms or standalone media player apps.

## Step 5 – Creating Modern Streams for Browsers (Optional)

As a final step, you may want to add support for newer streaming protocols so that users can stream video from your server using a web browser directly. There are two protocols that you can use to create HTTP-based video streams: Apple's [HLS](#) and MPEG [DASH](#). They both have advantages and disadvantages, so you will probably want to support both.

The Nginx-RTMP module supports both standards. To add HLS and DASH support to your server, you will need to modify the `rtmp` block in your `nginx.conf` file. Open `/etc/nginx/nginx.conf` using `nano` or your preferred editor, then add the following highlighted directives:

```
$ sudo nano /etc/nginx/nginx.conf Copy
```

`...  
rtmp {  
 server {  
 ...  
 application live {  
 live on;  
 record off;  
 hls on;  
 hls_path /var/www/html/stream/hls;  
 hls_fragment 3;  
 hls_playlist_length 60;  
  
 dash on;  
 dash_path /var/www/html/stream/dash;  
 }  
 }  
...  
}`

Save and close the file. Next, add this to the bottom of your `sites-available/rtmp`:

```
$ sudo nano /etc/nginx/sites-available/rtmp Copy
```

`...  
server {  
 listen 8088;  
  
 location / {  
 add_header Access-Control-Allow-Origin *;  
 root /var/www/html/stream;  
 }  
}  
  
types {  
 application/dash+xml mpd;  
}`

**Note:** The `Access-Control-Allow-Origin *` header enables *CORS*, or [Cross-Origin Resource Sharing](#), which is disabled by default. This communicates to any web browsers accessing data from your server that the server may load resources from other ports or domains. CORS is needed for maximum compatibility with [HLS](#) and [DASH](#) clients, and a common configuration toggle in many other web deployments.

Save and close the file. Note that you're using port `8088` here, which is another arbitrary choice for this tutorial to avoid conflicting with any services you may be running on port 80 or 443. You'll want to open that port in your firewall for now too:

```
$ sudo ufw allow 8088/tcp Copy
```

Finally, create a `stream` directory in your web root to match the configuration block, so that Nginx can generate the necessary files for HLS and DASH:

```
$ sudo mkdir /var/www/html/stream Copy
```

Reload Nginx again:

```
$ sudo systemctl reload nginx Copy
```

You should now have an HLS stream available at `http://your_domain:8088/hls/stream.m3u8` and a DASH stream available at `http://your_domain:8088/dash/stream.mpd`. These endpoints will generate any necessary metadata on top of your RTMP video feed in order to support modern APIs.

## Conclusion

The configuration options that you used in this tutorial are all documented in the [Nginx RTMP Wiki](#)

[page](#). Nginx modules typically share common syntax and expose a very large set of configuration options, and you can review their documentation to change any of your settings from here.

Nearly all internet video streaming is implemented on top of RTMP, HLS, and DASH, and by using the approach that you have explored in this tutorial, you can provide your stream via other broadcasting services, or expose it any other way you choose. Next, you could look into configuring Nginx as a [reverse proxy](#) in order to make some of these different video endpoints available as subdomains.

If you've enjoyed this tutorial and our broader community, consider checking out our DigitalOcean products which can also help you achieve your development goals.

[Learn more here →](#)

## Get \$200 to try DigitalOcean - and do all the below for free!

Build applications, host websites, run open source software, learn cloud computing, and more – every cloud resource you need. If you've never tried DigitalOcean's products or services before, we'll cover your first \$200 in the next 60 days.

[Sign up now to activate this offer →](#)

### About the authors



Alex Garnett Author

Senior DevOps Technical Writer

Still looking for an answer?

[Ask a question](#)

[Search for more help](#)

Was this helpful?

[Yes](#)

[No](#)



### Comments

8 Comments

B I U G O H1 H2 H3 ≡ ≡ “„ ⓘ ☰ <>

① ②

Leave a comment...

This textbox defaults to using [Markdown](#) to format your answer.

You can type !ref in this text area to quickly search our full set of tutorials, documentation & marketplace offerings and insert the link!

[Sign In or Sign Up to Comment](#)

[woods.marcus](#) • October 31, 2022

Thank you so much for the clear and excellent article. I was able to get this done minus the following issue below!

As of today, 10/31/2022 the following command does not work properly. The file does not exist when I try to run it. I ended up getting the xsl file from the github repo. I did do a find on the system and was unable to find any stat.xsl.gz available, so it appears they may not package this file any longer with the rtmp module. Please update accordingly or let me know if I am wrong.

```
sudo gunzip -c /usr/share/doc/libnginx-mod-rtmp/examples/stat.xsl.gz > /var/www/html/rt
```

[How To Set Up a Video Streaming Server using Nginx-RTMP on Ubuntu 20.04](#)

[Reply](#)

[CuteGreenBlueUrchin](#) • August 14, 2022

Hi! I'm having a problem when trying to load hls stream from a web player it shows "connection refused" status on the network inspector. I can do load the stream via VLC with no problem. Any clue? I already changed the ufw rules and checked it is enabled. also changed the source to obs\_stream.m3u8 as commented by matthewdewitt.

[Show replies](#) [Reply](#)

[EatingGrayCoral](#) • June 11, 2022

i find the issue

in last nginx.conf file need this

```
rtmp_auto_push on; rtmp { server { listen 1935; chunk_size 4096;
```

```
    application live {
        live on;
```

```
    hls on; hls_path /media/channels/; hls_fragment 5s; hls_base_url
http://192.168.1.135:81/hls/; hls_playlist_length 1m; wait_video on; hls_continuous on;
idle_streams on; hls_fragment_slicing aligned; record off;
```

then worked fine for me

[Reply](#)

[cf830c6886b4a559a7d04ca56](#) • May 9, 2022

The file /etc/nginx/sites-available/rtmp is wrong

[Reply](#)

[cf830c6886b4a559a7d04ca56](#) • May 6, 2022

Hi. I have done all the steps and it doesn't work as expected. I use OBS to stream my webcam as RTMP and I listen the audio but not the webcam!!! No error in the nginx log!!! But when I stream the desktop it shows it!!! What the hell! When I use RTMP to stream the webcam to YouTube RTMP it is ok.

[Reply](#)

[clemenko](#) • April 20, 2022

Owncast might be a better option. <https://owncast.online/>. I have been using it to stream my daughters gymnastics for a while now. Here is a little write up I have for deploying Owncast with Traefik using docker on a droplet. <https://github.com/clemenko/owncast>

[Reply](#)

[matthewdewitt](#) • April 5, 2022

There seems to be a typo in your config, or an error in mine.

When using OBS, the hls stream url is: obs\_stream.m3u8

Not: stream.m3u8

This can be validated by checking the contents of /var/www/html/stream/hls while OBS is

running.

Maybe that's expected? But you statically specified obs\_stream as the key earlier in the document, so I presume this is how the file is created in hls directory.

Anyway, a big THANK YOU for this article!

[Reply](#)

[omarruben](#) • February 22, 2022

Hello, I did try all, check very careful all details, not working... the Nginx works, I don't have any error on the server... I am running a local server with no firewall... but the streaming is not viewable with VLC or web browser

[Show replies](#) [Reply](#)



This work is licensed under a Creative Commons Attribution-NonCommercial- ShareAlike 4.0 International License.

💡 Congratulations on unlocking the whale ambience easter egg! Click the whale button in the bottom left of your screen to toggle some ambient whale noises while you read.

❤️ Thank you to the [Glacier Bay National Park & Preserve](#) and [Merrick079](#) for the sounds behind this easter egg.

🌐 Interested in whales, protecting them, and their connection to helping prevent climate change? We recommend checking out the [Whale and Dolphin Conservation](#).

Reset easter egg to be discovered again / Permanently dismiss and hide easter egg



Sign up for Infrastructure as a Newsletter.



Working on improving health and education, reducing inequality, and spurring economic growth?  
We'd like to help.



You get paid; we donate to tech nonprofits.

Featured on Community Kubernetes Course Learn Python 3 Machine Learning in Python Getting started with Go Intro to Kubernetes

DigitalOcean Products Virtual Machines Managed Databases Managed Kubernetes Block Storage Object Storage Marketplace VPC Load Balancers

## Welcome to the developer cloud

DigitalOcean makes it simple to launch in the cloud and scale up as you grow – whether you're running one virtual machine or ten thousand.

[Learn More](#)

### Company

### Products

### Community

### Solutions

### Contact

About

Products Overview

Tutorials

Website Hosting

Support

Leadership

Droplets

Q&A

VPS Hosting

Sales

Blog

Kubernetes

CSS-Tricks

Web & Mobile Apps

Report Abuse

Careers

App Platform

Write for DOnations

Game Development

System Status

Customers

Functions

Currents Research

Streaming

Share your ideas

Partners	Cloudways	Hatch Startup Program	VPN
Channel Partners	Managed Databases	deploy by DigitalOcean	SaaS Platforms
Referral Program	Spaces	Shop Swag	Cloud Hosting for Blockchain
Affiliate Program	Marketplace	Research Program	Startup Resources
Press	Load Balancers	Open Source	
Legal	Block Storage	Code of Conduct	
Security	Tools & Integrations	Newsletter Signup	
Investor Relations	API	Meetups	
DO Impact	Pricing		
	Documentation		
	Release Notes		
	Uptime		

© 2022 DigitalOcean, LLC. All rights reserved. DO is a registered trademark of DigitalOcean, LLC.



© 2022 DigitalOcean, LLC. All rights reserved.



[COOKIE PREFERENCES](#)