

Device Certificate Creation Steps(CVIP Preprod)

1. Create Folder & Copy CA Files

```
$ mkdir device_cert && cd device_cert
```

2. Generate Private Key

```
$ openssl genpkey -algorithm RSA -out device_private.key -pkeyopt rsa_keygen_bits:2048
```

3. Create CSR

```
openssl req -new -key device_private.key -out device.csr \
-subj
"/C=IN/ST=State/L=City/O=Traxo/OU=Software/CN=355013421200005-B234ZTZT03097
```

" 4.Create Payload

```
TS=$(date +%s)

csr_data=$(jq -Rs . < device.csr)

cat > payload.json <<EOF
{
  "commonName": "356741360411191-Traxo123",
  "timeStamp": $TS,
  "csr": $csr_data
}
EOF
```

5.Call Certificate API (For token please refer to 6 point and for Error please refer to 7 point)

```
TOKEN="75f6c8e1-1f94-30c1-9de4-adde85d0659f"
```

```
curl -k -v --tlsv1.2 \
-H "Authorization: Bearer ${TOKEN}" \
-H "Content-Type: application/json" \
-d @payload.json \
"https://cvipiot-preprod.fca-india.com:40543/csr/createCertificate" \
-o device_cert_response.json
```

6.Token get from the below api call

URL:<https://cvipiot-preprod.fca-india.com:40543/authentication/login>

METHOD:POST

PAYLOAD:{
 "userName": "admin",
 "password": "0[%62&Db\$Z:J",
 "accountId": "pkijeeptenant",
 "clientId": "oWXMOTG9yKyaTjZjuFin8kJmPXUa",
 "clientSecret": "XF3Cdm5NlkJr0NVRQ0vOZWkqmxEa"
}

In response you will get **access_token** look like this

RESPONSE:
{
 "access_token": "6938218b-dcb0-34e1-bcde-7ddc388a2fb",
 "refresh_token": "2ccbbf71-d588-3892-a198-208440fece8a",
 "token_type": "Bearer",
 "expires_in": 3600
}

This access_token need to pass in above 5 point as TOKEN

ERROR MSG FROM API CALL

7. In the above 5 point if the csr is mismatched then the error look like below from response

{
 "statusCode": 400,
 "message": "Public key mismatch. Please use previous key pair generated csr"
}

