

Material Requirement Planning

- MRP stands for Material Requirement Planning
- Main Purpose of MRP is to guarantee Material Availability
- MRP determines mainly; what material is needed? What Quantity of the material is needed? And when it is required?
- MRP Basically uses BOM in PP.BOM Stands for Bill of Material. for example let say you
 want to manufacture finished product as flange coupling now the components of
 Flange coupling as shown in figure will be entered in Bill of Material.



Now let us say you want to manufacture 1000 flange coupling, what system will do in this case if we run MRP for 1000 Flange coupling ?, system will calculate total quantity of components needed for manufacturing and will send information to the purchase department in the form of PR.


• Now when you run MRP there are generally two types of Materials in the organizations Inhouse Production (FERT ETC) and Externally Procured (ROH, ERSA etc.).



Chopade.sushilb@gmail.com


For the In-house material if you run MRP then system will generate planned order then that planned order can be converted into production order. This process comes under the scope of PP Module.

In case of externally procured material if you run MRP system will directly create PR and that PR can be converted to Purchase order. **OR** sometimes system will generates schedule lines. **OR** Sometimes it may possible to create planned order and that planned order can then be converted to PR and the PO as shown in figure below



Now where this procurement type (E or F) is maintained?


It is maintained in material master. It is maintained in MRP 2 view.



MRP Procedures

Basically there are two types of MRP Procedures;

- 1. MRP Based Planning
- 2. Consumption based planning





Forecast Based Planning


Based on the values of previous consumption of the material we plan for the future planning.

1. Create a material Master MM01


- Maintain Views basic data, purchasing, MRP1, MRP2, MRP3 and forecast based planning.
- IN MRP1 maintain basic details as shown in figure
- IN MRP2 Maintain GR Processing Time, Planned Delivery time and Scheduled Margin









2. Execute Forecast (T Code: MP30) here you need to enter Material MRP area and Plant







- If You click on past it will give you history of previous consumption.
- Click on Execute, select the forecast date after that you can see forecast values for future period




3. Convert Forecast values into Planned Order (MD02) OR MRP RUN

- Enter here Material, MRP Area and plant and select options as per requirement.
- You can click on display results before they are saved. It means it will show you how many orders are generated.








4. Convert Planned Orders to Purchase requisition (T Code: MD04)



- Maintain Material, Plant and MRP area Enter
- Double click on planned order and convert it to purchase requsition.
- Now this is for one planned order, where you can convert planned order to PR and after refreshing MD04 you can convert PR to PO
- Now collective conversion of Planned order to PR (T code MD15)
- Enter Plant select material enter material
- Then in next screen select all rows and click on convert online
- Keep goin on save button you will observe on by one planned order is getting converted into PR







Now again go to MD04 and check there all planned orders are converted to PR. You can convert these PR to PO one by one by double clicking on the PR.

But you can create single PO for All PR also


Now How to convert all PR into Single PO?


You can go to ME21N and in document overview go to selection variant then put only plant and material you will get list of all PR just select now PR and click on adopt so that it will be added in line items of single PO.

After this you can go for Good receipt and Monitor again in MMBE

Time phased Planning

It is also known as seasonal Planning. It is rarely used in industry, for time phased planning all the steps are same; only you need to change MRP views in **Material Master**.






Remaining MRP3, Forecasting Parameters remains the same .Only the planning will take place as per your planning calendar.


Reorder Point Planning


Reordering point planning involves calculating when stock levels hit a point at which it's the right time to reorder. This often involves taking into account demand forecasts, current stock levels and lead times.

1. Create Material Master (MM01)

- Maintain MRP1, MRP2, MRP 3 and forecasting view.
- IN MRP 1 Maintain MRP View AS VB(For Manual Reorder Point) and VM (Automatic reorder Point),MRP Controller and lots
- In MRP 2 view, you can maintain Procurement type, GR Processing time, Lead time and safety stock.
- MRP 3 Maintain Availability check
- In forecasting maintain forecast model as D, Define history period AND FORCAST PERIOD and go to consumption values. Maintain all consumptions of previous period's com to main data and click on execute forecast. Select forecast month and enter.
- Click on forecasting and enter.
- · Again select and click on forecasting







Material 60000454 is created. You can again observe the same reorder point in MRP1 view of the material.

- 2. Maintain stock of the material by maintaining PO (ME21N)and GR.(MIGO)
- 3. Stock maintained is 100 monitor by mmbe
- 4. Create GI to cost centre (MB1A/201)
- 5. We created GI of 40 quantities
- 6. Monotor stock at mmbe now our reorder point is 61.973 and available stock is 60 means available stock is less than reorder point
- 7. MRP RUN MD02

| Single-Item, Multi-Level | | | | | |
|----------------------------|-------------|--|--|--|--|
| | | | | | |
| Material | 60000454 | | | | |
| MRP Area | | | | | |
| Plant | 1000 | | | | |
| Scope of Planning | | | | | |
| Product group | | | | | |
| | | | | | |
| MRP Control Parameters | | | | | |
| Processing Key | NETCH | Net change for total horizon | | | |
| Create Purchase Req. | 3 | Purchase requisitions in opening period | | | |
| SA Deliv. Sched. Lines | 3 | Schedule lines | | | |
| Create MRP List | 1 | MRP list | | | |
| Planning mode | 1 | Adapt planning data (normal mode) | | | |
| Scheduling | 1 | Basic dates will be determined for plann | | | |
| Process Control Parameters | | | | | |
| Also plan unchanged com | ponents | | | | |
| Display results before the | y are saved | | | | |
| ✓ Display material list | | | | | |
| Simulation mode | | | | | |

Single-Item, Multi-Level



| Statistics | |
|-------------------------------------|---|
| Materials planned | 1 |
| Materials with New Exceptions | 1 |
| Materials with Termination MRP List | |

| 1000 | |
|-------|--------------------|
| 1000 | |
| NETCH | |
| 3 | |
| 3 | |
| 1 | |
| 1 | |
| 1 | |
| | 1000 NETCH 3 |

| Database Statistics |
|--------------------------|
| Planned orders created 1 |

| Runtime Statistics | |
|-----------------------|----------|
| Start of Planning Run | 14:12:23 |
| End of Planning Run | 14:12:23 |

| Ranking List of | Materials with | Highest CPU | Times | (in ms) | |
|-----------------|----------------|-------------|-------|------------|--------|
| Material | MRP Area | | Plnt | | |
| Runtime | Read Net | Calc. | BOM | LdTmeSched | Update |
| 60000454 | 1000 | | 1000 | | |
| 58 | 24 | 3 | 0 | 0 | 30 |

- 8. Planned orders are created
- 9. Planned order can be converted into PR by using MD04
- 10. You can observe reorder point is 61.973
- 11. Convert Planned order into Purchase Requisition
- 12. Convert PR into PO
- **13. MIGO**