DJBILBOX BEATS / HUMPIRE

Complete User Manual

Installation, license and detailed guide for every plugin

Version 1.0 - Windows (VST3) and macOS (VST3 / Audio Unit) - Royalty-free license

Contents

- Welcome
  - System requirements
  - Installation
  - Installation on macOS
  - First use in FL Studio
  - Common gestures
  - Presets
  - Uninstalling
  - License summary
  - Support
- ARENA BASS
  - Overview
  - Quick start in FL Studio
  - Interface
  - Parameters
  - Factory presets
  - Production tips
  - MIDI, automation and performance
  - FAQ
- CHINTZWAZ
  - Overview
  - Quick start in FL Studio
  - Interface
  - Parameters
  - Factory presets
  - Production tips
  - MIDI, automation and performance
  - FAQ
- CYBERPUNK LEAD
  - Overview
  - Quick start in FL Studio
  - Interface
  - Parameters
  - Factory presets
  - Production tips
  - MIDI, automation and performance
  - FAQ
- DZPOWER
  - Overview
  - Quick start in FL Studio
  - Interface
  - Parameters
  - Factory presets
  - Production tips
  - MIDI, automation and performance
  - FAQ
- FUNKYKOPS
  - Overview

- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

GOLDHAWK

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

HIGHROLLER GOLD

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

HUMPIRE CLUTCH

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE COMBO

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE GLITCH

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE HARDCAP

- Overview
- Quick start in FL Studio

- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE LAG
- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE LOADOUT
- Overview
- Installation
- What the plugins have in common
- Suggested chains
- Latency summary
- FAQ

HUMPIRE OVERCLOCK
- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE RESPAWN
- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE SKILLTREE
- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

K2000
- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance

- FAQ

MARABOUT

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

MIDNIGHT REELS

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI and automation
- FAQ

OCCITANIE

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

OCTOPUS

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

PHANTOM RIDER

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

ROCKPUNK

- Overview
- Installation
- Quick start in FL Studio
- Interface
- The sound path

- Parameters
- Your own guitars (optional)
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ
- Support

SAN ANDREAS LEAD

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

SHAMAN

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

STREETLIGHT TRAP

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

VOODOO

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

WARZONE808

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- MIDI, automation and performance
- FAQ

Welcome

Thank you for choosing **DJBILBOX BEATS / HUMPIRE**. This manual covers installation, licensing and the detailed use of every plugin in the collection: the DJBILBOX BEATS synthesizers and the **HUMPIRE LOADOUT** studio effects suite.

Every plugin is designed and programmed in Toulouse, France, by DJBILBOX BEATS, beatmaker and developer. All audio algorithms, interfaces and presets are original creations.

System requirements

Operating system	Windows 10 or 11, 64-bit; or macOS 11 or later (Apple Silicon and Intel)
Format	VST3 64-bit (Windows); VST3 and Audio Unit, universal (macOS)
Designed for	FL Studio. Any VST3 or Audio Unit host should load the plugins (Ableton Live, Logic Pro, Cubase, Studio One, Reaper, Bitwig…), but no human listening test and no test in every host has been done: try each plugin in your own host.
CPU	x64 processor (Intel Core i5 / AMD Ryzen 5 or better recommended)
Memory	4 GB minimum, 8 GB recommended
Display	1280 × 720 minimum; interfaces are resizable
Disk space	About 300 MB for the full collection

Installation

1. Close your music software (FL Studio or any other host).
2. Unzip the downloaded archive and run the **Setup.exe** installer it contains.
3. Accept the Windows administrator prompt. If Windows SmartScreen shows “Windows protected your PC”, click **More info**, then **Run anyway**.
4. Read and accept the license agreement.
5. Choose **Full installation**, or untick the plugins you do not want.
6. Click **Install**. The plugins are copied to the standard Windows VST3 folder: `C:\Program Files\Common Files\VST3`
7. This manual and the license agreement are installed in `C:\Program Files\DJBILBOX BEATS\Documentation` and can be opened from the Start menu (**DJBILBOX BEATS** folder).

Installation on macOS

1. Close your music software.
2. Open the macOS download and run the **.pkg** installer of the product (or the installers of the collection). The VST3 is installed in `/Library/Audio/Plug-Ins/VST3` and the Audio Unit in `/Library/Audio/Plug-Ins/Components`.
3. The installers are not notarized by Apple. If macOS says the package cannot be opened, open **System Settings > Privacy & Security**, scroll down and click **Open Anyway** next to the message about the installer, then confirm. The README in the download shows the same steps.
4. Restart your host and rescan plugins. In Logic Pro, the Audio Units are validated automatically. In FL Studio for macOS, use **Options > Manage plugins** and rescan.

First use in FL Studio

1. Open FL Studio, then **Options > Manage plugins**.
2. Make sure `C:\Program Files\Common Files\VST3` is listed among the plugin search paths (it is by default).
3. Click **Find installed plugins** (or **Start scan**). The plugins appear under the vendor **DJBILBOX BEATS** or **HUMPIRE by Djbilbox BEATS**.
4. Click the star (favorite) next to each plugin to find it quickly in the **Plugin database** and the browser.
5. **Synthesizers and sampler**: add them to the **Channel rack** (**+** button) and play them from a MIDI keyboard or the Piano roll.
6. **Effects**: open the **Mixer**, select a track, click an empty slot in the effects chain and choose the plugin.

> Tip: in FL Studio, right-click any plugin control and choose **Link to controller** to drive it from your MIDI controller, or **Create automation clip** to automate it.

Common gestures

Gesture	Action
Drag a knob vertically	Change the value
Shift + drag	Fine adjustment
Double-click	Reset to the default value
Right-click (on supported plugins)	Type a numeric value
Mouse wheel	Small steps
Bottom-right corner of the window	Resize the interface (on supported plugins)

Presets

Each plugin ships with factory presets organized by genre or instrument. Use the **<** and **>** arrows or the preset menu in the top bar. Your own presets are saved in your user folder (`Documents` or `AppData` , depending on the plugin, see the plugin's chapter) and are never overwritten by updates.

Uninstalling

On Windows, open **Windows Settings > Apps > Installed apps**, find **DJBILBOX BEATS - All Plugins** and click **Uninstall**. On macOS, delete the plugin files from the two folders above. Your own presets are kept.

License summary

The sounds and music you create with these plugins belong to you and are **royalty-free**: you may use them commercially (streaming, sales, placements, sync licensing, beat sales and leases) with no royalties and no mandatory credit. The license is personal and allows installation on two computers you own. Redistributing the plugins, their presets or their factory sounds on their own is prohibited. The full text is in **EULA_DJBILBOX_BEATS.txt**.

Support

Before contacting support, check the FAQ section of the plugin concerned. For any question: **djbilboxbeats.com**. Please include the plugin name, your Windows version, your host software and its version, and a precise description of the issue.

ARENA BASS

Stadium-size bass synthesizer: 808 subs, slap, reese, acid, horns and kicks from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

ARENA BASS is a bass synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: a sine sub with a pitch “knock”, a plucked-string slap bass, a Moog Bass engine (two saws, a square and a sub octave), a detuned Stadium Reese, a two-operator FM Growl, an Acid Rubber voice with a self-closing resonant filter, a Stadium Horns brass section and an Arena Kick for pitched kicks and stomps.

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and a master effects chain: distortion, chorus, ping-pong delay and reverb. The character is big, punchy and direct, made for sport-arena energy and hard-hitting low end.

ARENA BASS targets Trap, Drill and Hip-Hop 808s, Afrotrap and Afro bass lines, G-Funk slides, Deep House and acid bass, plus horn stabs and anthem hooks. Bass presets load in Mono mode for clean, one-note-at-a-time lines. The Stadium Horns bank plays chords in Poly mode with up to 16 voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **ARENA_BASS** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **ARENA BASS - Init Patch**: the Arena Sub engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. Bass lines sit best between MIDI notes 24 and 48 (C2 to C4 in FL Studio naming, where middle C is C5). Presets with TRANSPOSE at -12 sound one octave lower than the key you play.
5. Shape the sound with the three main controls:
   - **TONE**: the main character of the engine (knock, pluck hardness, sub level, FM ratio…).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, rounder bass.
   - **GLIDE**: slide time between notes. Leave it at zero for straight notes.
6. Adjust **VOLUME** (in the MASTER section) to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The camel artwork, the ARENA BASS title and “By Humpire”. The dotted grille at the left of the artwork is decorative.

Character panel (top right, slatted panel). Two rows of small knobs:

- Row 1: **TONE, BODY, BRIGHT, WIDTH, TEXTURE**. The five character controls of the selected engine.
- Row 2: **RES** (filter resonance), **ENV AMT** (filter envelope depth), **DISTORTION** and **DLY MIX** (delay level).

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, also under this header, is the global transposition (-12 to +12 semitones). It is not an LFO control.

MASTER section (right). VOLUME, **REVERB** and **CHORUS**.

Center row. From left to right:

- **AMP ENVELOPE**: four sliders, **ATTACK, DECAY, SUSTAIN, RELEASE**.
- **GLIDE** and **CUTOFF** knobs.
- **FILTER ENVELOPE**: four sliders, **ATK, DEC, SUS, REL**. The **VELOCITY** slider (velocity sensitivity of the level) sits just to their right.
- **DELAY**: **TIME** and **FEEDBACK** knobs (delay time and delay repeats). The delay level is the **DLY MIX** knob in the character panel.

Menu row. Five drop-down menus, each with a caption below it: **ENGINE** (Waveform), **LFO SHAPE** (LFO Source), **LFO DESTINATION** (Destination), **FILTER TYPE** and **VOICE MODE** (Mono/Poly). Each menu shows its current value.

Wheels (bottom left). Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

ARENA BASS exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Arena Sub, Slap Bass, Moog Bass, Stadium Reese, FM Growl, Acid Rubber, Stadium Horns, Arena Kick	Arena Sub	Selects the synthesis engine.

Parameter	Range	Default	Function
TONE (Tone)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 1	0.3	Character control 4. Engine-dependent (detune, drive, wobble speed…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (saturation, noise, feedback…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
ENV AMT (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects.

Parameter	Range	Default	Function
GLIDE (Glide)	0 to 2	0	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Modulation wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Arena Sub	Pitch “knock” at the attack	Adds the octave harmonic	Attack click	No effect	Saturation
Slap Bass	Pluck hardness	String sustain	Brighter, longer highs	Low body resonance (around 95 Hz)	Slap click
Moog Bass	Sub-octave level	Output weight	Built-in low-pass opening	Detune of the second saw	Blend from saws to square
Stadium Reese	Sub-octave level	Detune amount	Built-in low-pass opening	Saturation drive	Noise
FM Growl	Modulator ratio (0.5 to 3.5)	No effect	FM depth (growl intensity)	Speed of the built-in wobble (0.5 to 12.5 Hz)	Modulator feedback (grit)
Acid Rubber	Saw to pulse blend	Length of the built-in filter sweep	Depth of the built-in filter sweep	No effect	Saturation
Stadium Horns	Swell time of the built-in filter	Output weight	How far the filter opens	Detune of the three saws	Breath noise
Arena Kick	Pitch-drop depth	Decay length	Click	No effect	Saturation

Factory presets

ARENA BASS includes 70 factory presets in 7 banks of 10. All banks except Stadium Horns load in Mono mode. In the Stadium Horns bank, only Lead Horn is in Mono mode (with a short glide).

Arena Sub: Arena 808, Stadium Rumble, Long Slide Sub, Locker Room Sub, Hard Knock Bass, Short Pump, Smooth Court, Pitch Drop Dunk, Dirty Overtime, Scoreboard Sub.

Slap & Pluck Bass: Slap Bass, Pick Bass, Finger Funk, Muted Pocket, Upright Arena, Pop Slap, Deep Pluck, Chorus Bass, Dub Pluck, Walking Court.

Moog Bass: Arena Moog, Fat Moog, Rubber Moog, Sub Moog, Slide Moog, Pump Bass, Octave Moog, Hot Seat, Bass Stab, Warm Anthem.

Reese & Growl: Stadium Reese, Dirty Reese, Wobble Arena, Industrial Reese, Sub Reese, FM Growl, Talking Bass, Robot Growl, Metal Growl, Slow Growl.

Acid & Rubber: Acid Rubber, Squelch, Rubber Band, Acid Slide, Pulse Acid, Dirty Acid, Open Acid, Low Rubber, Pump Squelch, Buzzer Beater.

Stadium Horns: Stadium Horns, Fanfare, Brass Stab, Victory Horns, Soft Flugel, Slow Swell, Hit Section, Low Horns, Lead Horn, Anthem.

Kicks & Stomps: Arena Kick, Stomp, Long Boom, Punch Kick, Sub Kick, Crowd Stomp, Dirty Kick, Tom Fill, Drop Impact, Laser Kick.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.abpreset` file. The default folder is `DJBILBOX BEATS/ARENA_BASS/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .abpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Moog is a trademark of its owner. It is used here only to describe a sound style. DJBILBOX BEATS is not affiliated with the trademark owner.

Production tips

1. **Trap and Drill 808s.** Start from Arena 808 or Long Slide Sub. Raise TONE for a harder knock on short notes. Raise TEXTURE or add a little DISTORTION so the 808 stays audible on phone and laptop speakers.
2. **808 slides.** With GLIDE above zero, every new note slides from the previous one, even if the notes do not overlap. For slides on selected notes only, keep GLIDE at 0 and automate it up just before the notes that should slide.
3. **G-Funk bass.** Use the Moog Bass bank (Slide Moog, Fat Moog). Set GLIDE around 0.1 to 0.2 and play legato lines. Raise ENV AMT and shorten the filter DEC slider for a rounder “pluck” at the start of each note.
4. **Afrotrap and Afro bass.** The Slap & Pluck bank (Muted Pocket, Finger Funk, Pick Bass) gives bouncy, percussive lines. These presets are quieter by nature, so raise VOLUME. Use the VELOCITY slider around 60 to 80% so accents in your Piano roll come through.
5. **Deep House and acid.** Load Arena Moog or a preset from the Acid & Rubber bank. Automate CUTOFF over 8 or 16 bars. For movement, set LFO DESTINATION to Filter with a Square or Sample&Hold LFO shape, as in Pump Squelch.
6. **Reese and wobble.** On the Stadium Reese engine, BODY sets the detune and WIDTH drives the saturation. Set LFO DESTINATION to Filter, LFO SHAPE to Sine and RATE between 1 and 4 Hz for a wobble (see Wobble Arena).
7. **Horn hooks and anthems.** The Stadium Horns bank plays chords in Poly mode. Raise the ATTACK slider for swells (Slow Swell) or shorten DECAY and SUSTAIN for stabs (Hit Section). Add REVERB and CHORUS for a stadium-size sound.
8. **Kicks and stomps.** Load the Kicks & Stomps presets in a second ARENA BASS instance, so the kick and the 808 keep separate envelopes. Play kicks around MIDI notes 28 to 40 (E2 to E3 in FL Studio naming). TONE sets the pitch drop, BODY the length and BRIGHT the click. Tom Fill is transposed one octave up for fills.

MIDI, automation and performance

Notes and channels. ARENA BASS responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, pitch, bend, filter, distortion and delay changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. ARENA BASS is lightweight. Effects set to zero are bypassed and cost no CPU. Mono mode and short release times keep the voice count low. The plugin works at 44.1, 48, 88.2 and 96 kHz.

FAQ

ARENA BASS does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **ARENA_BASS** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Some presets use TRANSPOSE -12 and play very low, below what small speakers can reproduce. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. For notes outside the on-screen keyboard range (MIDI 36 to 84), play from a MIDI keyboard or the Piano roll.

My 808 is not perfectly centered. Each note gets a slight random stereo offset. For a strictly centered sub, reduce the stereo separation of the mixer track in FL Studio, or insert a mono utility after ARENA BASS. If the bass is also weak on small speakers, add harmonics with TEXTURE, BODY or DISTORTION.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for bass presets. Switch it to Poly (up to 16 voices).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

CHINTZWAZ

Retro floral synthesizer: sitar, flower-power keys, tape strings, flutes, kalimba, pads and psychedelic organ, from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

CHINTZWAZ is a retro, bohemian synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Sitar Bloom (a plucked string with a buzzing bridge), Flower EP (an electric piano with a bell-like tine), Mellotron (five detuned saws with tape flutter and breath), Hippie Flute (a sine with harmonics, vibrato and breath noise), Kalimba (short metallic tines), Daisy Pad (detuned saws with a sub octave and a slowly breathing filter), Bloom Bass (a filtered triangle/saw with a round sub) and Psyche Organ (a drawbar organ with tremolo).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The look is a pink brushed-metal faceplate on floral wallpaper.

CHINTZWAZ fits Lo-fi Hip-Hop and Boom Bap loops, psychedelic Soul and Funk, Oriental-flavored melodies (sitar, flute), Afrobeats and Amapiano (kalimba, pads), dreamy pads and retro keys. Most presets load in Poly mode (up to 16 voices). Twelve presets load in Mono mode: one flute-and-tape lead and the bass and organ voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **CHINTZWAZ** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **CHINTZWAZ - Init Patch**: the Sitar Bloom engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 48 to 96 (C4 to C8 in FL Studio naming, where middle C is C5). Keys, pads and plucks work well in the middle of that range; the Bloom Bass presets sit lower, so play them from a MIDI keyboard or the Piano roll.
5. Shape the sound with the three main controls:
   - **TONE**: the main character of the engine (pluck brightness, tape color, breath pitch, organ sub drawbar…).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, vintage tone.
   - **WIDTH**: jawari buzz, tape detune and wobble, flute vibrato, pad detune or organ tremolo, depending on the engine.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DB logo and the DJBILBOXBEATS name.

Center. The camel artwork, the CHINTZWAZ title and “By Humpire”. The two perforated speaker grilles on each side of the artwork carry the small character knobs (see below).

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, also under this header, is the global transposition (-12 to +12 semitones). It is not an LFO control.

Left speaker grille. Four small knobs stacked vertically: **TONE, BODY, BRIGHT, WIDTH**.

Right speaker grille. Three small knobs stacked vertically: **TEXTURE** (the fifth character control), **RES** (filter resonance) and **ENV AMT** (filter envelope depth).

AMP ENVELOPE (lower left). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

GLIDE and CUTOFF. The **GLIDE** knob sits at the left of the title and the **CUTOFF** knob at the right.

FILTER ENVELOPE (upper right). Four sliders: **ATTACK, DECAY, SUSTAIN** (filter envelope) and **VELOCITY** (how much note velocity changes the level).

MASTER and EFFECTS (right). VOLUME is the large knob in the top right corner. Under the **EFFECTS** header, first row: **REVERB, CHORUS, DISTORTION**. Second row: **DELAY** (delay level), **DLY TIME** (delay time) and **FEEDBACK** (delay repeats).

Menu row. Five drop-down menus, each with a caption below it: **ENGINE**, **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels (bottom left). PITCH BEND springs back to the center when you release it. **MOD WHEEL** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 48 to 96 (four octaves plus one key). The key labels on screen run from C2 to C6, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C4 to C8. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

CHINTZWAZ exposes 34 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Control	Range	Default	What it does
ENGINE (Waveform)	Sitar Bloom, Flower EP, Mellotron, Hippie Flute, Kalimba, Daisy Pad, Bloom Bass, Psyche Organ	Sitar Bloom	Selects the synthesis engine.
TONE (Tone)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 1	0.3	Character control 4. Engine-dependent (detune, buzz, vibrato, tremolo…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (noise, click, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (Filter Type)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
ENV AMT (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
FILTER ENVELOPE ATTACK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
FILTER ENVELOPE DECAY (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time. It also sets the filter release time after the key is released.
FILTER ENVELOPE SUSTAIN (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
VELOCITY (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
AMP ENVELOPE ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
AMP ENVELOPE DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
AMP ENVELOPE SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.

Control	Range	Default	What it does
AMP ENVELOPE RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects. Shown in dB.
GLIDE (Glide)	0 to 2 s	0	Portamento: the value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (slow, fixed rate).
DELAY (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.

Control	Range	Default	What it does
PITCH BEND wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
MOD WHEEL (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Sitar Bloom	Brightness of the pluck	String sustain	String brightness (less damping)	Jawari buzz amount	Level of a resonant formant (about 900 to 2,500 Hz)
Flower EP	No effect	Length of the tine decay	Bark (upper partials), stronger with velocity	No effect	Attack noise
Mellotron	Center of a mid band (400 to 1,100 Hz)	Level of that mid band	Low-pass opening	Detune of the five saws and tape wobble depth	Wobble speed and breath noise
Hippie Flute	Pitch of the breath noise	Resonance of the breath noise	Level of the 2nd and 3rd harmonics	Vibrato depth (fades in after the attack)	Breath noise level
Kalimba	Level of the pluck click	Ring length	Level of the upper partials	No effect	Resonance of the kalimba box
Daisy Pad	No effect	Sub-octave level	Filter opening, with a slow built-in breathing	Detune of the five saws	Noise
Bloom Bass	Blend from triangle to saw	Sub level	Opening of a built-in low-pass that closes during the note	How slowly that low-pass closes	Saturation
Psyche Organ	Sub-octave drawbar level	Level of the octave-up drawbar	Level of the upper drawbars	Tremolo speed and depth	Key click

Factory presets

CHINTZWAZ includes 70 factory presets in 7 banks of 10. 58 load in Poly mode and 12 in Mono mode (Violin Tape; Breathy Dawn, Sad Daisy, Flute Echo, Wind In Petals and Whistling Gardener; and the Bloom Bass & Organs presets Bloom Bass, Round Sub, Fuzz Petal, Slide Stem, Pluck Root and Vox Garden).

Sitar & Strings (Sitar Bloom engine): Sitar Bloom, Raga Morning, Patchouli Pluck, Jawari Buzz, Marigold Drone, Soft Tamboura, Hippie Strum, Bazaar Echo, Low Sitar, Glass Sitar.

Flower EP (Flower EP engine): Flower Power EP, Velvet Daisy, Bark Petal, Summer Haze Keys, Tremolo Bloom, Tape Wurly, Bell Blossom, Low Tide EP, Lazy Sunday, Wah Garden.

Mellotron & Choir (Mellotron engine): Chintz Mellotron, Strawberry Tape, Soft Choir Tape, Flute Mellotron, Violin Tape, Slow Wobble, Dream Tape Pad, Low Choir Tape, Eight Track, Kaleidoscope.

Hippie Flutes (Hippie Flute engine): Hippie Flute, Meadow Pipe, Breathy Dawn, Sad Daisy, High Piccolo, Flute Echo, Wind In Petals, Low Flute, Fog Flute, Whistling Gardener.

Kalimba & Bells (Kalimba engine): Daisy Kalimba, Music Box Garden, Thumb Piano, Wind Chimes, Glass Petals, Low Kalimba, Echo Garden, Rain On Leaves, Teacup Bell, Marimba Blush.

Daisy Pads (Daisy Pad engine): Daisy Pad, Petal Mist, Sundress Strings, Slow Bloom, Lavender Haze, Warm Chintz, Breeze Drift, Whisper Field, Pulse Of Spring, Twilight Garden.

Bloom Bass & Organs (Bloom Bass engine for the first five, Psyche Organ engine for the last five): Bloom Bass, Round Sub, Fuzz Petal, Slide Stem, Pluck Root, Psyche Organ, Vox Garden, Soft Flute Stop, Rotary Daisy, Golden Haze Organ.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.czpreset` file. The default folder is `DJBILBOX BEATS/CHINTZWAZ/Presets` inside your Documents folder. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .czpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Lo-fi and Boom Bap loops.** Start from Tape Wurly or Eight Track. Lower CUTOFF and add a little CHORUS for a dusty, vintage color. Raise DISTORTION slightly to glue the sound.
2. **Sitar and Oriental-flavored melodies.** Load Sitar Bloom or Raga Morning. WIDTH sets the jawari buzz and TEXTURE adds a resonant formant. Add DELAY (Bazaar Echo is a starting point) and set DLY TIME to a quarter or eighth note: 60 / BPM seconds, halved for an eighth.
3. **Psychedelic Soul and Funk keys.** Flower Power EP and Bark Petal respond to velocity: BRIGHT adds bark on hard notes. Use the VELOCITY slider around 60 to 80% so the accents of your Piano roll come through. Wah Garden uses the filter envelope; raise ENV AMT for a stronger wah.
4. **Afrobeats and Amapiano.** Daisy Kalimba, Thumb Piano and Music Box Garden give short, bouncy hooks; Daisy Pad and Sundress Strings hold the harmony. Add REVERB for space and a touch of DELAY for movement.
5. **Tape strings and choirs.** On the Mellotron engine, WIDTH detunes the five saws and adds tape wobble, and TEXTURE sets the wobble speed. Raise the AMP ENVELOPE ATTACK for swells (Dream Tape Pad).
6. **Flute leads.** Play Hippie Flute in Mono mode for clean lines, and add GLIDE (about 0.1 s) for smooth slides. WIDTH sets the vibrato depth; TEXTURE sets the breath.
7. **Slow-moving pads.** Slow Bloom and Daisy Pad use long attacks and releases. Automate CUTOFF over 8 or 16 bars, or set LFO DESTINATION to Filter with a slow Sine for gentle movement (Kaleidoscope uses the Timbre destination).
8. **Bass and organ.** The Bloom Bass presets load in Mono mode. Round Sub keeps TONE low for a soft low end; Fuzz Petal adds saturation through TEXTURE. Psyche Organ and Rotary Daisy play chords in Poly mode, or in Mono mode for lead lines like Vox Garden.

MIDI, automation and performance

Notes and channels. CHINTZWAZ responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen PITCH BEND wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen MOD WHEEL (up to +0.8 on top of AMOUNT, capped at 1). When both are used, the higher value wins. A note that starts later begins from the latest CC1 position. For repeatable results in a song, automate the **Mod Wheel** parameter.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 34 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, transpose, bend, cutoff, distortion and delay changes are smoothed to avoid clicks. Parameters show units in the host (Hz, ms, s, dB, semitones, %).

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. Effects set to zero are bypassed. Fewer simultaneous notes and shorter release times keep the voice count low.

FAQ

CHINTZWAZ does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **CHINTZWAZ** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. Some presets have a long attack (pads, Slow Bloom), so the sound fades in slowly. For notes outside the on-screen keyboard range (MIDI 48 to 96), play from a MIDI keyboard or the Piano roll.

The sound is slightly different on every note. Each note gets a random starting phase and a slight random stereo offset. This is intended and adds a natural feel.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The VOICE MODE menu is set to Mono. Switch it to Poly (up to 16 voices).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

CYBERPUNK LEAD

Neon lead synthesizer: supersaws, PWM, glitch FM, reese bass, laser plucks, brass, glass bells and bit-crushed FX from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

CYBERPUNK LEAD is a lead synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Neon Saw (a five-saw supersaw with sub and octave layers), Chrome PWM (two pulse waves with a moving pulse width), Glitch FM (two-operator FM with feedback), Reese Bass (detuned saws with a sub and saturation), Laser Pluck (a saw with a pitch dive and a closing filter), Neon Brass (detuned saws with an opening filter), Data Crush (a saw run through sample-rate and bit-depth reduction) and Hollow Glass (FM bells).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and a master effects chain: distortion, chorus, ping-pong delay and reverb.

CYBERPUNK LEAD targets Trap and Drill leads, Synthwave and Retrowave, Hip-Hop hooks, Afrotrap melodies, G-Funk portamento leads and dark electronic bass lines. The leads, basses and FX load in Mono for clean single-note lines. The Laser Plucks, Neon Brass & Pads and part of the other banks load in Poly mode, which plays up to 16 voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **CYBERPUNK_LEAD** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **CYBERPUNK LEAD - Init Patch**: the Neon Saw engine in Poly mode with default settings.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. Leads sit well between C5 and C7 in FL Studio naming (middle C is C5). The Reese & Bass presets work an octave or two lower.
5. Shape the sound with the three main controls:
   - **TONE**: the main character of the engine (sub level, PWM depth, FM ratio, pitch dive, crush rate…).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a softer, darker lead.
   - **GLIDE**: slide time between notes. Leave it at zero for straight notes.
6. Adjust **VOLUME** (top right, above REVERB and CHORUS) to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels on a dark steel faceplate with pink and yellow neon accents. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The camel artwork, the “Cyberpunk Lead” title and “By Humpire”. The dotted grilles on each side of the artwork are decorative.

Character knobs (center). Four small knobs, **TONE, BODY, BRIGHT, WIDTH**, sit left of the **GLIDE** knob. They are four of the five character controls of the selected engine. The fifth, **TEXTURE**, sits to the right of **CUTOFF**, together with **RES** (filter resonance), **ENV AMT** (filter envelope depth) and **DELAY MIX** (delay level).

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, also under this header, is the global transposition (-12 to +12 semitones). It is not an LFO control.

AMP ENVELOPE (left). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

FILTER ENVELOPE (top right). Five sliders: **ATTACK, DECAY, SUSTAIN, RELEASE** (the filter envelope) and **VELOCITY** (velocity sensitivity of the level, not part of the filter envelope).

Output and effects (right). Top row: **VOLUME**, **REVERB**, **CHORUS**. Bottom row: **DISTORTION**, **DLY TIME** (delay time), **FEEDBACK** (delay repeats).

Menu row. Five drop-down menus, each with a caption below it: **ENGINE** (Waveform), **LFO SHAPE** (LFO Source), **LFO DESTINATION** (Destination), **FILTER TYPE** and **VOICE MODE** (Mono/Poly). Each menu shows its current value.

Wheels (bottom left). PITCH BEND springs back to the center when you release it. **MODULATION** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 48 to 96: four octaves plus one key. Its key labels run from C2 to C6; FL Studio names the same notes C4 to C8 (middle C is C5).

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

CYBERPUNK LEAD exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Neon Saw, Chrome PWM, Glitch FM, Reese Bass, Laser Pluck, Neon Brass, Data Crush, Hollow Glass	Neon Saw	Selects the synthesis engine.
TONE (Tone)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).

Parameter	Range	Default	Function
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 1	0.3	Character control 4. Engine-dependent (detune, drive, PWM speed…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (noise, click, sub…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
ENV AMT (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
FILTER ATTACK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
FILTER DECAY (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
FILTER SUSTAIN (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
FILTER RELEASE (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects.

Parameter	Range	Default	Function
GLIDE (Glide)	0 to 2	0	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.
PITCH BEND wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
MODULATION wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Neon Saw	Level of the sub-octave sine	Supersaw detune	Opening of the built-in low-pass	Level of an added octave-up saw	Noise
Chrome PWM	Pulse-width modulation depth	Detune of the second pulse	Opening of the built-in low-pass	PWM speed (0.3 to 5.3 Hz)	Level of the sub-octave sine
Glitch FM	Modulator ratio (0.5 to 4.0)	Decay time of the FM depth	FM depth	Modulator feedback	Attack click
Reese Bass	Sub-octave level	Detune amount	Opening of the built-in low-pass	Saturation drive	Noise
Laser Pluck	Depth of the pitch dive at the attack	Closing time of the built-in filter	Opening of the built-in filter	Detune of the second saw	Attack click
Neon Brass	Swell time of the built-in filter	Output weight	How far the filter opens	Detune of the three saws	Noise
Data Crush	Crush rate (sample-and-hold length)	Bit depth (2 to 12 bits)	Opening of the built-in low-pass	Level of an added pulse	Noise
Hollow Glass	Modulator ratio (1.4 to 4.5)	Bell decay length	FM depth	Detune of the second oscillator	Attack click

Factory presets

CYBERPUNK LEAD includes 70 factory presets in 7 banks of 10. 32 presets load in Mono mode and 38 load in Poly mode.

Neon Leads (Neon Saw; Poly: Supersaw Wall): Neon Rider, Chrome Hero, Night Drive, Hacker Lead, Laser Solo, Supersaw Wall, Soft Neon, Blade Lead, Octave Jump, Wire Lead.

Chrome & Pulse (Chrome PWM): Chrome Pulse, Wide PWM, Cyber Bass PWM, Fast Wobble, Retro Keys, Sunset Pad, Pulse Stab, Hollow Pulse, Arcade Lead, Pulse Drone.

Glitch FM (Glitch FM): Glitch Bell, Data Pluck, FM Lead, Metal Keys, Digital Choir, Alien Voice, Cyber Marimba, Circuit Bass, Scan Lines, Neural Net.

Reese & Bass (Reese Bass, all Mono): Reese Core, Neon Sub, Dirty Reese, Wobble Grid, Industrial Bass, Cyber Slide, Acid Reese, Subway Bass, Bass Stab, Meltdown.

Laser Plucks (Laser Pluck, all Poly): Laser Pluck, Neon Arp, Zap Down, Chrome Pluck, Techno Stab, Soft Pluck, Synth Harp, Cyber Koto, Sci-Fi Drop, Pluck Wall.

Neon Brass & Pads (Neon Brass, then Hollow Glass; all Poly): Neon Brass, Blade Runner Pad, Synthwave Stab, Chrome Horns, Slow Open, Warm Neon, Hollow Glass, Ice Bell, Crystal Rain, Ghost Chime.

Data Crush & FX (Data Crush, plus Boot Sequence on Laser Pluck and Modem Dial on Glitch FM): Data Crush, 8-Bit Lead, Bit Rain, Glitch Bass, Corrupted Pad, Signal Lost, Modem Dial, Firewall, Static Wind, Boot Sequence.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.cppreset` file. The default folder is `DJBILBOX BEATS/CYBERPUNK_LEAD/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu, and **Open a .cppreset file…** loads a file from anywhere.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Trap and Drill leads.** Start from Neon Rider or Hacker Lead. Raise BRIGHT for a sharper edge, keep GLIDE at 0 for tight notes and add a little DELAY MIX with DLY TIME at 0.25 to 0.5 s.
2. **Synthwave and Retrowave.** Load Night Drive, Supersaw Wall or a preset from Neon Brass & Pads. Raise CHORUS and REVERB, set VOICE MODE to Poly and play chords.
3. **Portamento leads.** With GLIDE above zero, every new note slides from the previous one, even if the notes do not overlap. Around 0.1 to 0.2 gives a classic G-Funk glide. For slides on selected notes only, keep GLIDE at 0 and automate it up just before those notes.
4. **Dark bass lines.** The Reese & Bass bank loads in Mono. On the Reese engine, BODY sets the detune and WIDTH drives the saturation. Set LFO DESTINATION to Filter, LFO SHAPE to Sine and RATE between 1 and 4 Hz for a wobble (see Wobble Grid).
5. **Plucks and arps.** In the Laser Plucks bank, TONE sets how deep the pitch dive is and BODY sets how fast the filter closes. Shorten DECAY and RELEASE for tight arpeggios.
6. **Filter movement.** Raise ENV AMT and shape the FILTER ENVELOPE sliders: a short FILTER DECAY with FILTER SUSTAIN at 0 gives a pluck at the start of each note, a longer FILTER ATTACK gives a swell. Automate CUTOFF over 8 or 16 bars for builds.
7. **Glitch and FX.** In Data Crush, lower TONE for a lower sample rate and lower BODY for fewer bits. Sample&Hold on the LFO with DESTINATION set to Pitch or Timbre gives random movement.
8. **Bells and glass.** The Hollow Glass presets decay naturally (SUSTAIN is 0): play them with long RELEASE and add REVERB. Change TONE to move the FM ratio from soft to metallic.

MIDI, automation and performance

Notes and channels. CYBERPUNK LEAD responds to MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over. In Mono mode, each new note stops the previous one (last-note priority).

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen PITCH BEND wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen MODULATION wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives and the most recent position is applied to new notes.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob.

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. Effects set to zero are bypassed and cost no CPU. Mono mode and short release times keep the voice count low.

FAQ

CYBERPUNK LEAD does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **CYBERPUNK_LEAD** under **DJBILBOX BEATS**. It is an instrument: load it from the **Generators** list.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. With FILTER TYPE on High Pass, low notes are filtered out. Some presets, such as Static Wind, start slowly because of a long ATTACK.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for most lead and bass presets. Switch it to Poly (up to 16 voices).

Is the LFO or the delay synced to the tempo? No. The LFO runs in Hz (0.05 to 20 Hz) and the delay time is set in seconds (0.05 to 1 s).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

DZPOWER

Algerian Raï, Chaabi and Casbah sounds from eight synthesis engines: plucked strings, reed flutes, organ, strings and hand drums.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

DZPOWER is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines inspired by the instruments of Algerian popular music: Mandole (plucked string), Qanun (zither), Gasba (reed flute), Ghaita (double-reed horn), Rai Organ, Chaabi Strings, Derbouka (hand drum) and Bendir Sub (deep sub with rattle).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a resonant multimode filter with its own envelope, an amplitude envelope, an LFO and a master effects chain: distortion, chorus, ping-pong delay and reverb. Up to 16 voices play at once in Poly mode.

DZPOWER targets Raï and Raï'n'B, Chaabi, Oriental pop, Afrotrap, Hip-Hop and Trap. Use the Mandole and Qanun for melodic hooks, the Gasba and Ghaita for lead lines, the Rai Organ and Chaabi Strings for chords and pads, and the Derbouka and Bendir Sub for percussion and sub bass.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **DZPOWER** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **DZPOWER - Init Patch**: the Mandole engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 96 (C2 to C7 in the labels printed on the keys; C3 to C8 in FL Studio naming, where middle C is C5).
5. Shape the sound with three controls:
   - **TONE**: the main character of the engine (its effect depends on the engine, see the table in the Parameters section).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, rounder sound.
   - **REVERB**: places the sound in a small or large space.
6. Adjust **VOLUME** (in the MASTER section) to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 500 x 373 up to 2000 x 1492 pixels. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking it opens a message saying that expansion packs are coming soon, with a link to the DJBILBOX BEATS store. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name.

Center. The camel emblem and the DZPOWER title between two perforated speaker grilles that hold the small knobs. The left grille holds **TONE, BODY, BRIGHT, WIDTH**. The right grille holds **TEXTURE, FLT ENV** (filter envelope depth) and **DELAY MIX** (delay level).

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, in the same row, is the global transposition (-12 to +12 semitones). It is not an LFO control.

MASTER section (top right). VOLUME and **REVERB**.

AMP ENVELOPE (left, below the LFO). Four vertical sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

FILTER ENVELOPE (right). Four vertical sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**. The **VELOCITY** slider (velocity sensitivity of the level) sits just to their right, separated by a thin line, because it is not part of the filter envelope.

Center row. From left to right: the **GLIDE** knob, the **FILTER** group (**CUTOFF** and **RESONANCE**), the **EFFECTS** group (**CHORUS** and **DISTORTION**) and the **DELAY** group (**TIME** and **FEEDBACK**).

Menu row. Five drop-down menus, each with a caption below it: **WAVEFORM** (the engine), **LFO SOURCE** (LFO shape), **LFO DESTINATION**, **FILTER TYPE** and **MONO / POLY**. Each menu shows its current value.

PITCH & MOD (bottom left). The **Pitch Bend** wheel springs back to the center when you release it. The **Mod Wheel** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. It also lights up incoming MIDI notes within its range. The keyboard covers MIDI notes 36 to 96: five octaves plus one key, with labels from C2 to C7 (middle C, MIDI 60, is labeled C4; in FL Studio naming the same range reads C3 to C8). It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click a knob or slider to return it to its default value. The mouse wheel also adjusts controls.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

DZPOWER exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Control	Range	Default	What it does
WAVEFORM menu (Waveform)	Mandole, Qanun, Gasba, Ghaita, Rai Organ, Chaabi Strings, Derbouka, Bendir Sub	Mandole	Selects the synthesis engine.
TONE (Tone)	0 to 100%	50%	Character control 1. Engine-dependent.
BODY (Body)	0 to 100%	50%	Character control 2. Engine-dependent.

Control	Range	Default	What it does
BRIGHT (Brightness)	0 to 100%	50%	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 100%	30%	Character control 4. Engine-dependent (vibrato, detune, tremolo, drive…). It is not a stereo width control.
TEXTURE (Texture)	0 to 100%	20%	Character control 5. Engine-dependent (noise, click, body resonance…).
CUTOFF (Filter Cutoff)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RESONANCE (Resonance)	0 to 100%	15%	Filter resonance.
FILTER TYPE menu (Filter Type)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
FLT ENV (Filter Env Amount)	0 to 100%	0%	Filter envelope depth. At 100% the envelope opens the cutoff by up to 5 octaves. At 0% the filter envelope has no effect.
Filter ATTACK (Filter Attack)	2 ms to 3 s	2 ms	Filter envelope attack time.
Filter DECAY (Filter Decay)	20 ms to 4 s	300 ms	Filter envelope decay time.
Filter SUSTAIN (Filter Sustain)	0 to 100%	0%	Filter envelope sustain level.
Filter RELEASE (Filter Release)	20 ms to 4 s	300 ms	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 100%	50%	How much note velocity changes the level. 0%: all notes at the same level. 100%: full velocity response.
Amp ATTACK (Attack)	1 ms to 5 s	10 ms	Amplitude envelope attack time.
Amp DECAY (Decay)	10 ms to 5 s	400 ms	Amplitude envelope decay time.
Amp SUSTAIN (Sustain)	0 to 100%	70%	Amplitude envelope sustain level.
Amp RELEASE (Release)	20 ms to 8 s	400 ms	Amplitude envelope release time.
VOLUME (Volume)	0 to 1 (shown in dB, -inf to 0 dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.
GLIDE (Glide)	0 to 2 s	0	Portamento. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.

Control	Range	Default	What it does
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 100%	0%	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 80% to this value.
LFO SOURCE menu (LFO Source)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION menu (Destination)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
MONO / POLY menu (Mono/Poly)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 100%	0%	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 100%	0%	Stereo chorus mix (fixed rate).
DELAY MIX (Delay Mix)	0 to 100%	0%	Level of the ping-pong delay.
TIME (Delay Time)	50 ms to 1 s	350 ms	Delay time. Not tempo-synced: for a quarter note, use 60 / BPM seconds (0.5 s at 120 BPM).
FEEDBACK (Delay Feedback)	0 to 90%	35%	Number of delay repeats.
REVERB (Reverb)	0 to 100%	25%	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-2 to +2 semitones	0	On-screen pitch bend. Adds to MIDI pitch bend (also +/-2 semitones).
Mod Wheel (Mod Wheel)	0 to 100%	0%	On-screen mod wheel. Adds up to 80% to the LFO AMOUNT.

What the character controls do on each engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Mandole	Pluck hardness and body resonance frequency	String sustain	String brightness (damping)	No effect	Level of the body resonance

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Qanun	No effect	String sustain	String brightness (damping)	Level of the octave-up sympathetic attack	No effect
Gasba	Breath filter frequency	Breath filter resonance	Level of the 2nd and 3rd harmonics	Vibrato depth (about 5 Hz, fades in)	Breath noise level
Ghaita	Frequency of the nasal resonances	Level of the nasal resonances	Opening of the reed low-pass	Detune between the two reeds	Noise level
Rai Organ	Sub-octave drawbar level	Octave-up drawbar level	Level of the 3rd, 4th and 6th harmonic drawbars	Tremolo depth and speed	Key click
Chaabi Strings	Center frequency of the body band	Level of the body band	Opening of the low-pass	Vibrato depth (starts after 0.2 s)	Noise level
Derbouka	Depth of the pitch drop at the attack	Length of the doum	Frequency of the “tak” slap noise	Level of the “tak” slap	Click
Bendir Sub	Pitch knock at the attack	Octave harmonic level	Length of the rattle	Saturation drive	Level of the rattle

Factory presets

DZPOWER includes 70 factory presets in 7 banks of 10. 55 presets load in Poly mode and 15 in Mono mode: the whole Bendir Sub & Bass bank, plus Breathy Gasba, Zorna Fete, Snake Zorna, Rai Lead Organ and Violon Alger.

Mandole: Mandole Alger, Mandole Chaabi, Casbah Pick, Warm Mandole, Tremolo Pick, Low Mandole, Bright Strum, Rai Pluck, Muted Mandole, Desert Night Pluck.

Qanun & Plucks: Qanun Dar, Zither Rain, Harp Of Tlemcen, Bright Qanun, Soft Qanun, Oriental Arp, Low Qanun, Glass Qanun, Sahara Strings, Zellij Pluck.

Gasba & Ghaita: Gasba Reve, Desert Gasba, Breathy Gasba, Sufi Gasba, High Gasba, Ghaita Call, Zorna Fete, Nasal Reed, Mizmar Dz, Snake Zorna.

Rai Organ: Rai Organ, Oran Night, Full Rai, Rai Lead Organ, Accordeon Dz, Vintage Rai Keys, Soft Flute Stop, Rotary Casbah, Tape Rai, Golden Swell.

Chaabi Strings: Chaabi Strings, Violon Alger, Slow Swell, Dark Cellos, High Violins, Pizzicato Dz, Andalous Pad, Wobble Violin, Suspense Casbah, Rooftop Strings.

Derbouka & Perc: Derbouka Doum, Tak Tak, Deep Doum, Slap Derbouka, Tabla Dz, Rai Percussion, Dub Doum, Hand Drum Fill, Crowd Clap, Drop Doum.

Bendir Sub & Bass: Bendir Sub, Deep Casbah, Rattle Sub, Long Slide Sub, Pitch Drop Dz, Dirty Bendir, Smooth Sub, Hard Knock Dz, Short Boom, Rumble Alger.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.dzpreset` file. The default folder is `DJBILBOX BEATS/DZPOWER/Presets` inside your Documents folder. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .dzpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

- **Hooks.** Start from a Mandole or Qanun preset, add a little DELAY MIX and set TIME to an eighth note (30 / BPM seconds) for a rolling Raï-style pluck line.
- **Lead lines.** Use a Mono preset (Breathy Gasba, Zorna Fete) and add GLIDE for slides between notes. Raise WIDTH on the Gasba for more vibrato.
- **Pads.** On Chaabi Strings, raise ATTACK and RELEASE in the AMP ENVELOPE and add CHORUS and REVERB for a wide string bed.
- **Percussion.** On Derbouka, TONE sets the depth of the pitch drop, BODY the length of the doum and WIDTH the level of the slap. Play different notes to tune the drum.
- **Sub bass.** The Bendir Sub presets are Mono. Keep CUTOFF high and use TRANSPOSE (-12) to drop an octave. Add DISTORTION to make the sub audible on small speakers.
- **Movement.** Set LFO DESTINATION to Filter and AMOUNT around 30% for a slow wobble, or to Timbre to make the character controls drift.
- **Expression.** Raise VELOCITY to make notes you play softly quieter and harder hits louder. Map the mod wheel to add LFO depth while you play.

MIDI, automation and performance

- **Notes.** All 16 MIDI channels are accepted and play the same sound.
- **Velocity.** Controls the level, scaled by the VELOCITY slider.
- **Pitch bend.** MIDI pitch bend moves the pitch by +/-2 semitones, added to the on-screen Pitch Bend wheel.
- **Mod wheel (CC1).** Adds up to 80% to the LFO AMOUNT. CC121 (reset all controllers) resets it to zero.
- **Polyphony.** Up to 16 voices in Poly mode. Mono mode plays one note at a time with last-note priority.
- **Automation.** All 35 parameters appear in the host's automation list with units (%, Hz, ms, dB, semitones).
- **Latency.** 0 samples. The output is stereo.
- **Not supported.** Aftertouch is ignored. The delay and LFO are not synced to the host tempo. There is no microtonal tuning.

FAQ

I hear no sound. Check that the channel is routed to a mixer track, that VOLUME is above zero and that CUTOFF is not at its minimum. Also check the AMP ENVELOPE: with SUSTAIN at zero, notes fade out by themselves. Many plucked presets are designed that way.

DZPOWER does not appear in FL Studio. Run the plugin manager scan again (**Options > Manage plugins > Find installed plugins**) and check that the VST3 file is in the standard VST3 folder.

Some presets are quieter than others. Plucks and drums are short and peak quickly, so they sound quieter than sustained pads at the same VOLUME. Raise VOLUME or balance the level in the mixer.

Can I play chords on every preset? Yes. Switch MONO / POLY to Poly. Mono presets, such as the Bendir Sub bank, are meant for single-note lines.

Can DZPOWER play quarter tones? No. The plugin has no microtonal tuning. Use a pitch bend or the GLIDE control to approach in-between pitches by ear.

Does it use samples? No. Every sound is generated in real time by the synthesis engines.

FUNKYKOPS

Funk, disco and G-Funk synthesizer: clavinet, electric piano, synth bass, brass, strings, lead, guitar and talkbox sounds from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

FUNKYKOPS is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Clavinet (a plucked-string model with a pickup “bite”), Rhodes (tine and bell partials with velocity “bark”), Synth Bass (a saw, a sub-octave sine and a square blend), Brass (three detuned saws), Strings (five detuned saws), Lead (saw plus square), Guitar (a short plucked string) and Talkbox (saws through vowel formants).

Five small character knobs (VOWEL, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and a master effects chain: distortion, chorus, ping-pong delay and reverb.

FUNKYKOPS targets Funk, Disco, G-Funk, Hip-Hop and Afrobeat productions: wah clavs, silky electric pianos, rubbery bass lines, horn stabs, string pads, whistle leads and robot-voice talkbox hooks. Most keys, brass, string and guitar presets load in Poly mode with up to 16 voices. The Synth Bass bank and most lead presets load in Mono mode for clean one-note lines.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **FUNKYKOPS** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **FUNKYKOPS - Init Patch**: the Clavinet engine in Poly mode.
3. Click the **Presets** button at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 96. Presets with TRANSPOSE at -12 (Bootsy Clav, Lowrider Keys, Bus Driver) sound one octave lower than the key you play; Bell EP, Trumpet Call, Closing Credits, Disco Ball Bell and Laser Zap are one octave higher.
5. Shape the sound with the main controls:
   - **CUTOFF**: the filter cutoff. Turn it down for a darker, rounder sound.
   - **BRIGHT**: the brightness of the selected engine.
   - **DECAY** (AMP ENVELOPE) and **SUSTAIN**: how long a note rings.
6. Adjust **VOLUME** to set the level, then click **Save** to store your own version.

Interface

The window opens at 1000 x 746 pixels. It has a fixed size.

Preset display (top center). From left to right: the **Presets** button (preset menu), the current preset name, the **<** and **>** arrows and the **Save** button. The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOX BEATS logo.

Center. The camel artwork, the FUNKYKOPS title and “By Humpire”. The speaker grilles are decorative.

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. The **TRANSPOSE** knob sits on the same row; it is the global transposition (-12 to +12 semitones) and is not an LFO control.

AMP ENVELOPE (left, below the LFO). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Center row. Two small character knobs, **VOWEL** and **BODY**, then the **GLIDE** and **CUTOFF** knobs, then three small character knobs, **BRIGHT, WIDTH** and **TEXTURE**.

FILTER ENV (top right). Two sliders, **DEPTH** (how far the filter envelope opens the cutoff) and **DECAY** (its decay and release time), followed by the **RESO** (filter resonance) and **VEL** (velocity sensitivity) sliders. RESO and VEL are separated from the filter envelope by a thin line because they are not part of it.

Effects and level (right). VOLUME (top), **REVERB, CHORUS, DISTORTION**, then **DELAY MIX, DLY TIME, FEEDBACK**.

Menu row. Five drop-down menus, each with a caption below it: **WAVEFORM** (the engine), **LFO SOURCE** (LFO shape), **LFO DESTINATION**, **FILTER TYPE** and **MONO / POLY**. Each menu shows its current value.

Wheels (bottom left). Pitch Bend springs back to the center when you release it. **Mod Wheel** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 36 to 96 (five octaves, 61 keys). The key labels run from C2 to C7, with middle C (MIDI 60) labeled C4; in FL Studio naming, where middle C is C5, the same range is C3 to C8. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

FUNKYKOPS exposes 32 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Control	Range	Default	What it does
WAVEFORM (Waveform menu)	Clavinet, Rhodes, Synth Bass, Brass, Strings, Lead, Guitar, Talkbox	Clavinet	Selects the synthesis engine.
VOWEL (Vowel / Attack)	0 to 1	0.5	Character control 1. Moves the vowel of the Talkbox engine; no effect on the other engines.

Control	Range	Default	What it does
BODY (Body / Resonance)	0 to 1	0.5	Character control 2. Engine-dependent (see the table below).
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width / Detune)	0 to 1	0.3	Character control 4. Engine-dependent (detune or sub level). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (pickup bite, noise, square blend…).
CUTOFF (Filter Cutoff)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RESO (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
DEPTH (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff by up to 5 octaves. At 0 the filter envelope has no effect.
DECAY, FILTER ENV (Filter Decay)	0.02 to 2 s	0.3 s	Decay and release time of the filter envelope. The filter envelope attacks in 2 ms and has a sustain level of zero.
VEL (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY, AMP ENVELOPE (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects.
GLIDE (Glide)	0 to 2 s	0	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.

Control	Range	Default	What it does
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SOURCE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
MONO / POLY (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (fixed rate).
DELAY MIX (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Mod Wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	VOWEL	BODY	BRIGHT	WIDTH	TEXTURE
Clavinet	No effect	String sustain (longer ring)	String brightness (damping)	No effect	Pickup bite (saturation)

Engine	VOWEL	BODY	BRIGHT	WIDTH	TEXTURE
Rhodes	No effect	Decay length of the tine and bell partials	Bell “bark”, stronger at high velocity	No effect	Attack noise
Synth Bass	No effect	No effect	Built-in low-pass opening	Sub-octave sine level	Blend from saw to square
Brass	No effect	No effect	Built-in low-pass opening	Detune of the three saws	Breath noise
Strings	No effect	No effect	Built-in low-pass opening	Detune of the five saws	No effect
Lead	No effect	No effect	Built-in low-pass opening	Detune	No effect
Guitar	No effect	String sustain (longer ring)	String brightness (damping)	No effect	No effect
Talkbox	Vowel (formant position)	Formant level	Brightness of the carrier	Detune of the three saws	Noise

Factory presets

FUNKYKOPS includes 70 factory presets in 7 banks of 10. 47 load in Poly mode and 23 in Mono mode. Mono presets are marked with an asterisk (*) below.

Clavinet & Funk Keys: Chicken Scratch, Disco Clav, Wah Patrol, Afro Clav, Stevie Stab, Funk Pickup, Bootsy Clav*, Siren Clav, Dusty Clav, Badge Clav.

Rhodes & EP: Rhodes Suitcase, Silk Rhodes, Bark Rhodes, Midnight EP, Disco EP, Tremolo EP, Slow Jam Keys, Wurly Bite, Bell EP, Lowrider Keys.

Synth Bass (all Mono): Funk Moog, *Dre Bass*, Rubber Bass, *Sub Cop*, Slap Synth, *G-Funk Whine Bass*, Disco Octave, *Acid Funk*, Bus Driver, *Mean Streets*.

Brass & Stabs: Horn Section, Funk Stab, Police Horns, Disco Brass, Swell Brass, Soft Flugel, Big Band Hit, Synth Brass 80, Sax Pad, Trumpet Call.

Strings & Disco: Disco Strings, Philly Strings, Cop Show Strings, Mirror Ball Pad, Slow Jam Pad, Staccato Strings, Lush Ensemble, String Machine, Velvet Pad, Closing Credits.

Leads & Talkbox: Funk Lead, *Chrome Lead*, G-Funk Whistle, *Talkbox Wah*, Robot Cop, *Vocoder Cruise*, *Squeal Lead*, Pop Lock Lead, *Midnight Cruiser*, Disco Solo*.

Guitar & FX: Chank Guitar, Funk Strum, Wah Guitar, Clean Pluck, Jazz Box, Muted Pick, Siren FX, *Radio Dispatch*, Disco Ball Bell, Laser Zap*.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click **Save** to save the current sound as a `.fkpreset` file. The default folder is `DJBILBOX BEATS/FUNKYKOPS/Presets` inside your Documents folder. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .fkpreset file…** in the same menu to load a file from another location. The preset display shows the file name. User presets store the sound parameters; the wheels are not stored.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Funk clav.** Start from Chicken Scratch or Stevie Stab. BRIGHT sets the string brightness and TEXTURE the pickup bite. Set VEL high (around 80%) so ghost notes and accents in the Piano roll sound different.
2. **Wah.** Wah Patrol uses a Low Pass filter with a low CUTOFF, DEPTH at 50% and a sine LFO on the filter. Raise DEPTH for a deeper quack on every note, or lower the LFO RATE for a slow sweep.
3. **Electric piano.** On the Rhodes engine, BRIGHT sets the bark that appears at high velocity and BODY sets how long the notes ring. Add CHORUS and REVERB for a wide, slow-jam sound (Midnight EP, Slow Jam Keys).
4. **G-Funk whine.** Use G-Funk Whine Bass for the bass and G-Funk Whistle for the lead. Both rely on GLIDE and a small LFO amount on pitch. Play them legato.
5. **Bass lines.** The Synth Bass bank loads in Mono mode. Raise DEPTH and shorten the filter DECAY for a rubbery pluck. Raise WIDTH to bring up the sub-octave sine, and use TEXTURE to move from saw to square.
6. **Horns and strings.** The Brass & Stabs bank plays chords in Poly mode. Raise the ATTACK slider for swells (Swell Brass) or set SUSTAIN to zero for stabs (Funk Stab). On the Strings engine, raise WIDTH and CHORUS for a wider ensemble (Lush Ensemble).
7. **Talkbox.** Choose the Talkbox engine and move VOWEL during the note, or automate it, to make the synth talk. Robot Cop and Talkbox Wah are good starting points.
8. **Slides.** With GLIDE above zero, every new note slides from the previous one, even if the notes do not overlap. For slides on selected notes only, keep GLIDE at 0 and automate it up just before those notes.

MIDI, automation and performance

Notes and channels. FUNKYKOPS responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VEL slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Mod Wheel. When both are used, the higher value wins. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) sets the CC1 value back to zero.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 32 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, pitch, bend, cutoff, distortion and delay changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. Effects set to zero are bypassed and cost no CPU. Mono mode and short release times keep the voice count low.

FAQ

FUNKYKOPS does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **FUNKYKOPS** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. Some presets use a low CUTOFF on purpose. Presets with TRANSPOSE -12 play one octave lower than the key. For notes outside the on-screen keyboard range (MIDI 36 to 96), play from a MIDI keyboard or the Piano roll.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The MONO / POLY menu is set to Mono, which is the default for the Synth Bass bank and most lead presets. Switch it to Poly (up to 16 voices).

The VOWEL knob does nothing. VOWEL only acts on the Talkbox engine. Select Talkbox in the WAVEFORM menu.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

GOLDHAWK

Golden, cinematic synthesizer: hawk leads, brass, pads, plucks, bells, strings, basses and eagle cries from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

GOLDHAWK is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Hawk Lead (two pulse waves with modulated width, a saw and a sub octave), Golden Brass (three saws with a self-opening filter), Royal Pad (five detuned saws and a sub, with a slowly breathing filter), Falcon Pluck (a saw with a pitch dive and a filter that closes), Sky Bells (FM bells), Feather Strings (five saws with a delayed vibrato), Talon Bass (detuned saws, sub and saturation) and Eagle Cry (a falling glissando with formant-filtered breath).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and a master effects chain: distortion, chorus, ping-pong delay and reverb. The character is royal, wide and cinematic.

GOLDHAWK targets epic and cinematic beats, trap and hip-hop melodies, anthem leads and brass hits, atmospheric pads, bell and pluck motifs, string beds, bass lines and risers or FX. Up to 16 voices can play at once in Poly mode. The lead, bass and cry presets that are meant for single-note lines load in Mono mode.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **GOLDHAWK** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **GOLDHAWK - Init Patch**: the Hawk Lead engine in Poly mode with default settings.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. Leads, brass, strings and pads sit well between MIDI notes 48 and 84 (C3 to C6 in FL Studio naming, where middle C is C5). The Talon Bass presets use TRANSPOSE at -12, so they sound one octave lower than the key you play.
5. Shape the sound with the main controls:
   - **TONE**, **BODY**, **BRIGHT**, **WIDTH**, **TEXTURE**: the character of the selected engine (small knobs at the left, under the cassette).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, rounder sound.
   - **GLIDE**: slide time between notes. Leave it at zero for straight notes.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message saying that expansion packs are coming soon. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The camel artwork, the GOLDHAWK title and “By Humpire”. The two dotted grilles on either side of the artwork are decorative.

Character knobs (under the cassette). Two rows of small knobs:

- Row 1: **TONE, BODY, BRIGHT, WIDTH**.
- Row 2: **TEXTURE, RESO** (filter resonance), **FLT ENV** (filter envelope depth) and **DLY MIX** (delay level).

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, placed under the LFO header, is the global transposition (-12 to +12 semitones). It is not an LFO control.

AMP ENVELOPE (left). Four sliders: **ATK, DEC, SUS, REL**.

FILTER ENVELOPE (top right). Three sliders: **ATK, DEC/REL, SUS**. The filter envelope uses its decay time for its release too, so there is no separate release slider. The **VEL** slider (velocity sensitivity of the level) sits just to the right of a thin divider line: it is not part of the filter envelope. The **VOLUME** knob is at the far right of this row.

EFFECTS (right). REVERB, **CHORUS** and **DISTORTION**.

DELAY (right). TIME and **FEEDBACK** knobs (delay time and delay repeats). The delay level is the **DLY MIX** knob in the character area.

Center bottom. The **GLIDE** knob and five menus. Four menus have a label to their left: **WAVEFORM** (engine), **LFO SOURCE** (LFO shape), **LFO DEST** (destination) and **MONO/POLY**. The **CUTOFF** knob and the **FILTER TYPE** menu sit to the right of them. Each menu shows its current value.

PITCH & MOD wheels (bottom left). Pitch Bend springs back to the center when you release it. **Mod Wheel** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 36 to 96 (five octaves plus one key, 36 white keys). The key labels on screen run from C2 to C7, with middle C labeled C4; in FL Studio naming, where middle C is C5, the same range is C3 to C8. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

GOLDHAWK exposes 34 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
WAVEFORM (Waveform menu)	Hawk Lead, Golden Brass, Royal Pad, Falcon Pluck, Sky Bells, Feather Strings, Talon Bass, Eagle Cry	Hawk Lead	Selects the synthesis engine.
TONE (Tone)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 1	0.3	Character control 4. Engine-dependent (detune, saturation, pitch-fall speed…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (noise, saw level, breath…).
CUTOFF (Filter Cutoff)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RESO (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
FLT ENV (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK, filter (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC/REL, filter (Filter Decay/Release)	0.02 to 4 s	0.3 s	Filter envelope decay time. The same value is used as the filter release time.
SUS, filter (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
VEL (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATK, amp (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DEC, amp (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUS, amp (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.
REL, amp (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.

Parameter	Range	Default	Function
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects.
GLIDE (Glide)	0 to 2	0	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SOURCE (menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DEST (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
MONO/POLY (menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (fixed rate).
DLY MIX (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.

Parameter	Range	Default	Function
Mod Wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Hawk Lead	Depth of the pulse-width modulation	Detune between the two pulse voices	Built-in low-pass opening	Speed of the pulse-width modulation	Level of the added saw
Golden Brass	Time the built-in filter takes to open	Output weight	How far the filter opens	Detune of the three saws	Breath noise
Royal Pad	No effect	Level of the sub octave	Built-in low-pass opening (modulated by a slow breathing movement)	Detune of the five saws	Noise
Falcon Pluck	Depth of the pitch dive at the attack	Length of the filter closing	Starting brightness of the filter	Detune of the second saw	Attack click (noise burst)
Sky Bells	Frequency ratio of the FM modulator	Length of the decay and of the FM brightness	FM depth	Detune of the second voice	Strike noise
Feather Strings	Position of the built-in formant filter	Level of the formant filter	Built-in low-pass opening	Vibrato depth	Noise
Talon Bass	Sub-octave level	Detune of the three saws	Built-in low-pass opening	Saturation drive	Noise
Eagle Cry	Depth of the falling pitch glide, and formant position	Level of the third harmonic	Level of the second harmonic	Speed of the pitch fall	Level of the formant-filtered breath

Factory presets

GOLDHAWK includes 70 factory presets in 7 banks of 10. 27 presets load in Mono mode and 43 load in Poly mode.

Hawk Leads (Hawk Lead engine): Goldhawk Lead, Soaring, Royal Pulse, Golden Wire, Sky Solo, Hawk Wide, Thermal, Eagle Eye, Golden Stab, Altitude. Eight load in Mono mode; Hawk Wide and Golden Stab load in Poly mode.

Golden Brass (Golden Brass engine): Golden Brass, Royal Fanfare, Hawk Stab, Imperial Horns, Soft Flugel, Slow Swell, Low Brass, Gold Rush Hit, Trumpet Call, Cinematic Brass. Only Trumpet Call loads in Mono mode.

Royal Pads (Royal Pad engine): Royal Pad, Golden Hour, Palace Air, Rising Hawk, Cloud Throne, Warm Gold, Dream Flight, Dusk Strings, Whisper Wind, Pulse Of Gold. All load in Poly mode.

Falcon Plucks (Falcon Pluck engine): Falcon Pluck, Gold Arp, Dive Zap, Muted Talon, Soft Feather, Pluck Choir, Golden Harp, Royal Koto, Rhythm Gate, Sad Hawk. All load in Poly mode.

Sky Bells & Strings (Sky Bells and Feather Strings engines): Sky Bell, Golden Chimes, Crystal Crown, Temple Bell, Music Box Gold, Feather Strings, Violin Flight, Slow Rise Strings, Dark Cellos, Pizz Gold. The first five use the Sky Bells engine and the last five use Feather Strings. Only Violin Flight loads in Mono mode.

Talon Bass (Talon Bass engine): Talon Bass, Gold Sub, Dirty Talon, Wobble Wing, Industrial Hawk, Slide Bass, Acid Talon, Deep Nest, Bass Stab, Meltdown Gold. All load in Mono mode with TRANSPOSE at -12.

Eagle Cry & FX (Eagle Cry engine): Eagle Cry, Hawk Screech, Distant Call, Falcon Dive, Wind Rush, Mountain Echo, Golden Whistle, Raptor Siren, Night Hunter, Thunder Wing. Seven load in Mono mode; Wind Rush, Night Hunter and Thunder Wing load in Poly mode.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.ghpreset` file. The default folder is `DJBILBOX BEATS/GOLDHAWK/Presets` inside your Documents folder. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .ghpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Anthem leads.** Start from Goldhawk Lead or Soaring. The Hawk Lead engine uses a pulse-width modulation: raise TONE for a deeper movement and WIDTH for a faster one. Use a little GLIDE (0.05 to 0.15) and play legato lines.
2. **Brass hits and fanfares.** Load Royal Fanfare, Hawk Stab or Gold Rush Hit in Poly mode and play chords. TONE sets how slowly the filter opens: keep it low for punchy hits, raise it for swells. Add REVERB and CHORUS for a wider sound.
3. **Cinematic pads and risers.** Royal Pad, Golden Hour and Cloud Throne have long attacks and releases. In Rising Hawk, the filter envelope (FLT ENV, with a long filter ATK) opens the filter slowly for a riser.
4. **Pluck and bell motifs.** In the Falcon Plucks and Sky Bells banks, shorten or lengthen the amplitude DEC slider to set the note length. On Sky Bells, TONE changes the FM ratio and BRIGHT the FM depth: small moves give very different bell colors.
5. **Strings.** Feather Strings adds a vibrato that starts about 0.2 seconds after the note. Raise WIDTH for a deeper vibrato and BODY for more formant color. Use a slow ATK for string beds.
6. **Bass lines.** The Talon Bass presets are in Mono mode and transposed down one octave. Raise TONE for more sub, WIDTH for more saturation. For a slide bass, see Slide Bass (GLIDE 0.25). For an acid sound, see Acid Talon (high FLT ENV with a short DEC/REL).
7. **Cries and FX.** Eagle Cry, Hawk Screech and Falcon Dive use the falling glissando of the Eagle Cry engine. Raise TONE for a larger pitch fall and TEXTURE for more breath. Wind Rush is a noise-based swell for transitions.
8. **Movement.** Set LFO DEST to Filter with a Sine LFO shape and a RATE between 1 and 4 Hz for a wobble. Set LFO DEST to Pitch with a small AMOUNT for vibrato, then bring the mod wheel up to add it only when you want it.

MIDI, automation and performance

Notes and channels. GOLDHAWK responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VEL slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Mod Wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) sets the CC1

value back to zero.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 34 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, pitch, bend and cutoff changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. Effects set to zero are bypassed and cost no CPU. Mono mode and short release times keep the voice count low. Pads with long releases and high polyphony use the most CPU.

FAQ

GOLDHAWK does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **GOLDHAWK** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Some presets use TRANSPOSE -12 and play very low. Short presets (stabs, Pizz Gold) are also quieter: raise VOLUME. Check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. For notes outside the on-screen keyboard range (MIDI 36 to 96), play from a MIDI keyboard or the Piano roll.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The MONO/POLY menu is set to Mono, which is the setting of the lead, bass and cry presets. Switch it to Poly (up to 16 voices).

The filter envelope has no release slider. The filter envelope has three sliders: ATK, DEC/REL and SUS. The DEC/REL time is used for both the decay and the release of the filter envelope. The VEL slider next to them controls velocity sensitivity, not the filter.

Does the delay or the LFO follow the tempo of my project? No. Delay time is set in seconds (0.05 to 1 s) and the LFO runs in Hz (0.05 to 20 Hz).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

HIGHROLLER GOLD

Casino-lounge synthesizer: gold bells, velvet keys, big band brass, organ, mallets, strings, gold sub and smoky pads from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

HIGHROLLER GOLD is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Gold Bell (FM bell), Velvet Keys (electric-piano style tines with a bell), Big Band Brass (three detuned saws with an opening filter), Vegas Organ (drawbars with percussion and key click), Roulette Mallets (struck bars with tremolo), Silk Strings (five detuned saws with a slow drift), Gold Sub (a sine sub with pitch “knock” and saturation) and Cigar Smoke (a detuned saw pad with breath noise and a filter that slowly breathes).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb.

The sound is built for Hip-Hop, Trap and R&B keys and hooks, lounge and soul chords, brass stabs and pads, bell toplines and 808-style subs. The Gold Sub & Bass bank loads in Mono mode for clean one-note lines. All other banks load in Poly mode, with up to 16 voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **HIGHROLLER GOLD** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **HIGHROLLER GOLD - Init Patch**: the Gold Bell engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 48 to 96. Click a key to hear the sound.
5. Shape the sound with the main controls:
   - **TONE**: the main character of the engine (bell ratio, hardness, drawbar level, string or pad color…).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, rounder sound.
   - **RELEASE** (in AMP ENVELOPE): how long the note rings after you let go.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 500 x 373 up to 2000 x 1492 pixels. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens a message saying that expansion packs are coming soon. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The camel artwork, the HIGHROLLER GOLD title and “By Humpire”. The dotted grille around the artwork is decorative.

Character knobs (row above the artwork). TONE, BODY, BRIGHT, WIDTH, TEXTURE: the five character controls of the selected engine.

Left side.

- **LFO** section: **RATE** and **AMOUNT** set the LFO speed and depth.
- **TUNING** section: **TRANSPOSE**, the global transposition (-12 to +12 semitones). It is not an LFO control.
- **AMP ENVELOPE**: four sliders, **ATTACK, DECAY, SUSTAIN, RELEASE**.
- Small knobs **RES** (filter resonance) and **FLT ENV** (filter envelope depth).
- **GLIDE** knob.

Right side.

- **FILTER ENVELOPE**: four sliders **ATK, DEC, SUS, REL**, plus the **VELOCITY** slider (velocity sensitivity of the level) just to their right.
- **VOLUME** knob (output level), **CUTOFF** knob (filter cutoff).
- **REVERB, CHORUS, DISTORTION** knobs.
- **DLY MIX** (delay level), **DLY TIME** and **FEEDBACK** knobs.

Menu row. Five drop-down menus, each with a caption below it: **ENGINE**, **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE** (Poly or Mono). Each menu shows its current value.

Wheels (bottom left). Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 48 to 96 (four octaves plus one key). The key labels on screen run from C2 to C6, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C4 to C8. It always shows the whole range and does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

HIGHROLLER GOLD exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Gold Bell, Velvet Keys, Big Band Brass, Vegas Organ, Roulette Mallets, Silk Strings, Gold Sub, Cigar Smoke	Gold Bell	Selects the synthesis engine.

Parameter	Range	Default	Function
TONE (Tone)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width)	0 to 1	0.3	Character control 4. Engine-dependent (detune, tremolo depth, drift…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (noise, saturation, speed…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
FLT ENV (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7	Output level of each voice, before the effects. Shown in dB.

Parameter	Range	Default	Function
GLIDE (Glide)	0 to 2	0	Portamento. Higher values give a slower slide. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Modulation wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Gold Bell	Ratio of the FM modulator (bell color)	Length of the ring	FM depth (brightness of the strike)	Slight detune between the two carriers	Noise click at the attack
Velvet Keys	No effect	Length of the tines	“Bark” (upper partials), stronger with higher velocity	No effect	Attack noise
Big Band Brass	Time the filter takes to open	Output weight	How far the filter opens	Detune of the three saws	Breath noise
Vegas Organ	Level of the sub-octave drawbar	Level of the 2nd harmonic drawbar	Level of the upper drawbars	Percussion at the attack	Key click
Roulette Mallets	Mallet noise at the attack	Length of the ring	Level of the upper partials	Tremolo depth	Tremolo speed
Silk Strings	Position of the body resonance	Level of the body resonance	Filter opening	Detune and drift of the five saws	Speed of the slow drift
Gold Sub	Pitch “knock” at the attack	Adds the octave harmonic	Attack click	No effect	Saturation
Cigar Smoke	No effect	Level of the sub layer	How far the filter opens	Detune of the five saws	Breath noise

Factory presets

HIGHROLLER GOLD includes 70 factory presets in 7 banks of 10. The Gold Sub & Bass bank loads in Mono mode. In the Big Band Brass bank, only Cigar Lounge Horn is in Mono mode. Every other preset loads in Poly mode.

Gold Bells & Jackpot: Jackpot Bell, Gold Coin, Slot Machine, Casino Chimes, Velvet Box, Crystal Chandelier, Low Gong, Ring Of Fortune, Lucky Seven, Winner Echo.

Velvet Keys: Velvet Rhodes, High Stakes Keys, Bark EP, Lounge Keys, Tremolo Velvet, After Dark EP, Wurly Bite, Gilded Bell EP, Penthouse Chords, Tape Velvet.

Big Band Brass: Big Band Brass, High Roller Horns, Brass Stab, Soft Flugel, Slow Swell, Vegas Fanfare, Muted Horn, Sax Section, Disco Hit, Cigar Lounge Horn.

Vegas Organ: Vegas Organ, Smoky Lounge, Full Drawbars, Gospel Gold, Casino Floor, Perc Organ, Soft Flute Stop, Rotary Dream, Tape Organ, Golden Swell.

Mallets & Strings: Roulette Vibes, Gold Marimba, Chip Stack, Slow Motor Vibes, Dealer’s Hand (Roulette Mallets engine), then Silk Strings, Velvet Strings, Slow Rise Strings, Dark Cellos, Pizz Casino (Silk Strings engine).

Gold Sub & Bass: Gold 808, Long Slide Gold, Dirty Gold, Boom Bap Sub, Hard Knock, Deep Vault, Short Gold, Smooth Sub, Pitch Drop Gold, Rumble Royale.

Cigar Smoke Pads: Cigar Smoke, Smoky Backroom, Velvet Curtain, Golden Haze, High Roller Rise, Midnight Casino, Whisper Table, Vault Drone, Pulse Of Luck, Final Hand.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.hgpreset` file. The default folder is `DJBILBOX BEATS/HIGHROLLER_GOLD/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .hgpreset file…** in the same menu to load a file from another location.

The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Hooks and toplines.** Start from Jackpot Bell, Gold Coin or Crystal Chandelier. Raise TONE to change the bell color and BODY for a longer ring. Add REVERB and a little DLY MIX with DLY TIME at 0.375 s for a sparkling top layer.
2. **Soul and R&B chords.** The Velvet Keys bank plays chords in Poly mode. Raise BRIGHT for more bite on hard notes, and keep the VELOCITY slider around 60 to 80% so your Piano roll accents come through. Add CHORUS for width.
3. **Brass stabs and swells.** In Big Band Brass, shorten DECAY and SUSTAIN for stabs (Brass Stab, Disco Hit) or raise ATTACK for swells (Slow Swell). TONE sets how fast the filter opens.
4. **Organ beds.** Vegas Organ mixes drawbar levels with TONE, BODY and BRIGHT. WIDTH adds percussion at the attack and TEXTURE adds key click. Set LFO DESTINATION to Amp for a tremolo, as a starting point for rotary-style movement.
5. **Vibes and marimba.** In Roulette Mallets, WIDTH sets the tremolo depth and TEXTURE its speed. Lower RELEASE for dry, tight hits.
6. **Strings and pads.** Silk Strings and Cigar Smoke use detuned saws. Raise ATTACK and RELEASE for slow pads, and WIDTH for a thicker sound. In Cigar Smoke, BRIGHT opens the filter and the filter slowly breathes by itself.
7. **808 subs.** Load a Gold Sub & Bass preset (Gold 808, Long Slide Gold). Raise TONE for a harder knock. Raise TEXTURE or add a little DISTORTION so the sub stays audible on phone and laptop speakers.
8. **Slides.** With GLIDE above zero, every new note slides from the previous one, even if the notes do not overlap. For slides on selected notes only, keep GLIDE at 0 and automate it up just before the notes that should slide.
9. **Filter movement.** Raise FLT ENV and shorten the filter DEC slider for a plucked attack. For a wobble, set LFO DESTINATION to Filter and RATE between 1 and 4 Hz.

MIDI, automation and performance

Notes and channels. HIGHROLLER GOLD responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. A new note starts with the latest CC1 value. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead.

Other MIDI. The sustain pedal (CC64) is supported. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, pitch, bend and cutoff changes are smoothed to avoid clicks. Distortion and delay level changes are smoothed too.

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

Output. Stereo output. Each note gets a slight random position in the stereo field.

FAQ

HIGHROLLER GOLD does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **HIGHROLLER GOLD** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. Some presets have a very slow ATTACK (pads and swells) or a long fade-in, so hold the note for a moment. For notes outside the on-screen keyboard range (MIDI 48 to 96), play from a MIDI keyboard or the Piano roll.

My sub is not perfectly centered. Each note gets a slight random stereo offset. For a strictly centered sub, reduce the stereo separation of the mixer track in FL Studio, or insert a mono utility after HIGHROLLER GOLD. If the sub is also weak on small speakers, add harmonics with TEXTURE, BODY or DISTORTION.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for the Gold Sub & Bass presets. Switch it to Poly (up to 16 voices).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

HUMPIRE CLUTCH

Compressor with Clean, Punch and Crush modes, soft knee, sidechain high-pass, parallel mix and a LED life bar.

Type	Audio effect (compressor)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Modes	Clean, Punch, Crush
Factory presets	12
Latency	0 samples

Overview

HUMPIRE CLUTCH is a feed-forward compressor with a soft knee. A one-pole **sidechain high-pass** filter keeps low frequencies from triggering the compression, and the detector is stereo-linked (it follows the louder of the two channels). The **MIX** knob blends the dry signal with the compressed signal for parallel compression.

The **MODE** button switches between three characters. **Clean** compresses exactly as the knobs say. **Punch** triples the attack time (plus 4 ms) and shortens the release to 70%, so the start of each note passes through before the compression grabs it. **Crush** multiplies the ratio by 1.8 (up to 30:1), shortens the attack to 30% and adds saturation to the compressed signal.

The screen shows gain reduction as a **life bar** of 32 segments that drains as you compress (24 dB of reduction empties it), a numeric **GR** reading, a **HIT!** flash when a sudden reduction occurs and a history graph of the last moments.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE CLUTCH** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Play your track and lower **THRESH** until the life bar drains by 3 to 6 dB on the loud notes.
4. Choose the **RATIO**. Low values (2 to 3) are gentle. High values (8 and more) limit the signal.
5. Adjust **ATTACK** and **RELEASE**. A slower attack lets more of the transient through.
6. Use **MAKEUP** to bring the level back, and **MIX** below 100% for parallel compression.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.
- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.

- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Screen. At the top, **VITALITY** and the gain reduction in dB (**GR**). Below, the life bar: green-amber at the right when there is little reduction, going to orange and red as reduction grows. Under the bar, **HIT!** appears when a new reduction of more than 0.6 dB hits. At the bottom, the reduction history: the line goes down the screen as the reduction increases (24 dB at the bottom).

Knobs. THRESH, **RATIO**, **ATTACK**, **RELEASE**, **KNEE**, **SC HPF**, **MAKEUP**, **MIX**. In SIMPLE mode, **KNEE** and **SC HPF** are hidden.

Button. CLEAN / PUNCH / CRUSH (each click goes to the next mode).

Parameters

Control	Host name	Range	Default	Function
MODE button	Mode	Clean, Punch, Crush	Clean	Compression character. See the Overview.
THRESH	Threshold	-40 to 0 dB	-18 dB	Level above which compression starts.
RATIO	Ratio	1:1 to 20:1	4:1	Amount of compression. In Crush mode the ratio is multiplied by 1.8 (up to 30:1).
ATTACK	Attack	0.1 to 100 ms	10 ms	How fast the compressor reacts. Punch mode makes it slower (3x + 4 ms), Crush mode faster (30%).
RELEASE	Release	10 to 1000 ms	120 ms	How fast the compression lets go. Punch mode shortens it to 70%.
KNEE	Knee	0 to 24 dB	6 dB	Softness of the transition around the threshold.
MAKEUP	Makeup	-12 to +24 dB	0 dB	Gain applied after compression.
SC HPF	SC HPF	20 to 500 Hz	60 Hz	High-pass filter in the detector path only. The audio itself is not filtered.

Control	Host name	Range	Default	Function
MIX	Mix	0 to 1	1.00	Blend between the dry signal (0) and the compressed signal (1).
BYPASS	Bypass	Off / On	Off	Passes the audio through.

CLUTCH has 10 automatable parameters. In Crush mode the compressed signal passes through a saturator before the mix.

Factory presets

CLUTCH includes 12 factory presets.

Trap Vocals: Trap Vocal Lead, Ad-Lib Squash, Vocal Glue.

808: 808 Tamer, 808 Sustain.

Kick: Kick Punch, Kick Crush.

Oud: Oud Smooth.

Darbouka: Darbouka Snap.

Bus Drums: Bus Drums Glue, Parallel Smash.

Master: Master Gentle.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\CLUTCH\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/CLUTCH/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Vocals.** Start from **Trap Vocal Lead** or **Vocal Glue**. Keep gain reduction between 3 and 6 dB.
- **808s. 808 Tamer** controls peaks with a high ratio and a slow release. Lower **SC HPF** (25 to 30 Hz in the presets) so the sub still triggers the detector.
- **Drum punch.** Use **Punch** mode on kicks and snares: the slower attack keeps the click.
- **Parallel smash.** Choose **Crush** mode, lower the **MIX** to 40% to 70% and bring back the level with **MAKEUP** (see **Parallel Smash** and **Ad-Lib Squash**).
- **Bus glue.** Use a ratio of 2:1 with a slow attack and a long release (see **Bus Drums Glue**).

FAQ

Does it add latency? No. CLUTCH has no look-ahead.

What does the HIT! text mean? The gain reduction suddenly grew by more than 0.6 dB: the compressor just caught a loud hit.

Why do I not see KNEE and SC HPF? They are hidden in SIMPLE mode. Click SIMPLE at the top right to show them.

Is it stereo-linked? Yes. The detector follows the louder channel, so the stereo image does not shift.

HUMPIRE COMBO

Four one-shot performance effects (stutter, tape stop, filter sweep and reverse) on a game-controller panel with two XY pads and MIDI learn.

Type	Audio effect (performance FX, MIDI-triggered)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	12
Effects	Stutter, Tape Stop, Sweep, Reverse
MIDI	Notes 36 to 39 by default, MIDI learn
Audio buffer	4 seconds
Latency	0 samples

Overview

HUMPIRE COMBO is an effect you play. Four buttons trigger four one-shot effects while you hold them: **STUTTER**, **TAPE STOP**, **SWEEP** and **REVERSE**. Two XY pads (the two sticks of the controller) set how each effect behaves, and two triggers set the drive and the effect mix.

- **Stutter** repeats the last slice of audio. The length follows the host tempo and comes from the **left pad X axis**, in four steps: 0.125, 0.25, 0.5 or 1 beat.
- **Tape stop** slows the audio down to a halt, like a turntable or tape stopping. Its duration comes from the **right pad X axis**, from 0.1 to 2 seconds.
- **Sweep** closes a resonant low-pass filter from 18 kHz down to a target frequency from the **left pad Y axis** (40 Hz to 18 kHz).
- **Reverse** plays the most recent audio backwards. The length follows the host tempo and comes from the **right pad Y axis**: 0.25, 0.5, 1 or 2 beats.

The four effects can also be triggered from **MIDI notes**. By default, notes 36, 37, 38 and 39 trigger Stutter, Tape Stop, Sweep and Reverse. **MIDI LEARN** lets you choose other notes.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE COMBO** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Make sure the plugin receives MIDI if you want to play it from a keyboard (in FL Studio, open the plugin wrapper settings and select a MIDI input port for your controller). Mouse use needs no MIDI.
4. Press and hold **STUTTER**, **TAPE STOP**, **SWEEP** or **REVERSE** with the mouse. The effect runs while you hold the button.
5. Move the XY pads to change the rate, the filter, the tape time and the reverse length.
6. Raise the **L TRIG** slider for drive and lower the **R TRIG** slider for a lower effect mix.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display. COMBO has no advanced knobs, so SIMPLE has no visible effect.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.
- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.
- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Display (top center). The four effect names with a dot for each active effect, the current stutter length in milliseconds, the sweep target frequency in Hz, and, at the bottom, either `NOTES 36-39` (the current MIDI note range) or `LEARN: PRESS FX THEN NOTE` while MIDI learn is on.

Buttons (under the display). STUTTER, **TAPE STOP**, **SWEEP** and **REVERSE** are active while the button is held down. **MIDI LEARN** is an on/off switch.

Left stick. X: STUTTER RATE, **Y: FILTER** (sweep target).

Right stick. X: TAPE TIME, **Y: REVERSE LEN**.

Triggers. L TRIG: DRIVE and **R TRIG: MIX**, two vertical sliders between the sticks.

Parameters

Control	Host name	Range	Default	Function
STUTTER button	FX stutter	Off / On	Off	Holds the stutter effect.
TAPE STOP button	FX tapestop	Off / On	Off	Holds the tape stop effect.
SWEEP button	FX sweep	Off / On	Off	Holds the filter sweep.
REVERSE button	FX reverse	Off / On	Off	Holds the reverse effect.
Left stick X	Stick L X (Stutter Rate)	0 to 1	0.50	Stutter length in four steps: below 0.25 = 0.125 beat, 0.25 to 0.5 = 0.25 beat, 0.5 to 0.75 = 0.5 beat, above 0.75 = 1 beat.
Left stick Y	Stick L Y (Filter)	0 to 1	0.50	Sweep target cutoff, from 40 Hz (0) to 18 kHz (1), on a logarithmic scale.

Control	Host name	Range	Default	Function
Right stick X	Stick R X (Tape Time)	0 to 1	0.50	Tape stop time, from 0.1 s (0) to 2 s (1).
Right stick Y	Stick R Y (Reverse Len)	0 to 1	0.50	Reverse length: 1/4, 1/2, 1 or 2 beats in four steps.
L TRIG	Trigger L Drive	0 to 1	0.00	Saturation applied to the effect signal (up to 10x gain, level compensated).
R TRIG	Trigger R Mix	0 to 1	1.00	Amount of the effect blended with the dry signal.
MIDI LEARN	MIDI Learn	Off / On	Off	Not automatable. Assigns an effect to a MIDI note.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

COMBO has 13 parameters; MIDI Learn and the interface switches are not automatable. The MIDI note assignments are saved with your project.

MIDI mapping. The plugin accepts MIDI notes. By default: note 36 = Stutter, 37 = Tape Stop, 38 = Sweep, 39 = Reverse. The effect runs while the note is held. To remap: click **MIDI LEARN**, hold one of the four effect buttons (the display shows `LEARN: PRESS FX THEN NOTE`), then play the note you want. Learning stops after one note.

Factory presets

COMBO includes 12 factory presets. They set the sticks and the triggers; they do not turn effects on by themselves.

Trap Vocals: Trap Stutter 1/16, Ad-Lib Throw.

808: 808 Tape Dive, 808 Slow Stop.

Kick: Kick Roll 1/32, Kick Reverse.

Oud: Oud Reverse Swell, Oud Filter Close.

Darbouka: Darbouka Stutter.

Bus Drums: Bus Drums Freeze, Bus Filter Drop.

Master: Master Tape Stop.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\COMBO\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/COMBO/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Fills and transitions.** Hold **STUTTER** for the last beat of a bar. Move the left stick left for faster stutters.
- **808 dives. 808 Tape Dive** and **808 Slow Stop** use long tape-stop times.
- **Reverse swells. Oud Reverse Swell** uses the longest reverse length.

- **Filter drops. Bus Filter Drop** and **Oud Filter Close** lower the sweep target.
- **Automate the buttons.** In FL Studio, you can create automation clips of the four FX buttons for repeatable moves.

FAQ

Nothing happens when I play MIDI notes. Check that the plugin has a MIDI input in your host (in FL Studio, open the plugin wrapper settings and select a MIDI input port). The default notes are 36 to 39.

Do the effects follow my tempo? The stutter and reverse lengths do. The tape stop time is in seconds. Without a tempo from the host, 120 BPM is assumed.

Why do the effects stop when I release the button? They are one-shot effects held by the button or the note, by design.

How long is the buffer? The plugin keeps the last 4 seconds of audio.

HUMPIRE GLITCH

Lo-fi effect on a handheld-console body: bit crusher from 1 to 16 bits, sample-rate reducer, speaker filter and dither.

Type	Audio effect (lo-fi / bitcrusher)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	20
Bit depth	1 to 16 bits (fractional values allowed)
Sample rate	500 Hz to 48 kHz
Latency	0 samples

Overview

HUMPIRE GLITCH degrades the sound on purpose. The signal goes through a **drive** stage (soft saturation), a **sample-rate reducer** (sample and hold, with intentional aliasing), a **dither** stage and a **bit quantizer**. The **speaker** switch then adds a small-speaker simulation: the signal is summed to mono, filtered by a high-pass and a low-pass whose cutoffs follow the **SIZE** knob, and softly saturated.

The interface is a handheld console. A four-tone LCD shows the current settings (bits, rate, dither, speaker and mix). The **D-pad** changes the bit depth (up and down) and the sample rate (left and right). Button **A** cycles the dither and button **B** switches the speaker on or off.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE GLITCH** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Lower **BITS** and **RATE** until the sound gets the crunch you want. 8 bits and 16 kHz is a classic starting point.
4. Use **MIX** to blend the crushed sound with the original.
5. Switch the speaker on with button **B** for a radio or telephone sound, and adjust **SIZE**.
6. Click **SELECT** (SIMPLE) to show or hide the advanced knobs.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. In GLITCH, the SIMPLE and CLEAN switches are the **SELECT** and **START** buttons of the console.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.
- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.
- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.

- **SELECT** (SIMPLE) hides the advanced knobs and keeps the essential ones. **START** (CLEAN) replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable. GLITCH starts in SIMPLE mode.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

LCD (center). Two lines of text: `BITS 8.0 RATE 48K` and `DITH OFF SPK OFF MIX 100`. In bypass, the LCD shows `** BYPASS **` and is dimmed. A LED at the upper left shows that the plugin is powered.

D-pad (bottom left). Up raises the bits by one, down lowers them by one. Right raises the sample rate by about 26%, left lowers it by the same factor.

Buttons. A (**DITHER**): each click goes to the next dither mode (Off, RPDF, TPDF). **B** (**SPEAKER**): switches the speaker filter on or off. **SELECT** (**SIMPLE**) and **START** (**CLEAN**) are on/off switches with a LED.

Knobs. BITS, **RATE**, **SIZE**, **DRIVE**, **MIX** and **OUT**. In SIMPLE mode, only **BITS**, **RATE** and **MIX** are visible.

Parameters

Signal flow: input, drive, sample-rate reducer, dither, bit quantizer, speaker filter (if on), mix with the dry signal, output gain.

Control	Host name	Range	Default	Function
BITS (or D-pad up/down)	Bits	1 to 16 bits	8.0	Bit depth of the quantizer. Fractional values are allowed.
RATE (or D-pad left/right)	Sample Rate	500 Hz to 48 kHz	48 kHz	Target sample rate of the reducer. At 48 kHz the reducer does nothing.
DRIVE	Drive	0 to 100 %	0 %	Soft saturation before the crusher. Transparent at 0.
B button	Speaker	Off / On	Off	Mono small-speaker filter with soft saturation.
SIZE	Speaker Size	0 to 100 %	40 %	Size of the speaker: high-pass from 500 Hz (small) to 120 Hz (large), low-pass from 3.5 kHz (small) to 8 kHz (large).
A button	Dither	Off, RPDF, TPDF	Off	Noise added before quantization to smooth the distortion of low bit depths.
MIX	Mix	0 to 100 %	100 %	Dry/wet balance.
OUT	Output	-24 to +12 dB	0 dB	Output gain.

Control	Host name	Range	Default	Function
BYPASS	Bypass	Off / On	Off	Passes the audio through.

GLITCH has 9 automatable parameters. The settings are smoothed over about 30 ms to avoid clicks. The speaker filter gets its signal from the crushed audio and can be mixed with the dry signal.

Factory presets

GLITCH includes 20 factory presets, grouped by the instrument they suit.

Trap Vocals: Radio Crush, Telephone Ad-Lib, Dusty Vocal Chop, Megaphone Hook.

808: Dirty Sub 12bit, 808 Grit, Sampler Crunch 808.

Kick: 8-Bit Punch, Boom Bap Dust, Hard Clip Kick.

Oud: Cassette Oud, Old Souk Radio, Ghost Strings.

Darbouka: Darbouka Alley, Tin Can Tabla.

Bus Drums: Crushed Drum Bus, Parallel Dirt, Lo-Fi Loop Glue.

Master: Master Tape Hint, Old Console Preview.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\GLITCH\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/GLITCH/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Dusty vocal chops. Dusty Vocal Chop** uses 9 bits, 22 kHz and TPDF dither at 70% mix.
- **Radio and telephone. Radio Crush** and **Telephone Ad-Lib** turn the speaker on with a small size.
- **Gritty 808s. Dirty Sub 12bit** and **808 Grit** keep the sub but add texture. Check the low end after crushing.
- **Parallel dirt.** Keep MIX at 25% to 50% on a drum bus (**Parallel Dirt**, **Crushed Drum Bus**).
- **Tape feel. Master Tape Hint** uses 15 bits at 15% mix, a very light touch.
- **Extreme. Old Console Preview** uses 4 bits and 8 kHz.

FAQ

Does it add latency? No. The plugin reports 0 samples.

Why do I only see three knobs? GLITCH starts in SIMPLE mode. Click SELECT to see all six.

What does dither do? It adds a little noise before the quantizer, so quiet details are less distorted. RPDF is a flat noise, TPDF is a triangular noise that fully decorrelates the error.

Why does it sound worse when I lower the rate? That is the point: the sample-rate reducer creates aliasing on purpose.

HUMPIRE HARDCAP

Look-ahead true-peak limiter with automatic release and momentary, short-term and integrated LUFS meters.

Type	Audio effect (master limiter)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	12
Look-ahead	1 to 5 ms
Latency	About half of the look-ahead time, reported to the host

Overview

HUMPIRE HARDCAP is a look-ahead limiter for the end of your master chain. **GAIN** raises the input level by up to 24 dB, and the **CEILING** (from -6 to 0 dBTP) sets the maximum output level. Because the limiter looks ahead (1 to 5 ms), it lowers the gain before a peak arrives, so the attack is instantaneous.

With **TRUE PEAK** on, the plugin estimates the peaks between samples with a cubic interpolation, so the output does not exceed the ceiling after conversion. With **AUTO REL** on, the release time adapts automatically to the material (between 40 and 300 ms); with it off, the **RELEASE** knob sets it from 10 to 500 ms.

The screen shows three loudness readings based on the BS.1770 K-weighting method: **MOMENTARY** (400 ms), **SHORT-TERM** (3 seconds) and **INTEGRATED** (since the start), plus a LED strip from -30 to 0 LUFS with a target marker and a gain-reduction bar. When the integrated loudness stays within half a LU of the target for two seconds, **LEVEL UP!** is displayed.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE HARDCAP** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Put HARDCAP on the **last slot** of the Master track.
4. Set the **TARGET** to the loudness you aim for (for example -14 LUFS for streaming) and raise **GAIN** while you watch the gain reduction bar. A few dB of reduction is normal.
5. Keep **TRUE PEAK** on and **CEILING** at -1 dBTP for streaming platforms.
6. Play the whole song and read the **INTEGRATED** value. Raise or lower GAIN until it is near the target.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.

- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.
- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Screen. Three large readings (**MOMENTARY**, **SHORT-TERM**, **INTEGRATED**) in LUFS (shown as `---` below -69 LUFS). Under them, the LED strip with the **TARGET** marker (white line). At the bottom, **GAIN REDUCTION** with a bar (full scale 12 dB) and the value in dB.

Knobs. GAIN, **CEILING**, **RELEASE**, **LOOKAHEAD**, **TARGET**. In SIMPLE mode, **LOOKAHEAD** is hidden.

Buttons. AUTO REL and **TRUE PEAK** (each is an on/off switch with a LED).

Parameters

Control	Host name	Range	Default	Function
GAIN	Input Gain	0 to 24 dB	0 dB	Gain before the limiter.
CEILING	Ceiling	-6 to 0 dBTP	-1 dBTP	Maximum output level.
RELEASE	Release	10 to 500 ms	100 ms	Release time when AUTO REL is off.
LOOKAHEAD	Lookahead	1 to 5 ms	2 ms	Look-ahead time. Longer values are smoother and add more latency.
TARGET	Target LUFS	-24 to -6 LUFS	-14 LUFS	Loudness target shown on the meter.
AUTO REL	Auto Release	Off / On	On	Automatic release between 40 and 300 ms depending on the gain reduction.
TRUE PEAK	True Peak	Off / On	On	Detects peaks between samples.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

HARDCAP has 8 automatable parameters. The loudness meters do not change the audio.

About the LUFS meters. The meters follow the BS.1770 method (K-weighting and 100 ms blocks), but the integrated value uses an approximated gating. Use them as a guide, and confirm your final master with the loudness tool you normally use.

Latency. The limiter delays the audio by about half of the look-ahead time (1 ms at the default of 2 ms) and reports it to the host.

Factory presets

HARDCAP includes 12 factory presets.

Master: Streaming -14, Club Loud -9, Afrotrap Master, Deep House Smooth, Oriental Dynamic, G-Funk Warm, Hip-Hop Punch, Safe -16 LUFS.

Bus Drums: Bus Drums Catch.

808: 808 Guard.

Trap Vocals: Trap Vocal Safety.

Kick: Kick Ceiling.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\HARDCAP\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/HARDCAP/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Streaming.** Start from **Streaming -14** with a ceiling of -1 dBTP.
- **Club loudness. Club Loud -9** raises the gain to 7 dB with a faster release.
- **Protect an 808. 808 Guard** or **Kick Ceiling** on a single track can catch occasional peaks.
- **Do not over-limit.** If the gain reduction bar stays above 4 to 6 dB all the time, lower GAIN.
- **Leave headroom.** Do not put anything after HARDCAP except metering.

FAQ

Does it add latency? Yes, about half of the look-ahead time, reported to the host.

Why does the INTEGRATED reading show —? The signal has been too quiet (below -69 LUFS) or nothing has played yet.

What does LEVEL UP! mean? The integrated loudness stayed within half a LU of the target for two seconds.

Is the meter certified? No. It is a guide.

HUMPIRE LAG

Stereo delay with BPM sync, filtered feedback, ducking, ping-pong mode and four snapshots you can morph between.

Type	Audio effect (stereo delay)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	12
Delay time	1 ms to 2 s per side
Reported tail	30 seconds
Latency	0 samples

Overview

HUMPIRE LAG is a stereo delay with separate left and right times. Each side can run in milliseconds (1 ms to 2 s) or be **synced** to the host tempo with eight divisions: 1/16, 1/8, dotted 1/8, triplet 1/8, 1/4, dotted 1/4, 1/2 and 1/1. The feedback (up to 95%) passes through a **low cut** and a **high cut** filter, and a soft saturator in the feedback path keeps long repeats under control. **DUCK** lowers the echoes while the input signal is loud. **PING-PONG** feeds the input into the left delay only and sends the repeats back and forth between the two sides.

Four **snapshots** (slots A to D) store the time, feedback, filter, ducking and mix settings. Picking a slot makes the delay **morph** smoothly to those settings over a time you set with the **MORPH** knob.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE LAG** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Click **SYNC** to follow the host tempo, then use the two division buttons to choose the left and right note values. Click a division button to go to the next value.
4. Set **FEEDBACK** for the number of repeats, and **MIX** for the level of the echoes.
5. Use **DUCK** so the echoes appear in the gaps between words or notes.
6. To store a snapshot: click **STORE**, then click a slot (A to D). To recall it, click the slot.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.
- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.
- **UNDO** and **REDO** step through your recent control changes and preset loads.

- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Screen. Two lanes, **L** (amber) and **R** (violet). Each lane shows the source and its repeats as vertical bars that fade according to the feedback, and a moving light. The screen also shows the time of each side in milliseconds.

Knobs. TIME L, **TIME R**, **FEEDBACK**, **LOW CUT**, **HIGH CUT**, **DUCK**, **MIX** and **MORPH**. In SIMPLE mode, **LOW CUT**, **HIGH CUT**, **DUCK** and **MORPH** are hidden.

Buttons. SYNC, **PING-PONG**, the left division button (shows its current value, default 1/4) and the right division button (default 1/4 D). When SYNC is off, the time knobs set the delay; when SYNC is on, the division buttons do.

Snapshot row (bottom). SLOT A, **SLOT B**, **SLOT C**, **SLOT D** and **STORE**. A LED shows the active slot.

Parameters

Control	Host name	Range	Default	Function
TIME L	Time L	1 to 2000 ms	375 ms	Left delay time when SYNC is off.
TIME R	Time R	1 to 2000 ms	375 ms	Right delay time when SYNC is off.
SYNC	Sync	Off / On	Off	Follows the host tempo. Without a tempo from the host, 120 BPM is assumed.
Left division button	Division L	1/16, 1/8, 1/8 D, 1/8 T, 1/4, 1/4 D, 1/2, 1/1	1/4	Left note value when SYNC is on.
Right division button	Division R	Same	1/4 D	Right note value when SYNC is on.
FEEDBACK	Feedback	0 to 0.95	0.35	Amount of signal sent back into the delay.
LOW CUT	Low Cut	20 Hz to 1 kHz	100 Hz	High-pass filter inside the feedback loop.
HIGH CUT	High Cut	1 kHz to 20 kHz	8 kHz	Low-pass filter inside the feedback loop.
DUCK	Ducking	0 to 1	0.00	Lowers the echoes while the input is loud.
MIX	Mix	0 to 1	0.30	Level of the echoes added to the dry signal.
PING-PONG	Ping-Pong	Off / On	Off	Sends the repeats back and forth between left and right.

Control	Host name	Range	Default	Function
MORPH	Morph	20 ms to 3 s	500 ms	Time taken to move to a snapshot.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

LAG has 13 automatable parameters. The echoes are added to the dry signal, which always passes through unchanged. The delay time changes smoothly, like a tape delay.

Snapshots. A snapshot stores seven values: Time L, Time R, Feedback, Low Cut, High Cut, Duck and Mix. It does not store Sync, the divisions or Ping-Pong. The four slots start with these values (Time L / Time R in ms, Feedback, Low Cut in Hz, High Cut in Hz, Duck, Mix):

Slot	Time L	Time R	Feedback	Low Cut	High Cut	Duck	Mix
A	375	375	0.35	100	8000	0.00	0.30
B	250	375	0.50	200	6000	0.30	0.35
C	90	120	0.20	150	10000	0.00	0.25
D	800	1200	0.70	300	4000	0.50	0.45

Snapshots are saved with your project. While the delay morphs, the knobs move by themselves.

Factory presets

LAG includes 12 factory presets.

Trap Vocals: Trap Vocal 1/8, Ad-Lib Ping-Pong, Dotted Hook.

808: 808 Slap.

Kick: Kick Echo Tight.

Oud: Oud Wide Echo, Oud Desert.

Darbouka: Darbouka Roll.

Bus Drums: Bus Drums Space.

Master: Master Haze, Dub Throw, Infinite Ghost.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\LAG\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/LAG/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Hooks and vocals. Trap Vocal 1/8** and **Dotted Hook** use a synced delay with ducking so the words stay clear.
- **Wide echoes.** Use different times on the left and right (**Oud Wide Echo**) or enable ping-pong (**Ad-Lib Ping-Pong**).
- **Slapback. 808 Slap** uses very short times with a low feedback.
- **Dub throws.** Raise FEEDBACK to 0.75 (**Dub Throw**) and automate MIX or the snapshot slots.
- **Transitions.** Store a dry snapshot in slot A and an extreme one in slot D, then switch to D at the end of a bar with a long MORPH.
- **Keep the low end clean.** Raise LOW CUT so that repeats of a bass do not muddy the mix.

FAQ

The delay does not follow my tempo. Click SYNC. If your host does not send a tempo, the plugin uses 120 BPM.

What do the division values mean? D is dotted (1.5 times longer), T is triplet (two thirds as long).

How do I store a snapshot? Click STORE (it lights up), then click the slot. The current settings are stored in that slot.

Does it add latency? No.

HUMPIRE LOADOUT

Eight studio effects in one payment: EQ, compressor, enhancer, limiter, reverb, delay, lo-fi and performance effects.

Type	Audio effects bundle
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Plugins	8

Overview

HUMPIRE LOADOUT is a suite of eight effect plugins that share the same look, the same top bar and the same preset system. Each plugin has its own manual, included in this download. All plugins come with factory presets named for the material they are made for (trap vocals, 808, kick, oud, darbouka, drum bus, master).

Plugin	Type	What it does
HUMPIRE SKILLTREE	Parametric EQ	Six interactive bands, high-pass and low-pass filters, Mid/Side, linear phase and a real-time analyzer.
HUMPIRE CLUTCH	Compressor	Clean, Punch and Crush modes, sidechain high-pass and parallel mix, with a LED life bar.
HUMPIRE OVERCLOCK	Enhancer	Density, harmonics and perceived loudness with a Power knob and a two-band split.
HUMPIRE HARDCAP	Master limiter	Look-ahead true-peak limiter with auto-release and LUFS meters.
HUMPIRE RESPAWN	Reverb	Eight-line feedback delay network reverb with pre-delay, damping, EQ and ducking.
HUMPIRE LAG	Stereo delay	BPM sync, filtered feedback, ducking, ping-pong and four morphing snapshots.
HUMPIRE GLITCH	Lo-fi	Bit crusher, sample-rate reducer, speaker filter and dither on a handheld-console body.
HUMPIRE COMBO	Performance FX	Stutter, tape stop, filter sweep and reverse with two XY pads and MIDI triggering.

Installation

Run the installer from the Windows download, or the package from the macOS download. The installer lets you choose which of the eight plugins to install. On Windows, the plugins are copied to `C:\Program Files\Common Files\VST3` as `HUMPIRE SKILLTREE.vst3`, `HUMPIRE CLUTCH.vst3` and so on. On macOS, copy or install the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`. The README in each download explains the one-

time security prompt (Windows SmartScreen, macOS Gatekeeper): the installers are not code-signed. Then restart your host and rescan plugins. In FL Studio, open **Options > Manage plugins** and click **Find installed plugins**; the plugins are listed under the vendor **HUMPIRE by Djbilbox BEATS**.

All eight are effects: add them to a **Mixer** insert slot, not to the Channel rack.

What the plugins have in common

- **Top bar:** preset selection with **<** and **>**, **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS** and **IN / OUT** meters.
- **SIMPLE and CLEAN:** SIMPLE hides the advanced knobs. CLEAN replaces the textured body with a flat panel.
- **Resizable window:** 820 x 560 pixels, resizable from 50% to 200% with a fixed aspect ratio.
- **Presets:** factory presets by category, and your own presets in `%APPDATA%\HUMPIRE\<PLUGIN>\Presets` (Windows) or `~/Library/Application Support/HUMPIRE/<PLUGIN>/Presets` (macOS).
- **Automation:** every control can be automated in your host. In FL Studio, use **Tools > Last tweaked > Create automation clip**.
- **Stereo or mono:** all plugins accept mono or stereo tracks.

Suggested chains

- **Vocal:** SKILLTREE (clean the lows) then CLUTCH (even out the level) then RESPAWN or LAG on a send.
- **808:** OVERCLOCK (add harmonics) then CLUTCH or HARDCAP in a safe preset such as **808 Guard**.
- **Drum bus:** CLUTCH (**Bus Drums Glue**) then OVERCLOCK (**Drum Bus Power**) then GLITCH at low mix for dirt.
- **Master:** SKILLTREE (**Master Wide Air**) then HARDCAP as the very last plugin.
- **Live moves:** COMBO on a bus, triggered from your MIDI keyboard.

Latency summary

Plugin	Latency
SKILLTREE	0 samples in Minimum phase, 2048 samples in Linear phase
CLUTCH	0 samples
OVERCLOCK	Small, from the 2x oversampling filters (reported to the host)
HARDCAP	About half of the look-ahead time (reported to the host)
RESPAWN	0 samples
LAG	0 samples
GLITCH	0 samples
COMBO	0 samples

FAQ

Can I buy the plugins separately? Yes. Each plugin is also sold on its own.

Do the plugins work as instruments? No. They are effects. COMBO can be triggered by MIDI notes but processes audio.

Where are the individual manuals? Each plugin has its own PDF manual in the download. The complete manual contains all of them.

HUMPIRE OVERCLOCK

Enhancer that adds density, harmonics and perceived loudness with a Power knob and a two-band split.

Type	Audio effect (enhancer)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	12
Oversampling	2x
Latency	Reported to the host (the oversampling filters)

Overview

HUMPIRE OVERCLOCK splits the signal into a **low band** and a **high band** at an adjustable frequency (80 Hz to 4 kHz), using a Linkwitz-Riley 4th-order crossover. Each band goes through a saturator running at 2x oversampling to limit aliasing. The low band receives **density**, the high band receives generated **harmonics**.

POWER sets the amount of drive of the low band. **CURVE** morphs the saturation curve from soft and asymmetric (rich in even harmonics) to a hard clip. **DENSITY** sets how much of the saturated low band replaces the dry one. **HARMONICS** sets the drive and the amount of the high band. The output gain is automatically compensated as POWER rises, and a soft limit at the end of the chain keeps peaks under control.

On the screen, a ring and a spinning fan follow the Power setting: the ring goes from amber to red and the fan accelerates as POWER rises.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE OVERCLOCK** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Raise **POWER** until the sound feels denser and louder.
4. Use **DENSITY** to blend the effect with the original signal, and **CURVE** to choose between a smooth and an aggressive character.
5. Open **HARMONICS** and **SPLIT** (hidden in SIMPLE mode) to decide which part of the spectrum is enriched.
6. Compare with the **BYPASS** button and adjust **OUTPUT** so the level matches.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.

- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.
- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Screen. On the left, the power ring with the value as a percentage (**POWER %**). On the right, the animated fan.

Knobs. POWER, **DENSITY**, **CURVE**, **HARMONICS**, **SPLIT** and **OUTPUT**. In SIMPLE mode, **HARMONICS** and **SPLIT** are hidden.

Parameters

Control	Host name	Range	Default	Function
POWER	Power	0 to 1	0.35	Drive of the low band. The output is compensated (divided by 1 + 1.5 x Power).
DENSITY	Density	0 to 1	0.80	Amount of saturated low band mixed in.
CURVE	Curve	0 to 1	0.30	0 = soft, asymmetric curve. 1 = hard clip.
HARMONICS	Harmonics	0 to 1	0.30	Drive and amount of the generated harmonics in the high band.
SPLIT	Split	80 Hz to 4 kHz	400 Hz	Crossover frequency between the low and high bands.
OUTPUT	Output	-18 to +12 dB	0 dB	Output gain after the effect.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

OVERCLOCK has 7 automatable parameters. Peaks above 0.9 are bent by a soft limiter. A DC blocker removes any offset created by the asymmetric curve.

Factory presets

OVERCLOCK includes 12 factory presets.

Trap Vocals: Vocal Presence, Ad-Lib Heat.

808: 808 Harmonics, Sub Thicken.

Kick: Kick Weight, Kick Click.

Oud: Oud Warmth.

Darbouka: Darbouka Bite.

Bus Drums: Drum Bus Power.

Master: Loud Master, Overclocked!, Air Only.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\OVERCLOCK\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/OVERCLOCK/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **808s. 808 Harmonics** and **Sub Thicken** use a low split (120 to 150 Hz) so the sub gains harmonics that carry on small speakers.
- **Vocals. Vocal Presence** uses a split near 800 Hz and a medium amount of harmonics for presence without harshness.
- **Drum bus. Drum Bus Power** adds weight at a split around 300 Hz.
- **Air. Air Only** keeps the low band almost untouched and lifts the highs from 3 kHz.
- **Extreme. Overclocked!** pushes every control: lower OUTPUT to stay in control.

FAQ

Does it add latency? A small one, from the oversampling filters. The plugin reports it to your host.

Why is the level lower when I raise POWER? The output is compensated so that more drive does not simply mean louder. Use OUTPUT to adjust.

Why do I not see HARMONICS and SPLIT? They are hidden in SIMPLE mode.

HUMPIRE RESPAWN

Algorithmic reverb with an eight-line feedback delay network, pre-delay, damping, low-cut and high-cut filters and ducking.

Type	Audio effect (reverb)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	12
Decay	0.2 to 20 s
Reported tail	21 seconds
Latency	0 samples

Overview

HUMPIRE RESPAWN is an algorithmic reverb built on an **eight-line feedback delay network** with a Householder feedback matrix. The signal first goes through a **pre-delay**, then through six **early reflections**, and then feeds the eight delay lines that create the tail. The **DECAY** knob sets the time for the tail to fall by 60 dB (0.2 to 20 seconds), **SIZE** scales the length of the delay lines, **DAMP** darkens the tail as it decays, and **MOD** adds a slow modulation for a smoother tail.

A **low cut** and a **high cut** filter shape the reverb itself, and **DUCK** lowers the reverb while the input signal is playing, so a vocal stays clear and the reverb blooms in the gaps. The **MIX** knob sets the dry and wet balance.

The screen shows rings that spread from a speaker cone: the number and speed of rings follow the decay time, and the cone pulses with the level of the reverb.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE RESPAWN** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Start from a preset in the **Plate**, **Hall**, **Hammam** or **Cathedral** category.
4. Adjust **DECAY** and **SIZE** to the length and size of the space.
5. Add **PRE-DLY** (10 to 40 ms) to keep the source in front of the reverb.
6. Use **MIX** to place the sound. On a send track, set MIX to 100%.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.
- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.

- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Knobs. DECAY, **SIZE**, **PRE-DLY**, **DAMP**, **EARLY**, **MOD**, **LOW CUT**, **HIGH CUT**, **DUCK** and **MIX**. In SIMPLE mode, only **DECAY**, **SIZE**, **PRE-DLY**, **DAMP** and **MIX** remain visible.

Parameters

Control	Host name	Range	Default	Function
DECAY	Decay	0.2 to 20 s	2.0 s	Time for the tail to fall by 60 dB.
SIZE	Size	0.5 to 2	1.00	Scales the delay lines and the early reflections. Larger is a bigger space.
PRE-DLY	Pre-Delay	0 to 200 ms	15 ms	Delay before the reverb starts.
DAMP	Damping	0 to 1	0.40	High-frequency absorption of the tail (cutoff from 18 kHz down to 1.5 kHz).
EARLY	Early	0 to 1	0.50	Level of the early reflections.
MOD	Modulation	0 to 1	0.30	Depth of the slow modulation of the delay lines.
LOW CUT	Low Cut	20 Hz to 1 kHz	80 Hz	High-pass filter on the reverb signal.
HIGH CUT	High Cut	2 kHz to 20 kHz	12 kHz	Low-pass filter on the reverb signal.
DUCK	Ducking	0 to 1	0.00	Amount by which the reverb is lowered while the input is loud.
MIX	Mix	0 to 1	0.30	Dry/wet balance.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

RESPAWN has 11 automatable parameters. The plugin reports a 21-second tail to the host, so reverb tails are not cut when you render.

Factory presets

RESPAWN includes 12 factory presets.

Plate: Plate Vocal, Plate Snare.

Hall: Hall Medium, Hall Large.

Hammam: Hammam Steam, Hammam Chant.

Cathedral: Cathedral Choir, Cathedral Abyss.

Trap Vocals: Trap Vocal Space.

808: 808 Room.

Oud: Oud Chamber.

Darbouka: Darbouka Courtyard.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\RESPAWN\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/RESPAWN/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Vocals that stay clear. Trap Vocal Space** combines a medium decay with strong ducking (0.7).
- **Small rooms for 808s and drums. 808 Room** keeps the decay at 0.6 s with a high low cut (300 Hz) so the low end stays tight.
- **Oriental spaces. Hammam Steam** and **Hammam Chant** use heavy damping for a warm, steamy tail.
- **Huge spaces. Cathedral Abyss** reaches a 15-second decay: use it on a send and automate MIX.
- **CPU.** The reverb is lightweight, but very long decays keep the tail running: pause the track when you are not using it.

FAQ

Is there latency? No.

Why is nothing happening at MIX 0? MIX at 0 means 100% dry. Raise it.

How do I use it on a send? Set MIX to 100% and send the amount from each track.

HUMPIRE SKILLTREE

Six-band equalizer drawn as a skill tree, with Mid/Side targeting, minimum or linear phase and a real-time FFT analyzer.

Type	Audio effect (parametric EQ)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Bands	6 (low shelf, 4 peaking, high shelf) plus high-pass and low-pass
Factory presets	12
Latency	0 samples (Minimum phase); 2048 samples (Linear phase)

Overview

HUMPIRE SKILLTREE is a six-band parametric equalizer. Each band is a numbered node on a CRT-style screen: you drag the node to change its frequency and gain, turn the mouse wheel over it to change its Q, and double-click it to switch it on or off. The nodes are joined by lines in order of frequency, like a skill tree, and the amber curve shows the combined response of the equalizer.

Band 1 is a **low shelf**, band 6 is a **high shelf**, and bands 2 to 5 are **peaking** filters. A **high-pass** and a **low-pass** filter (24 dB per octave each) sit on either side. The **Target** button sets whether the equalizer processes the whole stereo signal, only the **Mid** (center) signal or only the **Side** signal. The **Phase** button chooses **Minimum** phase (no latency) or **Linear** phase (a 4096-tap FIR, with 2048 samples of latency reported to the host). A real-time **FFT analyzer** is drawn behind the curve.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE SKILLTREE** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Drag a **node** on the screen: left and right change the frequency, up and down change the gain. The label at the top of the screen shows the band, its frequency, its gain and its Q while you hover or drag.
4. Turn the **mouse wheel** over a node to change its Q. Double-click a node to switch the band on or off. A band with a gain of 0 dB, or switched off, does nothing.
5. Use the **HIGH PASS** and **LOW PASS** knobs to remove rumble or harshness, and the **OUTPUT** knob to match the level before and after.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.

- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.
- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Screen. The grid shows frequencies from 20 Hz to 20 kHz on a logarithmic scale and gains from -18 dB to +18 dB. The six nodes are numbered 1 to 6 (from the lowest default frequency to the highest). A switched-off node is dimmed. The violet area is the spectrum of the signal after the equalizer, drawn when the analyzer is on.

Knobs. HIGH PASS, **OUTPUT** and **LOW PASS**, in this order below the screen.

Buttons. STEREO / MID / SIDE (each click goes to the next target), **MINIMUM / LINEAR** (each click switches the phase mode) and **ANALYZER** (switches the spectrum on or off). When Linear phase is on, the screen shows "LINEAR PHASE LAT 2048" in violet at its top right.

Parameters

Signal flow: the signal is optionally split into Mid and Side, passes through the six bands and the two filters, and is then scaled by the output gain. With the Mid or Side target, only the chosen signal is processed and the other one is left untouched (delayed to match when Linear phase is on).

Control	Host name	Range	Default	Function
Node frequency (drag) x6	Band 1 Freq … Band 6 Freq	20 Hz to 20 kHz	60, 200, 600, 2000, 6000, 12000 Hz	Center frequency of each band (corner frequency for the two shelves).
Node gain (drag) x6	Band 1 Gain … Band 6 Gain	-18 to +18 dB	0 dB	Boost or cut of each band.
Node Q (mouse wheel) x6	Band 1 Q … Band 6 Q	0.2 to 10	0.7, 1, 1, 1, 1, 0.7	Width of the band: a higher Q is narrower.
Node on/off (double-click) x6	Band 1 On … Band 6 On	Off / On	On	Switches a band on or off.
HIGH PASS	High Pass	20 Hz to 1 kHz	20 Hz	24 dB per octave high-pass filter. At 20 Hz it is off.
LOW PASS	Low Pass	1 kHz to 20 kHz	20 kHz	24 dB per octave low-pass filter. At 20 kHz it is off.
STEREO / MID / SIDE	Target	Stereo, Mid, Side	Stereo	Which signal the equalizer processes. On a mono track, the target is always Stereo.

Control	Host name	Range	Default	Function
MINIMUM / LINEAR	Phase	Minimum, Linear	Minimum	Minimum phase has no latency. Linear phase keeps the phase untouched and reports 2048 samples of latency.
OUTPUT	Output	-18 to +18 dB	0 dB	Output gain after the equalizer.
ANALYZER	Analyzer	Off / On	On	Shows the spectrum behind the curve.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

The 6 bands use 4 parameters each, so SKILLTREE has 31 automatable parameters in total (24 band parameters, High Pass, Low Pass, Target, Phase, Output, Analyzer and Bypass).

Linear phase and latency. In Linear phase mode the plugin recalculates a 4096-tap FIR filter whenever you change a setting, and reports 2048 samples of latency to the host. FL Studio compensates this automatically. While the filter is being rebuilt, audio is briefly paused. For that reason, prefer Minimum phase while you are moving nodes and switch to Linear phase for the final result.

Factory presets

SKILLTREE includes 12 factory presets in categories named after the material they are made for.

Trap Vocals: Trap Vocal Air, Radio Vocal.

808: 808 Sub Boost, 808 Clarity.

Kick: Kick Punch, Kick Click.

Oud: Oud Body, Oud Air.

Darbouka: Darbouka Bite.

Bus Drums: Bus Drums Glue.

Master: Master Wide Air, Master Mono Bass.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\SKILLTREE\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/SKILLTREE/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Clean the low end first.** Raise **HIGH PASS** to 25 to 40 Hz on every track except the kick and the 808 to remove inaudible rumble (see **Kick Click** for an example).
- **Vocal air.** Start from **Trap Vocal Air**: a high-pass at 90 Hz, a small cut around 250 Hz, a boost near 3.5 kHz and a high shelf at 11 kHz.

- **Mid/Side on the master.** Set the target to **Side** and lift band 6 (as in **Master Wide Air**) to open up the top end without touching the center. Set the target to **Mid** and lift band 1 (as in **Master Mono Bass**) to strengthen the bass in the center.
- **Match levels.** Use **OUTPUT** to compensate for boosts so you judge the tone, not the loudness.
- **Check with the analyzer.** Switch the analyzer on to see where the energy is, then switch it off to reduce CPU use.

FAQ

Does Linear phase add latency? Yes: 2048 samples, reported to your host. Minimum phase adds none.

The nodes are in the wrong order. Nodes are numbered by band, not by position. Band 1 is always the low shelf and band 6 the high shelf, whatever frequency you give them.

Can I equalize only the stereo width? Yes. Set the target to **Side**.

Why does the screen show no spectrum? Check that **ANALYZER** is on and that audio is playing through the plugin.

Where do I find the plugin on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host.

K2000

80s synthwave and darksynth synthesizer: leads, basses, pads, plucks, keys and brass, with a ladder filter, an LFO with its own envelope and a full effects chain.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

K2000 is an 80s-style synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one oscillator section with six waveforms (Sawtooth, Square, Triangle, Sine, SuperSaw and 80s Brass), followed by a multimode filter, an amplitude envelope and an LFO that has its own ADSR envelope.

The sound then goes through a master effects chain: distortion, a stereo chorus, a ping-pong tape-style delay and a reverb, and finally a volume stage with a soft limiter. The look is a neon-cyan faceplate with a cassette-style EXPANSION slot, pitch and modulation wheels and an on-screen keyboard.

K2000 targets Synthwave, Darksynth, Retrowave, Synthpop, Outrun and 80s-style soundtrack work: lead lines, bass lines, wide pads, plucks and arps, keys, brass stabs and atmospheric effects. The filter offers five modes, including a 24 dB ladder and an “Acid” low pass. Voice mode is selectable: Poly 8, Poly 16, Mono Retrig and Mono Legato. Polyphony is up to 16 voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **K2000** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **K2000 - Init Patch**: a Sawtooth waveform in Poly 8 mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 84, which is C3 to C7 in FL Studio naming (where middle C is C5).
5. Shape the sound with the main controls:
   - **WAVEFORM** menu: the raw character of the oscillator.
   - **CUTOFF**: the filter cutoff. Turn it down for a darker, rounder sound.
   - **RES**: the filter resonance, for a sharper, more vocal sweep.
   - **GLIDE**: slide time between notes. Turn it down for straight notes.
6. Adjust **VOLUME** (right side of the panel) to set the output level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message announcing that expansion packs are coming soon. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The camel artwork, the K2000 title and “By Humpire”.

Left vent panel (beside the camel). Two small knobs: **RES** (filter resonance) and **FLT ENV** (filter envelope depth).

Right vent panel (beside the camel). Two small knobs: **AMP REL** (amplitude release time) and **DETUNE** (spread of the SuperSaw waveform).

AMP ENVELOPE and VELOCITY (top right). Five vertical sliders: **ATTACK, DECAY, SUSTAIN** (the amplitude envelope) and **BANK, ADSR** (the two velocity controls, under the VELOCITY header). The amplitude release is the **AMP REL** knob in the right vent panel.

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. The **LFO>PITCH** switch between them sends a light vibrato to the pitch, whatever the LFO DESTINATION menu says. To the right, the **LFO ENVELOPE** has four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**. They shape how the LFO depth fades in and out during each note.

Center and right knobs.

- Row 1, right: **VOLUME, REVERB, CHORUS, DISTORTION**. DISTORTION is the master distortion on the summed output.
- Row 2, left to right: **GLIDE, CUTOFF** (center), then **DRIVE** (filter input drive), **DLY MIX** (delay level), **DLY TIME** (delay time) and **FEEDBACK** (delay repeats).

Menu row. Five drop-down menus, each with a caption below it: **WAVEFORM**, **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels (bottom left). PITCH BEND springs back to the center when you release it. **MODULATION** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. A value bubble appears while you drag. You can also type a value, for example `440 Hz` or `35`, in the host’s parameter field.

Parameters

Signal flow: oscillator, then filter, then amplitude envelope (per voice, with the LFO and the filter envelope acting on pitch, cutoff, pulse width, volume and pan). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter close the chain, after the VOLUME control.

K2000 exposes 33 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
WAVEFORM (Waveform menu)	Sawtooth, Square, Triangle, Sine, SuperSaw, 80s Brass	Sawtooth	Selects the oscillator waveform. Square is a pulse wave with a 50% duty cycle. SuperSaw stacks seven detuned saws. 80s Brass blends a saw, a pulse wave and an octave-up sine.
DETUNE (Osc Detune)	0 to 100%	40%	Spread of the seven SuperSaw oscillators (up to about +/-2% in frequency at 100%). On 80s Brass it adds a very small detune (up to 0.3%). No effect on the other waveforms.
CUTOFF (Filter)	20 to 20,000 Hz	3,200 Hz	Filter cutoff. The cutoff is not keyboard-tracked.
RES (Filter Resonance)	0 to 100%	20%	Filter resonance.
FILTER TYPE (menu)	LowPass 24dB, LowPass 12dB, BandPass, HighPass, Acid LowPass	LowPass 24dB	LowPass 24dB is a 4-pole ladder filter. LowPass 12dB, BandPass and HighPass use a 12 dB state-variable filter. Acid LowPass is the ladder with extra resonance and drive.
DRIVE (Distortion Drive)	0 to 100%	15%	Drive applied at the filter input (per voice). Not the master distortion.
FLT ENV (Filter Env Amount)	0 to 100%	0%	Depth of the filter envelope. At 100% the envelope opens the cutoff by up to 5 octaves. The envelope is fixed: 2 ms attack, decay equal to the amplitude DECAY (limited to 0.03 to 3 s), sustain 0, release 0.1 s.
ATTACK (Amp Attack)	1 ms to 5 s	20 ms	Amplitude envelope attack time.
DECAY (Amp Decay)	5 ms to 8 s	0.8 s	Amplitude envelope decay time. It also sets the filter envelope decay.
SUSTAIN (Amp Sustain)	0 to 100%	70%	Amplitude envelope sustain level.
AMP REL (Amp Release)	10 ms to 8 s	0.4 s	Amplitude envelope release time.
BANK (Velocity Bank)	0 to 100%	75%	Velocity depth on the note level. At 0% all notes have the same level; at 100% the level follows the velocity fully.

Parameter	Range	Default	Function
ADSR (Velocity ADSR)	0 to 100%	40%	Additional velocity response on the amplitude envelope (a curved response, so soft notes get quieter). At 0% it has no effect.
GLIDE (Glide)	0 to 1 (time scale in seconds)	0.05	Portamento. Each new note slides from the pitch of the previous note, in every voice mode. Values below about 0.002 turn glide off.
RATE (LFO Rate)	0.05 to 25 Hz	4.5 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 100%	35%	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Square, Saw Up, Saw Down, Random S&H	Triangle	LFO shape. The LFO restarts at every new note. Random S&H picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Cutoff, Pitch, Pulse Width, Volume, Chorus, Pan	Cutoff	LFO target. Cutoff: up to +/-4 octaves. Pitch: up to +/-1 semitone. Pulse Width: pulse width from 5% to 95% (audible on Square and, in part, on 80s Brass). Volume: up to a 50% level dip (tremolo). Chorus: moves the chorus depth by up to +/-0.5. Pan: moves each voice across the stereo field.
LFO>PITCH (LFO Pitch Switch)	Off, On	Off	When on, adds a vibrato of up to +/-0.5 semitone from the LFO, in addition to the selected destination.
LFO ENVELOPE ATTACK (LFO Attack)	1 ms to 5 s	0.1 s	Time for the LFO depth to fade in at each note.
LFO ENVELOPE DECAY (LFO Decay)	5 ms to 8 s	0.5 s	Decay time of the LFO envelope.
LFO ENVELOPE SUSTAIN (LFO Sustain)	0 to 100%	100%	Sustain level of the LFO depth. At 0% the LFO fades out after the attack and decay.
LFO ENVELOPE RELEASE (LFO Release)	5 ms to 8 s	0.4 s	Release time of the LFO envelope.
VOICE MODE (Mono/Poly menu)	Poly 8, Poly 16, Mono Retrig, Mono Legato	Poly 8	Poly 8: up to 8 notes at once. Poly 16: up to 16 notes. Mono Retrig: one note at a time, envelopes restart at every note. Mono Legato: one note at a time, envelopes are not restarted when you play legato.

Parameter	Range	Default	Function
DISTORTION (Distortion Master)	0 to 100%	25%	Saturation on the summed output, with level compensation.
CHORUS (Chorus)	0 to 100%	45%	Stereo chorus depth.
DLY MIX (Delay Mix)	0 to 100%	30%	Level of the ping-pong delay.
DLY TIME (Delay Time)	10 ms to 1 s	0.375 s	Delay time. Not tempo-synced: for a quarter note use 60 / BPM (0.5 s at 120 BPM). The right channel is 15% longer than the left.
FEEDBACK (Delay Feedback)	0 to 95%	45%	Number of delay repeats. The repeats are darkened and slightly saturated.
REVERB (Reverb)	0 to 100%	35%	Reverb amount.
VOLUME (Volume)	0 to 100% (-inf to 0 dB)	80% (-1.9 dB)	Master output level, applied before the soft limiter.
Pitch Bend wheel (Pitch Bend)	-100 to +100% (-200 to +200 cents)	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Modulation wheel (Mod Wheel)	0 to 100%	0	On-screen mod wheel. Adds to the LFO AMOUNT, opens the cutoff by up to 0.8 octave and raises the chorus depth by up to 25%.

Factory presets

K2000 includes 70 factory presets in 7 banks. Voice modes across the 70 presets: 43 load in Poly 8, 3 in Poly 16, 10 in Mono Retrig and 14 in Mono Legato.

VOL.1 Factory (17): K2000 - Init Patch, 01 - Neon Night Drive, 02 - Outrun Bassline, 03 - Blade Runner Lead, 04 - Miami Vice Pad, 05 - Turbo Arp Pluck, 06 - VHS Tape Dreams, 07 - Cyber Chaser Bass, 08 - Sunset Grid Pluck, 09 - Stranger Horror Pad, 10 - Megadrive Solo Lead, 11 - Chrome Overdrive, 12 - Digital Rain Pluck, 13 - Retrowave Brass Stabs, 14 - Cyborg Camel Cry, 15 - Cassette LoFi Keys, 16 - Future Hero Solo.

Leads (9): 17 - Laser Grid Lead, 18 - Sunset Strip Lead, 19 - Neon Sirens, 20 - Turbo Brass Lead, 21 - Pulse Rider, 22 - Crystal Hero, 23 - Acid Rain Lead, 24 - Lost Highway, 25 - Cyber Whistle.

Bass (9): 26 - Night Pulse Bass, 27 - Sub Highway, 28 - Darksynth Growl, 29 - Octave Chase, 30 - Moog Miami, 31 - Rubber Grid, 32 - Terminator Sub, 33 - Wobble Chrome, 34 - Hi-NRG Bass.

Pads (9): 35 - Sunset Strip Pad, 36 - Blade Fog, 37 - Outrun Strings, 38 - Neon Choir, 39 - Dark Cinema, 40 - Aurora Slow Pad, 41 - Cassette Warmth, 42 - Retro Glass Pad, 43 - Cyborg Breath.

Plucks & Arps (9): 44 - Arp Machine, 45 - Neon Pluck, 46 - Glass Arp, 47 - Sequence Chrome, 48 - Dream Bell, 49 - Laser Tag, 50 - Night Marimba, 51 - Filter Gate, 52 - Echo Pluck.

Keys & Brass (9): 53 - Retro Electric Keys, 54 - Synthpop Keys, 55 - Power Brass, 56 - 80s Horns, 57 - Stab Section, 58 - Soft Strings Keys, 59 - Chip Organ, 60 - Polysynth Chord, 61 - Jazz Fusion Keys.

FX & Atmos (8): 62 - Warp Drive, 63 - Nuclear Dawn, 64 - Sonar Ping, 65 - Static Rain, 66 - Tape Stop Dream, 67 - Hologram, 68 - Overheating, 69 - Last Exit.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.k2preset` file. The default folder is `DJBILBOX BEATS/K2000/Presets` inside your Documents folder. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .k2preset file…** in the same menu to load a file from another location. The preset display shows the file name. User presets do not change the two wheels.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

“Moog Miami” is a preset name that refers to a sound style. Moog is a trademark of its owner. DJBILBOX BEATS is not affiliated with the trademark owner.

Production tips

1. **Synthwave leads.** Start from Laser Grid Lead or Sunset Strip Lead (Mono Legato). Raise GLIDE slightly for slides between notes, and keep the LFO>PITCH switch on for a light vibrato. Add DLY MIX and REVERB for the classic wide lead.
2. **Outrun and darksynth bass.** Use the Bass bank (Night Pulse Bass, Terminator Sub, Darksynth Growl). Raise FLT ENV and shorten the amplitude DECAY for a punchy filter pluck on every note. Raise RES for more bite.
3. **Wobble.** Set LFO DESTINATION to Cutoff, LFO SHAPE to Sine or Triangle and RATE to 2 Hz or so, as in Wobble Chrome. Keep AMOUNT above 50% for a deep movement.
4. **Wide pads.** The Pads bank uses long attacks. For extra width use the SuperSaw waveform, raise DETUNE and CHORUS, and add REVERB.
5. **Arps and plucks.** The Plucks & Arps bank uses short decays and zero sustain. Feed it a fast arpeggio from your Piano roll or a MIDI arpeggiator, then set DLY TIME to a musical value with moderate FEEDBACK. At 120 BPM, 0.375 s is a dotted eighth note (3 x 60 / BPM / 4).
6. **Brass stabs.** Choose the 80s Brass waveform, a medium ATTACK and a low SUSTAIN (see Stab Section and Retrowave Brass Stabs). Add a little CHORUS.
7. **Pulse width.** Select the Square waveform, set LFO DESTINATION to Pulse Width and RATE to a slow value for the classic moving pulse sound.
8. **Stereo movement.** Set LFO DESTINATION to Pan with a Triangle or Sine LFO and a low RATE for a slow auto-pan across the voices.
9. **Level and dynamics.** BANK sets how much velocity changes the level. Set it near 75% for natural accents, or 0% for even notes.

MIDI, automation and performance

Notes and channels. K2000 responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the BANK and ADSR sliders.

Polyphony. Up to 16 voices in Poly 16 and up to 8 voices in Poly 8. When you play more notes than the limit, a voice is taken over and cut. In both Mono modes, each new note stops the previous one (last-note priority). Releasing the newest note while an earlier note is still held brings that earlier note back.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen PITCH BEND wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth and opens the filter (up to 0.8 octave), like the on-screen MODULATION wheel. When both are used on a voice, the higher value wins for the LFO and filter. The chorus depth increase follows the on-screen **Mod Wheel** parameter only. For repeatable results in a song, automate the **Mod Wheel** parameter.

Other MIDI. The sustain pedal (CC64) is supported in the Poly modes and is ignored in the Mono modes. All Notes Off, All Sound Off and Reset All Controllers messages are handled. Aftertouch is ignored.

Automation in FL Studio. All 33 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**).

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. The master DISTORTION is bypassed when set to zero. Poly 8 and short release times keep the voice count low. SuperSaw uses seven oscillators per voice, so it costs more than the other waveforms. The plugin was tested at 44.1, 48, 88.2 and 96 kHz.

FAQ

K2000 does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **K2000** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to a low pass mode. Some presets (Bass bank, Pads) can sound soft on small speakers. For notes outside the on-screen keyboard range (MIDI 36 to 84), play from a MIDI keyboard or the Piano roll.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note, in every voice mode. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one or two notes. The VOICE MODE menu is set to Mono Retrig or Mono Legato (or Poly 8 with more than 8 notes). Switch it to Poly 8 or Poly 16.

The filter envelope does nothing. FLT ENV is 0% by default. Raise it to hear the filter opening at each note. The envelope's decay follows the amplitude DECAY slider.

Does it work without a MIDI keyboard? Yes. Draw notes in the Piano roll or click the on-screen keyboard.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

MARABOUT

Oriental and Afro-mystic synthesizer: kora, balafon, oud, ney, zurna, choir voices, dark pads and voodoo subs from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

MARABOUT is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: **Kora** (plucked harp string with a sympathetic octave), **Balafon** (inharmonic wooden bars with a gourd buzz), **Oud** (soft plucked string with a soundbox resonance), **Ney** (reed flute with filtered breath and vibrato), **Zurna** (double reed with a nasal resonance), **Choir** (five detuned saws through vowel filters), **Dark Pad** (five detuned saws plus a sub sine) and **Sub Voodoo** (sine sub with a pitch “knock” and saturation).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The character is dark, warm and atmospheric.

MARABOUT fits Afro-trap and Afrobeat melodies, Gnawa and Middle Eastern-flavored loops, Hip-Hop and Drill textures, cinematic pads and ritual drones, and voodoo-style 808 subs. Most presets load in Poly mode with up to 16 voices; 11 presets (leads and subs) load in Mono mode.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **MARABOUT** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **MARABOUT - Init Patch**: the Kora engine in Poly mode with default settings.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. Melodic presets sit well between MIDI notes 48 and 84 (C4 to C7 in FL Studio naming, where middle C is C5). Presets with TRANSPOSE at -12 or +12 sound one octave lower or higher than the key you play.
5. Shape the sound with the three main controls:
   - **TONE**: the first character control. Its role depends on the engine (vowel of the Choir, pick softness of the Oud, pitch knock of Sub Voodoo…).
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker, rounder sound.
   - **GLIDE**: slide time between notes. Leave it at zero for straight notes.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. The window can be resized from 50% to 200% with the proportions kept.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The camel artwork, the MARABOUT title and “By Humpire”. The two dotted grilles beside the artwork are decorative.

Left, under the cassette. Three knobs: **LFO RATE** and **LFO AMT** set the LFO speed and depth. **TRANSPOSE** sits next to them but is not an LFO control: it is the global transposition (-12 to +12 semitones).

AMP ENVELOPE (left). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Character knobs (center). Small knobs **TONE, BODY, BRIGHT, WIDTH** (left of GLIDE) and **TEXTURE** (right of CUTOFF): the five character controls of the selected engine. Beside TEXTURE are **RES** (filter resonance) and **FLT ENV** (filter envelope depth). The large **GLIDE** and **CUTOFF** knobs sit between them.

FILTER ENVELOPE (right). Four sliders **ATK, DEC, SUS, REL**, with the **VELOCITY** slider (velocity sensitivity of the level) just to their right. The **VOLUME** knob is at the far right of the same row.

FX (right). Six knobs in two rows. Top row: **REVERB, CHORUS, DISTORTION**. Bottom row: **DLY MIX** (delay level), **DLY TIME** (delay time) and **FEEDBACK** (delay repeats).

Menu row. Five drop-down menus, each with a caption below it: **ENGINE**, **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels (bottom left). Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 48 to 96 (four octaves plus one key). The key labels on screen run from C2 to C6, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C4 to C8. The keyboard does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click a control to return it to its default value (standard JUCE behavior). A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

MARABOUT exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Control	Range	Default	What it does
ENGINE (Waveform menu)	Kora, Balafon, Oud, Ney, Zurna, Choir, Dark Pad, Sub Voodoo	Kora	Selects the synthesis engine.
TONE (Tone / Vowel)	0 to 1	0.5	Character control 1. Its effect depends on the engine (see the table below).

Control	Range	Default	What it does
BODY (Body)	0 to 1	0.5	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	0.5	Character control 3. Engine-dependent.
WIDTH (Width / Detune / Vibrato)	0 to 1	0.3	Character control 4. Engine-dependent (detune or vibrato depth). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	0.2	Character control 5. Engine-dependent (resonance, buzz, breath noise, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% (a quarter octave per octave, centered on middle C).
RES (Resonance)	0 to 1	0.15	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
FLT ENV (Filter Env Amount)	0 to 1	0	Filter envelope depth. At 1 the envelope opens the cutoff by up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	0.5	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	0.7	Amplitude envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1	0.7 (-3.1 dB)	Output level of each voice, before the effects. Displayed in dB.

Control	Range	Default	What it does
GLIDE (Glide)	0 to 2	0	Portamento. Higher values give longer slides. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
LFO RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
LFO AMT (LFO Amount)	0 to 1	0	LFO depth. The mod wheel adds to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0	Saturation on the summed output, with level compensation.
CHORUS (Chorus)	0 to 1	0	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	0.35	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	0.25	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Modulation wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMT value.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Kora	No effect	String sustain	Brightness of the string (damping)	No effect	Level of the sympathetic octave
Balafon	No effect	Decay length of the bars	Level of the upper partials and the mallet click	No effect	Gourd buzz level
Oud	Pick softness and soundbox tuning	String sustain	Brightness of the string	No effect	Soundbox resonance level
Ney	Pitch of the breath filter	Focus (resonance) of the breath filter	Upper harmonics	Vibrato depth	Breath noise level
Zurna	Frequency of the nasal resonances	Level of the nasal resonances	Opening of the built-in low-pass	Detune of the two reeds	Noise level
Choir	Vowel, sweeping a, o, u, i	Level of the vowel formants	Opening of the built-in low-pass	Detune spread of the five saws	Breath noise level
Dark Pad	No effect	Level of the sub sine	Opening of the built-in low-pass	Detune spread of the five saws	Noise level
Sub Voodoo	Depth of the pitch “knock” at the attack	Level of the octave harmonic	Attack click	No effect	Saturation

Factory presets

MARABOUT includes 70 factory presets in 7 banks of 10. 59 presets load in Poly mode and 11 load in Mono mode (marked with an asterisk below).

Kora & Harps: Kora Dawn, Griot Kora, Night Harp, Bright Kora, Soft Pluck, Desert Harp, Sahel Arp, Moonlit Kora, Low Kora, Glass Strings.

Balafon & Mallets: Balafon Classic, Gourd Balafon, Wood Bells, Marimba Moon, Dry Mallet, Rain Balafon, Kalimba Dream, Buzzy Balafon, Ritual Mallets, Ice Xylo.

Oud & Plucks: Oud Taksim, Warm Oud, Bright Oud, Saz Night, Low Oud, Desert Guitar, Gnawa Guembri*, Tape Oud, Muted Pick, Oud Dub.

Ney & Zurna: Ney Whisper, Desert Ney, Breathy Reed, Sufi Flute, High Ney, Zurna Call, Wedding Zurna*, Nasal Reed, Mizmar, Snake Charmer*.

Choir & Voices: Marabout Choir, Ooo Ancestors, Ah Elders, Ee Spirits, Vowel Sweep, Whisper Choir, Low Voices, Muezzin Pad*, Gospel Dust, Hollow Chant.

Dark Pads & Drones: Candle Pad, Smoke Drone, Midnight Souk, Shell Glow, Ritual Swell, Voodoo Mist, Dune Wind, Amber Strings, Tomb Choir Pad, Pulse Drone.

Sub Voodoo & FX: Voodoo Sub*, 808 Marabout, Deep Hex*, Knock Bass*, Dirty Sub*, Glide Sub*, Ghost Boom, Bell Drop, Spirit Siren*, Hex Zap*.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.mbpreset` file. The default folder is `DJBILBOX BEATS/MARABOUT/Presets` inside your Documents folder. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .mbpreset file…** in the same menu to load a file from another location. The preset display shows the

file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Afro-trap melodies.** Start from Griot Kora, Sahel Arp or Kalimba Dream. Add a little DLY MIX with DLY TIME set to an eighth note (30 / BPM seconds) for bouncy, repeating plucks.
2. **Gnawa and Maghreb grooves.** Gnawa Guembri (Mono, one octave down) and Muted Pick work well as repeating bass or rhythm lines. Raise TEXTURE on the Oud engine for more soundbox resonance.
3. **Wide melodies from the Ney.** On the Ney engine, WIDTH sets the vibrato depth and TEXTURE the breath noise. Raise the ATTACK slider for a slow, breathy entrance (see Ney Whisper).
4. **Lead lines.** Wedding Zurna and Snake Charmer load in Mono with a short glide. Raise GLIDE for longer slides between notes.
5. **Vowel movement.** On the Choir engine, TONE sweeps the vowel from a to o to u to i. Set LFO DESTINATION to Timbre to let the LFO move it automatically (see Vowel Sweep), or automate TONE.
6. **Cinematic pads.** Dark Pads & Drones are Poly pads made for long notes. Add REVERB and CHORUS, and automate CUTOFF over several bars for evolving textures.
7. **Voodoo subs.** On the Sub Voodoo engine, TONE sets the pitch knock, TEXTURE the saturation and BODY adds the octave harmonic. Raise TEXTURE or DISTORTION so the sub stays audible on small speakers.
8. **Slides.** With GLIDE above zero, every new note slides from the previous one. For slides on selected notes only, keep GLIDE at 0 and automate it up just before the notes that should slide.

MIDI, automation and performance

Notes and channels. MARABOUT responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, and new notes start from the latest CC1 value. For repeatable results in a song, automate the **Mod Wheel** parameter instead.

Other MIDI. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. You can also pick parameters from the plugin wrapper menu (**Browse parameters**). Level, pitch, bend, filter, distortion and delay changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples), so no delay compensation is needed. It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. Distortion, chorus, delay and reverb are bypassed when set to zero and cost no CPU. Short release times keep the voice count low.

FAQ

MARABOUT does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **MARABOUT** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

I hear nothing, or almost nothing, when I click the on-screen keyboard. Check VOLUME, and check that CUTOFF is not turned all the way down with FILTER TYPE set to Low Pass. Some presets use TRANSPOSE -12 and play low. For notes outside the on-screen keyboard range (MIDI 48 to 96), play from a MIDI keyboard or the Piano roll.

The sound dies away quickly even if I hold the key. Plucked and mallet engines (Kora, Balafon, Oud) decay naturally. Their presets use a SUSTAIN of zero, so the DECAY slider sets how long the note rings. Raise DECAY, and BODY on the engine, for longer notes.

Every note slides into the next one. GLIDE is above zero. Glide applies to every new note. Set GLIDE to 0, or automate it only where you want slides.

My chord only plays one note. The VOICE MODE menu is set to Mono. Switch it to Poly (up to 16 voices).

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host.

MIDNIGHT REELS

Film-noir keys, brass, bass and strings: vibes, electric piano, muted trumpet, tenor sax, upright bass, organ, strings and celesta from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

MIDNIGHT REELS is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Vibes (struck bars with a tremolo motor), Reel EP (an electric piano with a velocity-sensitive “bark”), Muted Trumpet, Tenor Sax (with a delayed vibrato), Upright Bass (a plucked string with a body resonance), Organ (drawbar-style), Noir Strings (five detuned saws with a tape-style flutter) and Celesta (bell-like partials).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The character is dark and smoky, built for late-night, detective-movie atmospheres.

MIDNIGHT REELS targets film-noir and jazz-flavoured Lo-Fi, Hip-Hop and R&B beats, Trip-Hop, soundtrack and cinematic cues, and lounge or slow-jam arrangements. Most presets load in Poly mode with up to 16 voices. Twelve presets (the ten Upright Bass presets plus Late Night Sax and Growl Sax) load in Mono mode for single-note lines.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **MIDNIGHT REELS** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **Init Patch**: the Vibes engine with default settings.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 84 (C3 to C7 in FL Studio naming, where middle C is C5).
5. Shape the sound with the main controls:
   - **TONE, BODY, BRIGHT, WIDTH, TEXTURE**: the character of the selected engine.
   - **CUTOFF**: the filter cutoff. Turn it down for a darker, tape-like sound.
   - **REVERB** and **CHORUS**: space and width.
6. Adjust **VOLUME** (the rightmost slider, top right) to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. The proportions stay fixed when the host resizes the window.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The detective camel artwork and the MIDNIGHT REELS title with “By Humpire”. The dotted grilles at each side of the artwork are decorative.

FILTER ENVELOPE (top right). Five vertical sliders: **ATK, DEC, REL** (the filter envelope), **VELOCITY** (velocity sensitivity of the level) and **VOLUME** (output level of the voices).

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE** sits in the same row: it is the global transposition (-12 to +12 semitones), not an LFO control.

AMP ENVELOPE (left, below the LFO). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Character and filter (center).

- **TONE, BODY, BRIGHT, WIDTH**: four small knobs to the left of GLIDE.
- **GLIDE** and **CUTOFF**: two large knobs.
- **TEXTURE**, **RES** (filter resonance) and **ENV AMT** (filter envelope depth): three small knobs to the right of CUTOFF.

Effects (right). Top row: **REVERB, CHORUS, DISTORTION**. Bottom row: **DLY MIX** (delay level), **DLY TIME** (delay time) and **FEEDBACK** (delay repeats).

Menu row. Five drop-down menus, each with a caption below it: **ENGINE**, **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE** (Poly or Mono). Each menu shows its current value.

Wheels (bottom left). PITCH BEND springs back to the center when you release it. **MOD WHEEL** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. It covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

MIDNIGHT REELS exposes 34 automatable parameters. The host name is shown in parentheses when it differs from the panel label. The filter envelope has no sustain control: it rises and decays to zero, and ENV AMT sets how far it opens the filter.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Vibes, Reel EP, Muted Trumpet, Tenor Sax, Upright Bass, Organ, Noir Strings, Celesta	Vibes	Selects the synthesis engine.
TONE (Tone)	0 to 1 (0 to 100 %)	50 %	Character control 1. Engine-dependent (see the table below).

Parameter	Range	Default	Function
BODY (Body)	0 to 1	50 %	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	50 %	Character control 3. Engine-dependent.
WIDTH (Width / Vibrato)	0 to 1	30 %	Character control 4. Engine-dependent (detune, tremolo, vibrato…). It is not a stereo width control.
TEXTURE (Texture)	0 to 1	20 %	Character control 5. Engine-dependent (noise, click, flutter speed…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	15 %	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode.
ENV AMT (Filter Env Amount)	0 to 1	0 %	Filter envelope depth. At 100 % the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	50 %	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY (Decay)	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	70 %	Amplitude envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME (Volume)	0 to 1 (shown in dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.
GLIDE (Glide)	0 to 2	0	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.

Parameter	Range	Default	Function
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 0.8 to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. The LFO restarts at every new note. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION (Distortion)	0 to 1	0 %	Saturation on the summed output, with automatic level compensation.
CHORUS (Chorus)	0 to 1	0 %	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0 %	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1.0 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	35 %	Number of delay repeats (0 to 90% feedback).
REVERB (Reverb)	0 to 1	25 %	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Mod Wheel (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT, together with MIDI CC1 (the larger of the two applies).

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Vibes	Mallet attack noise	Ring length of the bars	Level of the upper partials	Depth of the tremolo motor	Speed of the tremolo motor
Reel EP	No effect	Decay length	Bark: level of the upper partials, stronger with velocity	No effect	Attack noise
Muted Trumpet	Mute resonance frequency	Mute resonance and level	Low-pass opening	Detune of the two saws	Breath noise at the start of the note
Tenor Sax	Formant frequencies	Formant level	Low-pass opening	Vibrato depth (starts after a short delay)	Breath noise
Upright Bass	Pluck hardness	String sustain	String brightness	No effect	Body resonance (around 95 Hz)
Organ	Sub-octave drawbar level	Second-harmonic drawbar level	Upper drawbars level	Percussion	Key click
Noir Strings	Frequency of the mid resonance	Level of the mid resonance	Low-pass opening	Detune spread and tape flutter depth	Tape flutter speed
Celesta	Mallet attack noise	Ring length of the bells	Level of the upper partials	No effect	No effect

Factory presets

MIDNIGHT REELS includes 70 factory presets in 7 banks of 10. 58 presets load in Poly mode. 12 presets load in Mono mode: Late Night Sax and Growl Sax (Trumpet & Sax bank) and all ten presets of the Upright Bass bank. Late Night Sax and Detective Walk load with a short glide.

Vibes & Mallets: Midnight Vibes, Smoke Vibes, Hard Mallet Vibes, Slow Motor, Fast Motor, Rainy Window, Low Vibes, Dry Vibes, Ghost Mallets, Vibes Delay.

Reel EP: Reel Electric Piano, Noir Keys, Bark EP, Lounge EP, Tremolo EP, Tape EP, After Hours, Wurly Bite, Bell EP, Detective Chords.

Trumpet & Sax: Muted Trumpet, Harmon Mute, Wah Trumpet, Lonely Horn, Trumpet Stab, Tenor Sax, Smoky Sax, Breathy Sax, Late Night Sax, Growl Sax.

Upright Bass: Walking Upright, Slap Upright, Deep Pocket, Muted Bass, Jazz Club Bass, Bowed Cello, Detective Walk, Tape Bass, Fat Pluck, Sub Noir.

Organ & Lounge: Jazz Organ, Smoky Lounge, Full Drawbars, Gospel Hammond, Church Hall, Perc Organ, Tape Organ, Soft Flute Stop, Rotary Dream, Noir Swell.

Noir Strings: Noir Strings, Tape Strings, Slow Swell, Dark Cellos, High Violins, Pizzicato Noir, Film Score Pad, Wobble Reel, Suspense, Rooftop Strings.

Celesta & Reels: Music Box Noir, Celesta Dream, Glass Bells, Lullaby Reel, Toy Piano, Haunted Box, Low Celesta, Projector Click, Reel To Reel, Closing Credits.

Two presets use another engine than their bank name suggests: Bowed Cello (Upright Bass bank) uses Noir Strings, and Projector Click and Reel To Reel (Celesta & Reels bank) use Organ and Reel EP.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.mrpreset` file. The default folder is `DJBILBOX BEATS/MIDNIGHT_REELS/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .mrpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

- **Lo-Fi keys:** load **Tape EP**, then lower CUTOFF and raise CHORUS for a worn-tape feel.
- **Chords with glue:** the Reel EP and Organ banks are Poly. Raise REVERB to place chords behind a vocal.
- **Cinematic builds: Suspense** and **Slow Swell** have long attacks. Draw long notes and automate CUTOFF or ENV AMT.
- **Walking lines:** the Upright Bass bank is Mono. Write one note at a time and keep VELOCITY above 50% for a more natural touch.
- **Movement:** set LFO DESTINATION to Timbre or Filter and raise the mod wheel (or AMOUNT) for slow evolving textures.
- **Tempo-matched delay:** DLY TIME is in seconds. Use 60 / BPM for a quarter note.

MIDI and automation

- **Notes:** all MIDI channels are accepted. Velocity changes the level (see VELOCITY) and, for Reel EP, the bark.
- **Pitch bend:** +/-2 semitones, added to the on-screen PITCH BEND wheel.
- **Mod wheel (CC1):** raises the LFO AMOUNT by up to 0.8. It starts from the last position received, even if no note is playing.
- **CC121 (reset all controllers):** returns the MIDI mod wheel to zero.
- **Polyphony:** up to 16 voices in Poly mode. In Mono mode, a new note cuts the previous one (last-note priority).
- **Automation:** the 34 parameters listed above are automatable in your host. The ENGINE, LFO SHAPE, LFO DESTINATION, FILTER TYPE and VOICE MODE menus are automatable choice parameters.
- **Latency:** 0 samples. The output is stereo.

FAQ

Does it use samples? No. Every sound is generated in real time by one of eight engines.

Can I play chords with the Upright Bass presets? Switch VOICE MODE to Poly. The Upright Bass bank loads in Mono.

Why does TRANSPOSE sit next to the LFO knobs? It is a global transposition in semitones (-12 to +12). It is not an LFO control.

The keyboard on screen stops at C5. Can I play lower or higher notes? The on-screen keyboard covers MIDI notes 36 to 84 only. Play outside that range from a MIDI controller or the Piano roll.

Is the delay tempo-synced? No. DLY TIME is in seconds (0.05 to 1 s), and the LFO runs in Hz (0.05 to 20 Hz).

Can I save my own presets? Yes. The disk icon saves a `.mrpreset` file. Your presets appear in the User submenu of the preset menu.

Is there a filter sustain? No. The filter envelope has attack, decay and release. It decays to zero, and ENV AMT sets its depth.

OCCITANIE

Folk instruments of Southern France: bagpipe, hurdy-gurdy, pipe, mandolin, guitar, accordion, choir and bells, with a built-in drone.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Developer	DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

OCCITANIE is a 16-voice synthesizer inspired by the traditional instruments of Occitania, the region around Toulouse. It has eight synthesis engines: Cabrette (nasal bagpipe with breath), Vielle (bowed strings with the typical buzz), Galoubet (three-hole folk pipe), Mandoline (plucked string with plectrum tremolo), Guitare (plucked string with a soft attack), Accordeon (three detuned reeds, musette style), Choeur (ensemble with vowel formants) and Carillon (inharmonic bells). It uses no samples. Every note is generated in real time.

A **DRONE** control adds a soft tone one octave below each note, on any engine: the classic bagpipe and hurdy-gurdy sound. Each voice then runs through a multimode filter and a per-voice LFO. The output goes through an effects chain: distortion, chorus, stereo delay and reverb. A soft limiter at the output keeps the level under control.

OCCITANIE brings folk color to modern productions. Use the accordion and pipe sounds for Oriental and Rai melodies, the mandolin and guitar for Afrotrap and Drill hooks, the choirs and bells for cinematic Trap intros, and the hurdy-gurdy and bagpipe for medieval, fantasy and world music. It also works for Deep House toplines and folk-flavored Hip-Hop loops.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **OCCITANIE** (manufacturer **DJBILBOX BEATS**). You can also drag it from **Plugin database > Generators**.
2. The interface opens on **OCCITANIE - Init Patch** (Cabrette engine).
3. Click the **Presets** button at the left of the preset display. Open a bank (for example **Accordeon & Musette**) and pick a preset. You can also step through all 70 presets with the **<** and **>** buttons.
4. Play notes from your MIDI keyboard, or draw them in the **Piano roll**.
5. Raise the **DRONE** slider (right) to add a low drone under every note.
6. Move the **REED** slider to change the color of the engine: the nasal tone of the bagpipe, the vowel of the choir, the breath of the pipe.
7. Turn **REVERB** to place the sound in a small room or a large church.
8. Click **Save** at the right of the preset display to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from half size (500 x 373) to double size (2000 x 1492). The proportions stay fixed.

Preset display (top center). From left to right: **Presets** opens the preset menu, **<** loads the previous preset, the center shows the current preset name, **>** loads the next preset, and **Save** saves a user preset. The arrows wrap around from the last preset to the first. The preset menu lists the seven factory banks as submenus, a **User** submenu with your saved presets, and an **Open a .occpreset file…** item.

EXPANSION cassette (top left). Click it to see information about upcoming expansion packs (**EXPANSION VOL.1**) and the link to the DJBILBOX BEATS store. Version 1.0 contains no expansion content.

Logo (top right). The DJBILBOX BEATS name and logo.

Medallion (center). The camel warrior, wearing a horned helmet with the Occitan cross, sits between decorative speaker grilles. The OCCITANIE title and “By Humpire” are below it.

LFO group (left). RATE and **AMOUNT** set the LFO speed and depth. **PITCH** sits under the same “LFO” caption but is the global transpose of the instrument, not an LFO control.

Volume envelope (left, below the LFO group). Four vertical sliders: **ATTACK**, **DECAY**, **SUSTAIN** and **RELEASE**.

Timbre sliders and VOLUME (right, below the speaker grille). Five short vertical sliders: **REED**, **BODY**, **BRIGHT**, **DRONE** and **VEL** (velocity sensitivity). The **VOLUME** knob is to their right.

Effects (right). REVERB, **CHORUS** and **DISTORTION** on the upper row. **DELAY** (level), **TIME** and **FEEDBACK** on the lower row.

Center bottom. Two small knobs, **WIDTH** and **TEXTURE**, then the **FILTER** knob (cutoff) and the **GLIDE** knob.

Menu row. Five drop-down menus across the panel. Each one shows its current value. From left to right: the engine (**Waveform**, default “Cabrette”), the LFO shape (**LFO Source**, default “Sine”), the LFO target (**Destination**, default “Pitch”), the filter mode (**Filter Type**, default “Low Pass”) and the voice mode (**Mono/Poly**, default “Poly”).

Wheels (bottom left). The left wheel bends the pitch and springs back to center when you release the mouse. The right wheel is the modulation wheel and stays where you leave it.

On-screen keyboard (bottom). Click a key to audition the sound. It also lights up incoming MIDI notes within its range. In version 1.0 the keyboard covers the lowest part of the MIDI range (keys labeled C-2 to about D1, MIDI notes 0 to 38). Use it to check low notes. Play melodies and chords from a MIDI keyboard or the Piano roll.

Using the controls. Drag a knob up/down or left/right. Drag a slider vertically. The mouse wheel adjusts in small steps. Double-click to return to the default value. Hold Ctrl or Alt while you drag for velocity-sensitive movement. A small bubble shows the current value while you hover or drag.

Parameters

Names in parentheses are the parameter names shown in FL Studio for automation, when they differ from the panel label.

Parameter	Range	Default	Function
Engine menu (Waveform)	Cabrette, Vielle, Galoubet, Mandoline, Guitare, Accordeon, Choeur, Carillon	Cabrette	Selects the synthesis engine. See the engine table below.
LFO shape menu (LFO Source)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO waveform. Sample&Hold picks a new random value once per cycle.

Parameter	Range	Default	Function
LFO target menu (Destination)	Pitch, Filter, Amp, Timbre	Pitch	Where the LFO goes. Pitch: up to ±1 semitone. Filter: up to ±3 octaves of cutoff. Amp: tremolo, up to 50% volume dip. Timbre: moves REED, BODY, BRIGHT, WIDTH and TEXTURE together, up to ±0.5.
Filter mode menu (Filter Type)	Low Pass, High Pass, Band Pass	Low Pass	12 dB/octave state-variable filter mode. Band Pass gets a small level boost.
Voice mode menu (Mono/Poly)	Poly, Mono	Poly	Poly: up to 16 notes. Mono: each new note releases the previous one.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. The LFO restarts at each new note. It is not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0	LFO depth. The modulation wheel (or MIDI CC1) adds up to 0.8 on top.
PITCH (Pitch)	-12 to +12 semitones, continuous	0	Global transpose. Values between semitones detune the whole instrument.
GLIDE (Glide)	0 to 2 s	0 (off)	Portamento. Above 0, each new note slides from the pitch of the previous note, in Poly and Mono.
FILTER (Filter)	40 Hz to 18 kHz	9 kHz	Filter cutoff frequency. The cutoff follows the played note at 25% (key tracking).
REED (Reed / Vowel)	0 to 1	0.5	Engine timbre control 1: reed color, vowel or breath. See the engine table.
BODY (Body / Resonance)	0 to 1	0.5	Engine timbre control 2. See the engine table. BODY also raises the filter resonance slightly.
BRIGHT (Brightness)	0 to 1	0.5	Engine timbre control 3: brightness. See the engine table.
WIDTH (Width / Detune)	0 to 1	0.3	Engine timbre control 4: detune and width. See the engine table.
TEXTURE (Texture)	0 to 1	0.2	Engine timbre control 5: breath, buzz or tremolo. See the engine table.
DRONE (Drone)	0 to 1	0	Level of a softened saw one octave below each note. Works on every engine.

Parameter	Range	Default	Function
VEL (Velocity)	0 to 1	0.5	How much note velocity changes the volume. 0 = every note at full level. 1 = full velocity response.
ATTACK (Attack)	0.001 to 5 s	0.01 s	Volume envelope attack time.
DECAY (Decay)	0.01 to 5 s	0.4 s	Volume envelope decay time.
SUSTAIN (Sustain)	0 to 1	0.7	Volume envelope sustain level.
RELEASE (Release)	0.02 to 8 s	0.4 s	Volume envelope release time after note-off.
VOLUME (Volume)	0 to 1	0.7	Instrument level, before the effects.
DISTORTION (Distortion)	0 to 1	0	Soft saturation. Drive rises up to 15x; the level is compensated.
CHORUS (Chorus)	0 to 1	0	Chorus mix (fixed 0.7 Hz modulation).
DELAY (Delay)	0 to 1	0	Level of the stereo cross-feedback (ping-pong style) delay.
TIME (Delay Time)	0.05 to 1 s	0.35 s	Delay time in seconds. Changes glide smoothly, like a tape delay.
FEEDBACK (Feedback)	0 to 0.9	0.35	Delay repeats. Higher values give more echoes.
REVERB (Reverb)	0 to 1	0.25	Reverb amount. The room also grows larger as you turn it up.
Pitch bend wheel (Pitch Bend)	-1 to +1	0	Bends all notes by up to ±2 semitones. Adds to the MIDI pitch wheel.
Modulation wheel (Mod Wheel)	0 to 1	0	Adds LFO depth (up to +0.8). The higher of this wheel and MIDI CC1 is used.

Effects order: Distortion, Chorus, Delay, Reverb, then the output soft limiter. Each effect is bypassed while its knob is at zero. OCCITANIE has no filter envelope: shape the sound over time with the volume envelope and the LFO.

What the timbre controls do on each engine

Engine	REED	BODY	BRIGHT	WIDTH	TEXTURE
Cabrette: two saws with a nasal double formant and an attack puff	Formant position (nasal color)	Formant level	Brightness	Detune between the two saws	Breath noise and attack puff
Vielle: two saws with formants and a buzzing bridge	Formant position	Formant level	Brightness	Detune between the two saws	Buzz (bridge saturation)

Engine	REED	BODY	BRIGHT	WIDTH	TEXTURE
Galoubet: soft harmonic tone with breath	Breath amount (more air, less tone)	Breath focus (resonance of the air noise)	Upper harmonics	Second, detuned pipe layer	Chiff (attack noise)
Mandoline: plucked string model with plectrum tremolo	No effect	Sustain	Brightness	No effect	Plectrum tremolo depth (14 Hz)
Guitare: plucked string model with a soft attack	No effect	Sustain (long at high values)	Brightness	No effect	No effect
Accordeon: three detuned reeds with formants	Formant position	Formant level	Brightness	Musette detune between the reeds	Bellows noise
Choeur: five detuned saws with vowel formants	Vowel (formant position)	Formant level	Brightness	Ensemble detune	Breath noise
Carillon: four inharmonic bell partials	No effect	Ring length	Upper partials	No effect	Strike noise

On every engine, BODY also controls the filter resonance (from flat at 0 to a gentle peak at 1).

Factory presets

OCCITANIE includes 70 factory presets in 7 banks of 10. Loading a factory preset resets every parameter before applying the preset. The pitch bend and modulation wheels are not changed. Most banks use the engine of the same name; exceptions are noted. Bank and preset names are shown exactly as they appear in the plugin (French, with place names of the region such as Capitole, Garonne, Albi and Carcassonne).

Cabrette & Cornemuse (Cabrette engine) Capitole Cabrette, Canal du Midi, Garonne Drone, Pic du Midi, Fete Votive, Cabreta Triste, Bal Bagpipe, Corbieres, Pastel Bleu, Saint Sernin.

Vielle & Cordes frottees (Vielle engine) Roue de Cordes, Trompette Buzz, Bourdon Albigeois, Menestrel, Troubadour, Chant Cathare, Rouergue, Brume du Tarn, Chanterelle, Cordes sur Ciel.

Flutes & Galoubet (Galoubet engine) Galoubet Joyeux, Tambourin Air, Flute de Berger, Fifre Camargue, Pastoral, Mistral, Tramontane, Flute Cathare, Sifflet Occitan, Aube Corbieres.

Cordes pincees (Guitare engine; Mandoline Toulousaine, Mandoline Tremolo, Cistre, Plectre Doux uses Mandoline) Mandoline Toulousaine, Mandoline Tremolo, Guitare Gitane, Luth Medieval, Cistre, Guitare Nylon Soft, Plectre Doux, Strum du Midi, Pizz Menestrel, Theorbe Grave.

Accordeon & Musette (Accordeon engine) Musette Toulouse, Bal Musette, Valse Violette, Accordeon Cabaret, Java du Midi, Soufflet Lent, Harmonium Chapelle, Orgue de Barbarie, Gavotte, Cassoulet Musette.

Choeurs & Pads (Choeur engine; Brume Ariege uses Vielle) Choeur Cathare, Montsegur, Carcassonne Pad, Cite Medievale, Voix d Oc, Plainchant Albi, Lune d Oc, Abbaye Moissac, Brume Ariege, Crypte Saint Sernin.

Carillons & Textures (Carillon engine; Vent d Autan uses Galoubet; Orage Cevenol uses Vielle) Carillon Capitole, Cloches Saint Etienne, Angelus du Soir, Clocher d Albi, Glockenspiel Rose, Cristaux Ariege, Rosee Garonne, Vent d Autan, Orage Cevenol, Etoiles d Oc.

User presets. Save writes the current sound as a `.occpreset` file in `Documents\DJBILBOX BEATS\OCCITANIE\Presets`. Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .occpreset file…** to load a preset from another folder. Your sound is also saved inside your FL Studio project.

Production tips

- **Bagpipe lines.** Start from **Canal du Midi**: Cabrette engine, Mono, short glide and DRONE at 0.5. **REED** moves the nasal formant, **TEXTURE** adds breath and a puff at each attack. The drone is part of each voice: it follows the note you play and stops with it. For a fixed drone under a moving melody, hold one long low note on a second OCCITANIE channel.
- **Oriental and Rai melodies.** Use the Accordeon engine with **WIDTH** between 0.6 and 0.85 for a wide musette detune. Switch to **Mono** and set **GLIDE** to 0.05 to 0.1 s for slides between notes. Use the pitch wheel (±2 semitones) for ornaments. For vibrato, set the LFO to **Pitch**, **RATE** to 5 or 6 Hz and push the modulation wheel only on long notes.
- **Hurdy-gurdy buzz.** On the Vielle engine, **TEXTURE** drives the buzzing bridge. **Trompette Buzz** pushes it to 0.85. Combine it with **DRONE** and a slow **ATTACK** (0.1 to 0.3 s) for a bowed, medieval feel.
- **Plucked hooks for Afrotrap and Drill. Mandoline Toulousaine** and **Strum du Midi** cut through a busy beat. On the Mandoline engine, **TEXTURE** adds the fast plectrum tremolo. On both string engines, **BODY** sets how long the string rings and **BRIGHT** how bright it sounds. **Theorbe Grave** gives a deep plucked bass line in Mono.
- **Choirs and chant.** On the Choeur engine, **REED** selects the vowel. **Voix d Oc** sends a slow LFO to **Timbre** so the vowel keeps moving. Add **DRONE** (0.3 to 0.4) for a plainchant effect, as in **Plainchant Albi**.
- **Bells for intros.** On the Carillon engine, **BODY** sets the ring length and **BRIGHT** the upper partials. Set **PITCH** to -12 for large tower bells (**Cloches Saint Etienne**). A dotted delay and a long reverb turn a single hit into an intro.
- **Layering in a Trap or Hip-Hop mix.** Folk sounds can fill the low mids. Choose **High Pass** in the filter mode menu and raise **FILTER** to 150 to 300 Hz to make room for the 808 and the kick. Lower **DRONE** on dense chords.
- **Delay in time with the beat.** TIME is set in seconds. Quarter note = 60 / BPM. Eighth note = 30 / BPM. Dotted eighth = 45 / BPM. At 100 BPM, a quarter note is 0.6 s.

MIDI, automation and performance

- **Notes.** OCCITANIE responds to all MIDI notes (0 to 127) on all MIDI channels, tuned to equal temperament with A4 = 440 Hz. Middle C is MIDI note 60 (C5 in FL Studio).
- **Polyphony.** 16 voices in Poly mode. When you play more than 16 notes, the oldest note is cut to make room; the lowest and highest held notes are protected. In Mono mode, each new note releases the previous one (its release tail still sounds). Releasing a note does not bring back an earlier held note.
- **Velocity.** Velocity changes the volume according to the VEL slider.
- **Pitch bend.** ±2 semitones. The MIDI pitch wheel and the on-screen wheel add together.
- **Modulation (CC1).** Adds up to 0.8 to the LFO AMOUNT. The higher of MIDI CC1 and the on-screen wheel is used. MIDI CC1 is read by the notes that are sounding when you move the wheel.
- **Sustain pedal (CC64).** Supported. Aftertouch and other MIDI CCs are ignored. Use host automation for everything else.
- **Automation in FL Studio.** Every parameter in the table can be automated. Move a control on the OCCITANIE panel, then choose **Tools > Last tweaked > Create automation clip**. To use a hardware knob, choose **Tools > Last tweaked > Link to controller** and move the knob. Volume, pitch, bend and cutoff changes are smoothed to avoid zipper noise.
- **Latency.** 0 samples. No delay compensation is needed. The plugin reports a 12-second tail to the host so that delay and reverb tails are not cut when you render.
- **CPU.** OCCITANIE uses no samples and streams nothing from disk. The CPU load grows with the number of sounding notes. The five-saw Choeur engine is the heaviest. Effects at zero are bypassed and use no CPU. Long release times, common on pads and bells, keep voices active longer.
- **Sample rates.** 44.1, 48, 88.2 and 96 kHz.

FAQ

I hear no sound. Check that the OCCITANIE channel is routed to a Mixer track and that the channel is not muted. Check VOLUME. With Low Pass selected, a very low FILTER setting can silence the sound. With High Pass selected, a high FILTER setting removes low notes. Finally, remember that the on-screen keyboard plays very low notes in version 1.0: test with a MIDI keyboard or the Piano roll.

OCCITANIE does not appear in FL Studio. OCCITANIE is a 64-bit VST3 plugin. Check that `OCCITANIE.vst3` is in `C:\Program Files\Common Files\VST3`. In FL Studio, open **Options > Manage plugins** and click **Find installed plugins**. Look for **OCCITANIE** under **Generators**, manufacturer **DJBILBOX BEATS**.

The drone changes pitch with my melody. This is by design. DRONE adds a tone one octave below each note you play, so it moves with the melody. For a fixed drone, play one sustained low note on a separate channel.

Where is the filter resonance control? OCCITANIE has no separate resonance knob. BODY raises the resonance gently while it shapes the engine.

The sound gets quieter when I turn REVERB fully down. In version 1.0, the reverb stage also lifts the dry signal by about 6 dB while it is active. At 0 the reverb is bypassed, so the overall level drops. For a dry sound at the usual level, leave REVERB at a very low value such as 0.01, or compensate with VOLUME.

OCTOPUS

Abyssal synthesizer: kraken subs, bubble plucks, coral bells, abyss pads, ink reese, tentacle leads, siren choirs and whale song from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

OCTOPUS is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Kraken Sub (a sine sub with a pitch “knock” and saturation), Bubble Pluck (a sine whose pitch rises quickly, like a bubble), Coral Bells (an FM bell), Abyss Pad (five detuned saws with breath noise and a breathing filter), Ink Reese (detuned saws with a sub and saturation), Tentacle Lead (two pulse waves with a modulated width), Siren Choir (five saws through vowel formants) and Whale Song (a sine with slow glissandos, a harmonic and a resonance).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The character is deep, wet and underwater.

OCTOPUS targets dark Trap and Drill sub lines, ambient and cinematic beds, Lo-Fi textures and sound design. 44 presets load in Poly mode with up to 16 voices; 26 load in Mono mode for single-note lines.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **OCTOPUS** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **OCTOPUS - Init Patch**: the Kraken Sub engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 84 (C3 to C7 in FL Studio naming, where middle C is C5).
5. Shape the sound with the main controls:
   - **TONE, BODY, BRIGHT, WIDTH, TEXTURE**: the small knobs under the title, which reshape the selected engine.
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker sound.
   - **GLIDE**: slide time between notes. Leave it at zero for straight notes.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

Center. The octopus camel artwork, the OCTOPUS title and “By Humpire”. The dotted grilles on each side of the artwork are decorative.

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, in the same row, is the global transposition (-12 to +12 semitones). It is not an LFO control.

AMP ENVELOPE (left, below the LFO). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Character row (center, under the title). Seven small knobs, left to right: **TONE, BODY, BRIGHT, WIDTH, TEXTURE, RES** (filter resonance) and **ENV AMT** (filter envelope depth). **GLIDE** and **CUTOFF** are two larger knobs to their right.

FILTER ENVELOPE (top right). Five vertical sliders: **ATK, DEC, SUS, REL** and **VELOCITY** (velocity sensitivity of the level). The **VOLUME** knob sits below them.

Effects (right). REVERB, CHORUS, DISTORTION on the upper row. **DLY MIX** (delay level), **DLY TIME** and **FEEDBACK** (delay repeats) on the lower row.

Menu row. Five drop-down menus, each with a caption: **ENGINE** (Waveform), **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels. Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard. Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

OCTOPUS exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Kraken Sub, Bubble Pluck, Coral Bells, Abyss Pad, Ink Reese, Tentacle Lead, Siren Choir, Whale Song	Kraken Sub	Selects the synthesis engine.
TONE	0 to 1	50 %	Character control 1. Engine-dependent (see the table below).

Parameter	Range	Default	Function
BODY	0 to 1	50 %	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	50 %	Character control 3 (brightness). Engine-dependent.
WIDTH	0 to 1	30 %	Character control 4. Engine-dependent (detune, vibrato, sweep speed…). It is not a stereo width control.
TEXTURE	0 to 1	20 %	Character control 5. Engine-dependent (noise, click, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	15 %	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode (state-variable filter, 12 dB per octave). Band Pass gets a small level boost.
ENV AMT (Filter Env Amount)	0 to 1	0 %	Filter envelope depth. At 100 % the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0 %	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	50 %	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN	0 to 1	70 %	Amplitude envelope sustain level.
RELEASE	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME	0 to 1 (shown in dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.

Parameter	Range	Default	Function
GLIDE	0 to 2 s	0 s	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced. The LFO restarts at every new note.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 0.8 to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION	0 to 1	0 %	Saturation on the summed output, with automatic level compensation.
CHORUS	0 to 1	0 %	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0 %	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	35 %	Number of delay repeats (0 to 90% feedback).
REVERB	0 to 1	25 %	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.

Parameter	Range	Default	Function
Mod Wheel	0 to 1	0 %	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT; the larger of this wheel and MIDI CC1 applies.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Kraken Sub	Pitch “knock” at the attack	Adds the octave harmonic	Attack click	No effect	Saturation
Bubble Pluck	Pitch rise amount	Length of the bubble (rise time and decay)	Second harmonic level	No effect	Attack click
Coral Bells	Modulator ratio (1.4 to 4.5)	Ring length	FM depth (bell brightness)	Detune between the two carriers	Attack noise
Abyss Pad	No effect	Level of a sine one octave below	Breathing low-pass opening	Detune spread of the five saws	Breath noise
Ink Reese	Sub level	Detune amount	Low-pass opening	Saturation drive	Noise
Tentacle Lead	Depth of the pulse-width modulation	Detune of the second pulse	Low-pass opening	Speed of the pulse-width modulation (0.3 to 5.3 Hz)	Level of a sine one octave below
Siren Choir	Vowel (a, o, u, i)	Formant level	Low-pass opening	Detune spread of the five saws	Noise
Whale Song	Speed of the slow glissando (0.12 to 0.62 Hz)	Third harmonic level	Second harmonic level	Depth of the glissando	Level of the resonant noise at twice the pitch

Factory presets

OCTOPUS includes 70 factory presets in 7 banks of 10. 44 presets load in Poly mode and 26 in Mono mode. Mono presets: Kraken Sub (all 10); Ink Reese & Leads (8 of 10); Siren Choir (1 of 10); Whale Song (7 of 10). 9 presets load with a glide.

Kraken Sub: Kraken Sub, Deep Trench, Pressure Drop, Long Slide Sub, Dirty Kraken, Smooth Tide, Hard Knock Reef, Short Wave, Rumble Below, Submarine.

Bubbles & Drops: Bubble Pluck, Water Drop, Deep Bloop, Rising Bubbles, Reef Marimba, Aqua Arp, Pop Pop, Glass Bubble, Tide Pool, Foam.

Coral Bells: Coral Bell, Shell Chimes, Glass Jellyfish, Pearl, Sunken Bell, Music Box Sea, Echo Chamber, Drift Chimes, Hollow Kalimba, Sonar Ping.

Abyss Pads: Abyss Pad, Ink Cloud, Bioluminescence, Rising Current, Kelp Forest, Dark Water, Surface Light, Whisper Current, Pulse Of The Deep, Drowned Strings.

Ink Reese & Leads: Ink Reese, Eel Bass, Wobble Reef, Octopus Bass, Tentacle Lead, Chrome Squid, Pulse Current, Slow Wave Lead, Sea Cave Lead, Pulse Stab.

Siren Choir: Siren Choir, Ooo Sirens, Ah Mermaids, Ee Deep, Vowel Tide, Whisper Reef, Low Sirens, Lure Song, Coral Chorale, Hollow Chant.

Whale Song: Whale Song, Humpback, Blue Whale Call, Sonar Sweep, Dolphin Click, Siren Of The Deep, Ghost Ship, Distant Pod, Ocean Drone, Sperm Song.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.ocpreset` file. The default folder is `DJBILBOX BEATS/OCTOPUS/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .ocpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Trap and Drill subs.** Start from **Kraken Sub** or **Long Slide Sub** (Kraken Sub bank). Raise TONE for a harder knock on short notes. Add TEXTURE or DISTORTION so the sub stays audible on phone speakers.
2. **Slides.** Presets such as **Long Slide Sub** and **Pressure Drop** use glide. For slides on selected notes only, keep GLIDE at 0 and automate it before the notes that should slide.
3. **Bubbles and drops.** The Bubbles & Drops bank loads in Poly mode: write short staccato notes. BODY sets the length of each bubble.
4. **Underwater bells.** On the Coral Bells engine, TONE sets the bell ratio and BRIGHT the FM depth. Add REVERB and DLY MIX for a wet space.
5. **Abyss pads.** Raise the ATTACK and RELEASE sliders and keep the filter moving with the LFO set to Filter.
6. **Whale song.** The Whale Song engine glides on its own: TONE sets how fast, WIDTH how far. Play long notes and add reverb.
7. **Siren choir.** TONE selects the vowel; set LFO DESTINATION to Timbre to make it move.
8. **Tempo-matched delay.** DLY TIME is in seconds. Use 60 / BPM for a quarter note.

MIDI, automation and performance

Notes and channels. OCTOPUS responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) returns the MIDI mod wheel to zero.

Other MIDI. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. Level, pitch, bend and cutoff changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples). It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. OCTOPUS uses no samples. Effects set to zero are bypassed and cost no CPU. The plugin works at 44.1, 48, 88.2 and 96 kHz.

FAQ

I hear nothing, or almost nothing, in the Kraken Sub bank. These are Mono presets with low notes. Check VOLUME and CUTOFF, and play from a MIDI keyboard or the Piano roll if the notes are below the on-screen keyboard range.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for the sub, lead and whale presets. Switch it to Poly (up to 16 voices).

Short presets sound quiet. Very short presets have less energy. Raise VOLUME.

OCTOPUS does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **OCTOPUS** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

Is the delay tempo-synced? No. Delay time is in seconds (0.05 to 1 s), and the LFO runs in Hz (0.05 to 20 Hz).

PHANTOM RIDER

Ghost-western synthesizer: theremin, ghost choir, twang guitar, haunted organ, wraith pad, ghost bells, dead bass and whispering wind from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

PHANTOM RIDER is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Theremin (a sine with a vibrato that settles in and a light breath), Ghost Choir (five saws through vowel formants), Twang Guitar (a plucked-string model with a body resonance), Haunted Organ (drawbar-style with a slow flutter), Wraith Pad (five detuned saws with a breathing filter), Ghost Bells (an FM bell), Dead Bass (a sine sub with knock and saturation) and Whisper Wind (noise through two moving formants).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The character is spectral and lonesome, a ghost-town western mood.

PHANTOM RIDER targets dark Trap and Drill toplines, cinematic and horror scoring, spaghetti-western moods and atmospheric intros. 51 presets load in Poly mode with up to 16 voices; 19 load in Mono mode, most of them with glide.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **PHANTOM RIDER** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **PHANTOM RIDER - Init Patch**: the Theremin engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 84 (C3 to C7 in FL Studio naming, where middle C is C5).
5. Shape the sound with the main controls:
   - **TONE, BODY, BRIGHT, WIDTH, TEXTURE**: the five small knobs, which reshape the selected engine.
   - **CUTOFF**: the cutoff of the filter. Turn it down for a darker sound.
   - **GLIDE**: slide time between notes, important for the theremin and whistle presets.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOX BEATS name and the DB logo.

Center. The phantom rider artwork, the PHANTOM RIDER title and “By Humpire”.

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, in the same row, is the global transposition (-12 to +12 semitones). It is not an LFO control.

AMP ENVELOPE (left, below the LFO). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Character controls (center). Two clusters of small knobs. Left of the center: **TONE, BODY** (upper row) and **BRIGHT, WIDTH** (lower row). Right of the center: **TEXTURE, RES** (filter resonance) and **ENV AMT** (filter envelope depth). The large **GLIDE** and **CUTOFF** knobs sit between the two clusters.

FILTER ENVELOPE (top right). Four vertical sliders: **ATK, DEC, REL** and **VELOCITY** (velocity sensitivity of the level). The **VOLUME** knob sits to their right.

Effects (right). REVERB, CHORUS, DISTORTION on the upper row. Under a **DELAY** caption: **DELAY MIX** (delay level), **TIME** and **FEEDBACK** (delay repeats).

Menu row. Five drop-down menus across the panel, each with a caption: **ENGINE** (Waveform), **LFO SHAPE**, **LFO DEST** (Destination), **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels. Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard. Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

PHANTOM RIDER exposes 34 automatable parameters. The host name is shown in parentheses when it differs from the panel label. The filter envelope has no sustain control: it rises and decays to zero, and ENV AMT sets how far it opens the filter.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Theremin, Ghost Choir, Twang Guitar, Haunted Organ, Wraith Pad, Ghost Bells, Dead Bass, Whisper Wind	Theremin	Selects the synthesis engine.
TONE	0 to 1	50 %	Character control 1. Engine-dependent (see the table below).
BODY	0 to 1	50 %	Character control 2. Engine-dependent.

Parameter	Range	Default	Function
BRIGHT (Brightness)	0 to 1	50 %	Character control 3 (brightness). Engine-dependent.
WIDTH	0 to 1	30 %	Character control 4. Engine-dependent (detune, vibrato, sweep speed…). It is not a stereo width control.
TEXTURE	0 to 1	20 %	Character control 5. Engine-dependent (noise, click, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	15 %	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode (state-variable filter, 12 dB per octave). Band Pass gets a small level boost.
ENV AMT (Filter Env Amount)	0 to 1	0 %	Filter envelope depth. At 100 % the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	50 %	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN	0 to 1	70 %	Amplitude envelope sustain level.
RELEASE	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME	0 to 1 (shown in dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.
GLIDE	0 to 2 s	0 s	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.

Parameter	Range	Default	Function
TRANSPOSE	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced. The LFO restarts at every new note.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 0.8 to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION	0 to 1	0 %	Saturation on the summed output, with automatic level compensation.
CHORUS	0 to 1	0 %	Stereo chorus mix (slow, fixed rate).
DELAY MIX	0 to 1	0 %	Level of the ping-pong delay.
TIME (Delay Time)	0.05 to 1 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	35 %	Number of delay repeats (0 to 90% feedback).
REVERB	0 to 1	25 %	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Mod Wheel	0 to 1	0 %	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT; the larger of this wheel and MIDI CC1 applies.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Theremin	Vibrato speed (4.8 to 6.8 Hz)	Third harmonic level	Second harmonic level	Vibrato depth (fades in over the first moments of the note)	Breath noise
Ghost Choir	Vowel (a, o, u, i)	Formant level	Low-pass opening	Detune spread of the five saws	Noise
Twang Guitar	Pluck hardness	String sustain	String brightness	Frequency of the body resonance (1.1 to 2.5 kHz)	Level of the body resonance
Haunted Organ	Sub-octave drawbar level	Level of the drawbar one octave above	Upper drawbars level	Depth of the slow pitch flutter	Key click
Wraith Pad	No effect	Level of a sine one octave below	Breathing low-pass opening	Detune spread of the five saws	Breath noise
Ghost Bells	Modulator ratio (1.4 to 4.5)	Ring length	FM depth (bell brightness)	Detune between the two carriers	Attack noise
Dead Bass	Pitch “knock” at the attack	Adds the octave harmonic	Attack click	No effect	Saturation
Whisper Wind	Frequency of the first moving formant	Resonance of the first formant	Frequency of the second formant	Speed of the formant movement	Level of a faint sine at the note pitch

Factory presets

PHANTOM RIDER includes 70 factory presets in 7 banks of 10. 51 presets load in Poly mode and 19 in Mono mode. Mono presets: Theremin & Whistles (all 10); Ghost Choir (1 of 10); Twang & Strings (1 of 10); Dead Bass & Wind (7 of 10). 13 presets load with a glide.

Theremin & Whistles: Phantom Theremin, Ghost Whistle, Lonesome Wail, Spectral Sine, Cold Wind Lead, Siren From Beyond, Crystal Voice, Low Moan, Haunt Echo, Fading Signal.

Ghost Choir: Phantom Choir, Ooo Ghosts, Ah Specters, Ee Wraiths, Vowel Haunt, Whisper Gang, Low Spirits, Graveyard Hymn, Dust Chorale, Hollow Chant.

Twang & Strings: Ghost Town Twang, Spaghetti Lead, Dusty Pick, Reverb Surf, Low Rider Gtr, Muted Bounty, Harp Of Bones, Ride Away, Haunted Banjo, Midnight Pluck.

Haunted Organs: Haunted Organ, Chapel Of Dust, Funeral March, Carnival Of Souls, Whisper Pipes, Cellar Door, Full Ghost Stops, Dying Swell, Fog Organ, Last Hymn.

Wraith Pads: Wraith Pad, Fog Bank, Dead Moon, Cold Breath, Rising Dread, Moaning Strings, Dune Spirit, Tomb Drone, Pulse Of The Dead, Phantom Veil.

Ghost Bells: Ghost Bell, Church Of Dust, Chain Chimes, Spirit Glass, Toll For Me, Music Box Ghost, Wind Chimes, Hollow Toll, Cursed Kalimba, Echoing Hall.

Dead Bass & Wind: Dead Bass, Grave Sub, Knock Knock, Rotten Sub, Hearse Drone, Whisper Wind, Howling Gale, Dead Harmonica, Tumbleweed, Ghost Rider Wind.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.prpreset` file. The default folder is `DJBILBOX BEATS/PHANTOM_RIDER/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .prpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Lonesome leads.** Start from **Phantom Theremin** or **Ghost Whistle**. They load in Mono with glide: play legato lines. WIDTH sets the vibrato depth.
2. **Western twang.** On the Twang Guitar engine, TONE sets the pluck hardness and BRIGHT the string brightness (see **Spaghetti Lead**).
3. **Chords in the dark.** The Haunted Organs and Wraith Pads banks load in Poly mode and sound best with long RELEASE and REVERB.
4. **Bells for intros.** On the Ghost Bells engine, BODY sets the ring length and BRIGHT the FM depth. A long reverb and a dotted delay make an intro.
5. **Dead bass.** The Dead Bass engine is a sine sub with a pitch knock: **Dead Bass** and **Grave Sub** are Mono presets for 808-style lines.
6. **Wind and atmosphere.** The Whisper Wind engine is filtered noise: **Ghost Rider Wind** and **Howling Gale** add atmosphere under a beat.
7. **Movement.** Set LFO DESTINATION to Timbre or Filter and raise the mod wheel (or AMOUNT) for slow evolving textures.

MIDI, automation and performance

Notes and channels. PHANTOM RIDER responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) returns the MIDI mod wheel to zero.

Other MIDI. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 34 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. Level, pitch, bend and cutoff changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples). It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. PHANTOM RIDER uses no samples. Effects set to zero are bypassed and cost no CPU. The plugin works at 44.1, 48, 88.2 and 96 kHz.

FAQ

Can I play chords with the theremin presets? They load in Mono. Switch VOICE MODE to Poly for chords.

Is there a filter sustain? No. The filter envelope has attack, decay and release. It decays to zero, and ENV AMT sets its depth.

PHANTOM RIDER does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **PHANTOM RIDER** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

Is the delay tempo-synced? No. Delay time is in seconds (0.05 to 1 s), and the LFO runs in Hz (0.05 to 20 Hz).

ROCKPUNK

Rock'n'roll electric guitar instrument: two modelled strings per note, the "Urban Slayer" amp, four drive types, a filter, an LFO, chorus, reverb and a tempo-syncable delay. 76 factory presets, no recordings.

Type	Instrument (modelled electric guitar)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.1.0
Factory presets	76
Polyphony	8 voices, or Mono
Automatable parameters	65

Overview

ROCKPUNK is a rock guitar you play from MIDI. It ships **no recording**: every note is calculated. Each note runs two modelled strings (**string A**, a rhythm string with a short sustain and a soft pick, and **string B**, a lead string with a long sustain and an aggressive pick). Both strings use a plucked-string model (Karplus-Strong) with a body resonance. A **layer mix** crossfades between them.

The signal then goes through the **Urban Slayer** amp (gain, tone, an asymmetric saturation and a level control), a **drive** stage with four flavours (Soft, Hard, Asymmetric and Fuzz), a resonant **filter** with its own envelope, an **LFO**, a **chorus**, a ping-pong **delay** (free or synced to the tempo), a **reverb**, a stereo **width** control and a limiter.

An optional **sampled layer** plays your own audio files if you drop them in a folder. None are included, and the 76 factory presets do not need it.

Installation

Windows. Run the installer included in your download. Accept the Windows elevation prompt: the VST3 folder is under Program Files, and the installer cannot write there without administrator rights. The plugin is installed as `C:\Program Files\Common Files\VST3\ROCKPUNK.vst3`. The installer is not code-signed, so Windows SmartScreen may show a warning: click **More info**, then **Run anyway**.

macOS. Copy `ROCKPUNK.vst3` to `/Library/Audio/Plug-Ins/VST3` and, for Logic, `ROCKPUNK.component` to `/Library/Audio/Plug-Ins/Components`, or use the installer package of your download. The package is not notarized by Apple: if macOS refuses to open it, use **System Settings > Privacy & Security > Open Anyway**.

After installing, restart your host and force a plugin rescan. In FL Studio, open **Options > Manage plugins** and click **Find installed plugins**; the plugin is listed as **ROCKPUNK** under **Generators**.

Where are the files?

What	Windows	macOS
Plugin	`C:\Program Files\Common Files\VST3\ROCKPUNK.vst3`	`/Library/Audio/Plug-Ins/VST3` (and `Components` for the Audio Unit)
Presets (factory and yours)	`Documents\DJBILBOX\ROCKPUNK\Presets`	`Documents/DJBILBOX/ROCKPUNK/Presets`

What	Windows	macOS
Your audio files	`Documents\DJBILBOX\ROCKPUNK\Samples`	`Documents/DJBILBOX/ROCKPUNK/Samples`

The factory presets travel inside the plugin and are copied to your Documents folder the first time it runs, without overwriting a file of the same name. Back up the Presets folder: uninstalling never touches it.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **ROCKPUNK**.
2. Click the **folder button** or the preset name in the preset bar and pick a preset by family, or step through the presets with **<** and **>**. Start with **01 Schoolyard Crunch**.
3. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers three octaves (37 keys, C2 to C5).
4. Make sure at least one of the two **speaker grills** in the center of the panel is lit: they switch string A and string B on and off.
5. Shape the sound with **DISTORTION**, **FILTER**, **REVERB** and the **WAVEFORM** menu (the pick hardness: Soft, Round, Bright or Sharp).
6. Click the **disk button** to save your own version as a preset.

Interface

Everything is drawn on one faceplate. The window opens at 1000 x 746 pixels and can be resized from 500 to 2000 pixels wide; the whole panel scales and the proportions stay fixed.

Mouse. Drag knobs and faders up or down. Hold Shift for fine control. Double-click a knob, fader or wheel to return it to its default value. The mouse wheel over a knob or fader nudges it. Hover over any control to read what it does.

Preset bar (top center). The folder button or the preset name opens the list of presets sorted by family. **<** and **>** load the previous and next preset. The disk button saves the current sound as a preset (`.rpk` file).

EXPANSION cassette (top left). Click it to open a menu:

- **Init patch**: every control back to its default value.
- **Open preset file…**: load any `.rpk` file.
- **Save preset as…**: same as the disk button.
- **Show presets folder**: opens `Documents\DJBILBOX\ROCKPUNK\Presets`.
- **Delay on / Delay synced**: switch the delay on and lock it to the host tempo.
- **Your samples**: the optional sampled layer (see below).
- **About**.

LFO (left panel). RATE (0.05 to 20 Hz), **AMOUNT** (depth of the LFO on the destination chosen with DESTINATION) and **PITCH** (vibrato depth, whatever the destination).

Volume envelope (left panel faders). ATTACK, DECAY, SUSTAIN, RELEASE: from a dry, short rhythm sound to a pad that swells in.

Filter envelope (right panel faders). A, S, D, R shape the filter sweep, in the order shown on the panel. The fifth fader, **VELOCITY**, sets how much your playing dynamics shape each note (at zero, every note attacks the same).

Knobs.

- **GLIDE**: time taken to slide from one note to the next.
- **FILTER**: filter cutoff. Turning it switches the filter on if FILTER TYPE is Off.
- **VOLUME**: master level.

- **REVERB**: amount of reverb.
- **CHORUS**: amount of chorus (stereo widening).
- **DISTORTION**: amount of drive after the amp.
- **TIME**: delay time. Turning it switches the delay on.
- **FEEDBACK**: number of delay repeats. Turning it switches the delay on.

Speaker grills (center, on either side of the logo). They are switches: click one to mute or restore the matching string. A lit dot at the top means the string is on. If you hear nothing, check that at least one grill is lit.

Drop-down selectors (bottom).

- **WAVEFORM**: how hard the pick is: Soft, Round, Bright or Sharp.
- **LFO SOURCE**: shape of the LFO: Sine, Triangle, Square or S&H.
- **DESTINATION**: what the LFO moves: Pitch, Filter, Volume or Drive.
- **FILTER TYPE**: Low-pass, Band-pass, High-pass or Off.
- **MONO/POLY**: Poly (8 notes), or Mono to play one note at a time and let GLIDE join them.

Wheels (bottom left). PITCH BEND moves the pitch by plus or minus two semitones and springs back to the middle. **MODULATION** opens the vibrato; it also follows MIDI CC1 from your keyboard.

Keyboard (bottom). Three octaves, C2 to C5. Click and slide to play; it also lights up with the MIDI notes it receives. The panel has a neon animation: keys, knobs, faders, wheels and grills light up when you hover over them and while you play.

The sound path

MIDI notes go to a synthesizer of 8 voices. Each voice has two strings (A and B), each with a body resonance. The two strings are blended by the **Layer Mix** (an equal-power crossfade). The mixed signal goes through the **Urban Slayer** amp (pre-gain, a tone filter, an asymmetric saturation that adds second and third harmonics, and an output level), then the **Drive** stage (Soft, Hard, Asymmetric or Fuzz, with its own tone filter), the **Delay** (stereo ping-pong, free or synced, with a low-pass filter in the loop), the **Width** control (mid/side), the **Volume** and a final soft limiter. A note keeps the same position in the stereo field every time you play it (the pan depends on the note name).

Parameters

ROCKPUNK has 65 automatable parameters. The controls on the faceplate are listed first. Some settings have no knob on the faceplate but can be automated from the parameter list of your host.

Controls on the faceplate

Control	Host name	Range	Default	Function
ATTACK	Attack	0.5 to 2,000 ms	3 ms	Volume envelope attack.
DECAY	Decay	1 to 4,000 ms	600 ms	Volume envelope decay.
SUSTAIN	Sustain	0 to 100 %	70 %	Volume envelope sustain level.
RELEASE	Release	1 to 5,000 ms	220 ms	Volume envelope release.
GLIDE	Glide	0 to 1,000 ms	0	Time to slide between notes.
MONO/POLY	Mono	Poly, Mono	Poly	Mono plays one note at a time.

Control	Host name	Range	Default	Function
FILTER TYPE	Filter Type	Low-pass, Band-pass, High-pass, Off	Off	Filter mode.
FILTER	Filter	60 Hz to 18 kHz	14 kHz	Filter cutoff.
A, S, D, R (right faders)	Filter Attack, Filter Decay, Filter Sustain, Filter Release	0.5 to 2,000 ms; 1 to 4,000 ms; 0 to 100 %; 1 to 5,000 ms	5 ms, 400 ms, 100 %, 300 ms	Filter envelope.
VELOCITY	Velocity	0 to 100 %	60 %	How much velocity shapes each note.
RATE	LFO Rate	0.05 to 20 Hz	5 Hz	LFO speed.
AMOUNT	LFO Amount	0 to 100 %	0 %	LFO depth on the destination.
PITCH	LFO Pitch	0 to 100 %	0 %	Vibrato depth.
LFO SOURCE	LFO Wave	Sine, Triangle, Square, S&H	Sine	LFO shape.
DESTINATION	LFO Destination	Pitch, Filter, Volume, Drive	Filter	What the LFO moves.
WAVEFORM	Pick Shape	Soft, Round, Bright, Sharp	Round	Pick hardness.
VOLUME	Volume	-60 to +6 dB	-3 dB	Master level.
REVERB	Reverb	0 to 100 %	18 %	Reverb amount.
CHORUS	Chorus	0 to 100 %	0 %	Chorus amount.
DISTORTION	Drive	0 to 100 %	20 %	Amount of the drive stage after the amp.
TIME	Delay Time	10 ms to 2 s	350 ms	Delay time (when not synced).
FEEDBACK	Delay Feedback	0 to 95 %	40 %	Delay repeats.
Pitch Bend wheel	Pitch Bend	-2 to +2 semitones	0	Pitch bend.
Modulation wheel	Modulation	0 to 100 %	0 %	Vibrato depth (also follows CC1).
Left speaker grill	Layer A On	Off, On	On	Switches string A on or off.
Right speaker grill	Layer B On	Off, On	On	Switches string B on or off.

Settings without a faceplate control (host automation)

Host name	Range	Default	Function
Layer Mix	0 to 100 %	50 %	Crossfade between string A and string B.
Width	0 to 100 %	80 %	Stereo width (mid/side).
Limiter	Off, On	On	Final soft limiter.

Host name	Range	Default	Function
Layer A Blend, Tone, Body, Sustain, Pick	0 to 100 %	80, 60, 30, 35, 30 %	Blend, tone, body resonance, sustain and pick brightness of string A.
Layer A Level	0 to 100 %	100 %	Level of string A.
Layer B Blend, Tone, Body, Sustain, Pick	0 to 100 %	90, 25, 25, 55, 70 %	Same controls for string B.
Layer B Level	0 to 100 %	100 %	Level of string B.
Amp On	Off, On	On	Switches the Urban Slayer amp. Off passes the strings straight through.
Amp Gain	0 to 24 dB	6 dB	Amp pre-gain.
Amp Distortion	0 to 100 %	55 %	Amount of asymmetric saturation.
Amp Tone	100 Hz to 10 kHz	2.5 kHz	Tone filter of the amp.
Amp Level	-12 to +12 dB	0 dB	Amp output level.
Drive Type	Soft, Hard, Asym, Fuzz	Soft	Character of the drive stage.
Drive Tone	100 Hz to 10 kHz	2.5 kHz	Tone filter of the drive stage.
Delay On	Off, On	Off	Switches the delay (turning TIME or FEEDBACK also switches it on).
Delay Sync	Off, On	Off	Locks the delay time to the host tempo.
Delay Division	1/16, 1/8T, 1/8, 1/4T, 1/4, 1/2, 1 bar, 2 bar, 4 bar	1/8	Note value when synced.
Delay Mix	0 to 100 %	25 %	Level of the delay.
Delay LP	100 Hz to 20 kHz	5 kHz	Low-pass filter inside the delay loop.
Reverb Size	0 to 100 %	60 %	Size of the reverb.
Filter Resonance	0.5 to 8	0.9	Resonance of the filter.
Sample On, Sample Index, Sample Root Offset, Sample Level, Sample Loop, Sample Attack, Sample Release	see below	Off, 0, 0, 80 %, Off, 5 ms, 250 ms	Controls of the optional sampled layer.

The sampled layer defaults to Off, so it does not affect any factory preset.

Your own guitars (optional)

The sampled layer plays your files. Drop `.wav`, `.aif` or `.flac` files in `Documents\DJBILBOX\ROCKPUNK\Samples`, then click the cassette and choose **Your samples**, and pick a file. It plays across the whole keyboard. ROCKPUNK measures the note of each file to tune the keyboard; if the measurement lands beside the note (chords and riffs are ambiguous), use the

Sample Root Offset parameter from your host to correct it. Sub-folders become categories in the list (for example `Samples/Rhythm/palm-mute-E.wav`). The folder is empty after installation, and that is normal: the factory presets only use the two modelled strings. Use only recordings you have the right to use.

Factory presets

ROCKPUNK includes 76 factory presets. They are numbered and grouped by family, and all of them are set to the same level, so moving from one to another gives no jump in volume. None of them needs the Samples folder.

Crunch rhythm (14 presets, numbers 1 to 14): 01 Schoolyard Crunch, 02 Dirty Alley Riff, 03 Bar Fight Boogie, 04 Blacktop Shuffle, 05 Stadium Stomp, 06 Highway Dust, 07 Loud And Guilty, 08 Steel Toe Boots, 09 Rattlecan Red, 10 Curfew Breaker, 11 Two Bar Warning, 12 Half Past Loud, 13 Smokestack Strut, 14 Rust Belt Anthem.

Leads (12 presets, numbers 15 to 26): 15 Leather Jacket Lead, 16 The Long Encore, 17 Last Call, 18 Screaming Treble, 19 Third Encore, 20 Pocket Knife Lead, 21 Gutter Star, 22 Barbed Wire Bend, 23 Nine Volt Heart, 24 Siren Lead, 25 Empty Stage, 26 Backstage Pass.

High gain (10 presets, numbers 27 to 36): 27 Amp On Fire, 28 Six String Riot, 29 Whiskey Throttle, 30 Gravel And Gasoline, 31 Broken Bottle Blues, 32 Iron Lung Crunch, 33 Wrecking Yard, 34 Bad Ignition, 35 Full Throttle Choir, 36 Sweat And Sparks.

Clean (12 presets, numbers 37 to 48): 37 Clean Getaway, 38 Chrome Bumper, 39 First Gear, 40 Train Yard Twang, 41 Back Row Boogie, 42 Cold Start Clean, 43 Lipstick Pickup, 44 Motel Neon, 45 Paper Cup Whiskey, 46 Alley Cat Strut, 47 Cellar Door, 48 Closing Time Chords.

Bare strings (8 presets, numbers 49 to 56): 49 Sunday Sermon, 50 Porch Light, 51 Open Road Steel, 52 Double Denim, 53 Ashtray Ballad, 54 Slow Burn Sunday, 55 Tin Roof Rumble, 56 Velvet Bruise.

Nocturnal (8 presets, numbers 57 to 64): 57 Midnight Mechanic, 58 Neon Garage, 59 Nightshift Riff, 60 Cheap Hotel, 61 Static Highway, 62 Last Bus Home, 63 Diesel Sunday, 64 Amp In The Rain.

Textures (8 presets, numbers 65 to 72): 65 Feedback Chapel, 66 Warehouse Echo, 67 Dust Devil, 68 Overdrive Sunset, 69 Rooftop Riot, 70 Chrome And Bone, 71 Dead Battery, 72 Nightshift Wah.

Low end (4 presets, numbers 73 to 76): 73 Rusty Thunder, 74 Iron Ballast, 75 Anvil Chorus, 76 Bottom Feeder.

Loading a preset replaces the current settings with the preset. **User presets** are saved as `.rpk` files in `Documents\DJBILBOX\ROCKPUNK\Presets` and appear in the preset list. A `.rpk` file is the plugin state in XML. Do not rename a factory preset file: saved projects find their preset by its name.

Production tips

1. **Riffs.** Start from the Crunch rhythm family (01 to 14): the dry attack and short notes suit palm-muted riffs. Play power chords in Poly mode.
2. **Leads.** The Leads family sustains and uses delay and vibrato. Set MONO/POLY to Mono and raise GLIDE for slides.
3. **High gain.** The High gain family uses the Fuzz and Asymmetric drive types. Lower VOLUME if the level feels too hot.
4. **Clean parts.** The Clean family uses the amp on a clean gain with chorus and delay.
5. **Use the strings.** Switch one of the two speaker grills off to hear string A (rhythm) or string B (lead) alone.
6. **Delay in time.** Choose **Delay synced** in the cassette menu, then set the Delay Division from your host's parameter list.
7. **Movement.** Set DESTINATION to Filter or Drive and raise AMOUNT for textures (see the Textures family).

MIDI, automation and performance

Notes. ROCKPUNK responds to MIDI notes on any MIDI channel, with up to 8 voices. Velocity shapes each note according to the VELOCITY fader.

Pitch bend and modulation. MIDI pitch bend covers plus or minus two semitones. CC1 and the MODULATION wheel open the vibrato.

Automation in FL Studio. All 65 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob.

FAQ

The plugin does not appear in my DAW. Check that the plugin scan includes `C:\Program Files\Common Files\VST3`, then run a full rescan. In FL Studio, use **Options > Manage plugins > Find installed plugins**.

I hear nothing. Make sure at least one of the two speaker grills is lit: they switch the two strings, and with both off there is nothing left to play. Also check that the plugin is not bypassed and that MIDI reaches it.

The "Your samples" list is empty. That is the normal state of a fresh install: ROCKPUNK ships no recording. Drop your files in `Documents\DJBILBOX\ROCKPUNK\Samples` (cassette, then **Your samples**, then **Open the Samples folder**).

Where are my presets? In `Documents\DJBILBOX\ROCKPUNK\Presets`. Back this folder up: uninstalling does not touch it.

Can I sell the music I make with ROCKPUNK? Yes, royalty-free and with no credit required. See the license included in the download.

Does it sound like a real guitar? It is a physical model, not a recording. Its character is tight and punchy, built for rock and punk riffs and leads. Audition the presets in your own projects.

Support

djbilboxbeats.com - support@djbilboxbeats.com

SAN ANDREAS LEAD

G-funk lead synthesizer: whistles, Moog-style leads, square leads, talkbox, funk bass, Rhodes-style keys, strings and clav from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

SAN ANDREAS LEAD is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: G-Funk (a sine and a soft saw with a vibrato that fades in and a “whine” on the second harmonic), Moog (two saws, a square and a sub octave), Square (a PWM lead with two detuned pulses), Talkbox (a saw through vowel formants), Bass (a funk bass with a snapping filter), Rhodes (an FM electric piano), Strings (a lowrider string ensemble) and Clav (a narrow pulse with a fast filter).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The character is sunny and smooth, built around gliding mono leads.

SAN ANDREAS LEAD targets G-Funk and West Coast Hip-Hop, funk and R&B hooks, Trap leads and lowrider bass lines. 48 presets load in Mono mode (most with glide) and 22 in Poly mode, up to 16 voices.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **SAN ANDREAS LEAD** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **SAN ANDREAS LEAD - Init Patch**: the G-Funk engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 48 to 96 (C4 to C8 in FL Studio naming, where middle C is C5).
5. Shape the sound with the main controls:
   - **TONE, BODY, BRIGHT, WIDTH, TEXTURE**: the small knobs on each side of the artwork, which reshape the selected engine.
   - **CUTOFF**: the cutoff of the filter.
   - **GLIDE**: slide time between notes. Most lead presets use it.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save), under a **PRESET** caption. The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOX BEATS name and the DB logo.

Center. The artwork, the SAN ANDREAS LEAD title and “By Humpire”.

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, in the same row, is the global transposition (-12 to +12 semitones). It is not an LFO control.

AMP ENVELOPE (left, below the LFO). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Character controls. A column of four small knobs to the left of the artwork: **TONE, BODY, BRIGHT, WIDTH**. A column of three to its right: **TEXTURE, RES** (filter resonance) and **ENV AMT** (filter envelope depth). The large **GLIDE** and **CUTOFF** knobs sit below the artwork, with **VOLUME** to their right.

FILTER ENVELOPE (right). Five vertical sliders: **ATK, DEC, SUS, REL** and **VELOCITY** (velocity sensitivity of the level).

Effects (right). REVERB, CHORUS, DISTORTION on the upper row. Under a **DELAY** caption: **TIME**, **FEEDBACK** and **DELAY MIX** (delay level).

Menu row. Five drop-down menus, each with a caption: **ENGINE** (Waveform), **LFO SHAPE**, **LFO DEST** (Destination), **FILTER TYPE** and **VOICE MODE**.

Wheels. Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard. Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 48 to 96 (four octaves plus one key). The key labels on screen run from C2 to C6, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C4 to C8. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

SAN ANDREAS LEAD exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	G-Funk, Moog, Square, Talkbox, Bass, Rhodes, Strings, Clav	G-Funk	Selects the synthesis engine.
TONE	0 to 1	50 %	Character control 1. Engine-dependent (see the table below).
BODY	0 to 1	50 %	Character control 2. Engine-dependent.

Parameter	Range	Default	Function
BRIGHT (Brightness)	0 to 1	50 %	Character control 3 (brightness). Engine-dependent.
WIDTH	0 to 1	30 %	Character control 4. Engine-dependent (detune, vibrato, sweep speed…). It is not a stereo width control.
TEXTURE	0 to 1	20 %	Character control 5. Engine-dependent (noise, click, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	15 %	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode (state-variable filter, 12 dB per octave). Band Pass gets a small level boost.
ENV AMT (Filter Env Amount)	0 to 1	0 %	Filter envelope depth. At 100 % the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0 %	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	50 %	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN	0 to 1	70 %	Amplitude envelope sustain level.
RELEASE	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME	0 to 1 (shown in dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.
GLIDE	0 to 2 s	0 s	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.

Parameter	Range	Default	Function
TRANSPOSE	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced. The LFO restarts at every new note.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 0.8 to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION	0 to 1	0 %	Saturation on the summed output, with automatic level compensation.
CHORUS	0 to 1	0 %	Stereo chorus mix (slow, fixed rate).
DELAY MIX	0 to 1	0 %	Level of the ping-pong delay.
TIME (Delay Time)	0.05 to 1 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
FEEDBACK (Delay Feedback)	0 to 0.9	35 %	Number of delay repeats (0 to 90% feedback).
REVERB	0 to 1	25 %	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Mod Wheel	0 to 1	0 %	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT; the larger of this wheel and MIDI CC1 applies.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
G-Funk	Level of the soft saw added to the sine	Level of the sine (0.6 to 1.0)	Low-pass opening	Vibrato depth (fades in after 0.15 s)	Level of the second-harmonic “whine”
Moog	Level of the second saw	Level of the sub octave	Low-pass opening	Detune of the second saw	Level of the square
Square	Depth of the pulse-width modulation	Level of the sub octave	Low-pass opening	Detune of the second pulse	Speed of the pulse-width modulation (0.6 to 4.6 Hz)
Talkbox	Vowel (a, o, u, i)	Formant level	Level of the direct, unfiltered saw	Speed and depth of the vowel sweep	Noise
Bass	Saw level	Sub level	Base opening of the filter	Length of the filter snap	Depth of the filter snap
Rhodes	Level of the tine bell partial	Decay length	FM depth	Tremolo speed (4.5 to 7.5 Hz)	Tremolo depth
Strings	Output level (0.6 to 1.0)	Level of a sine at the fundamental	Low-pass opening	Detune spread of the five saws	Noise
Clav	Depth of the filter snap	Length of the filter snap	Base opening of the filter	Pulse width (0.08 to 0.48)	Resonance of the filter snap

Factory presets

SAN ANDREAS LEAD includes 70 factory presets in 7 banks of 10. 22 presets load in Poly mode and 48 in Mono mode. Mono presets: G-Funk Whistles (all 10); Moog Leads (all 10); Square Leads (9 of 10); Talkbox (9 of 10); Funk Bass (all 10). 39 presets load with a glide.

G-Funk Whistles: Compton Whistle, Dre Whine, Long Beach Glide, Sunset Boulevard, Whistle Pure, Sharp Whine, Cruise Control, Hydraulic, High Rider, Nate Dogg Air.

Moog Leads: Moog Lowrider, Fat Funk Lead, Chronic Lead, Saw Cruiser, Slide Lead, Pimp Lead, Smooth Moog, Acid Cali, Octave Sub Lead, Wide Moog.

Square Leads: Square Cruiser, PWM Lowrider, Hollow Square, Chiptune Cali, Wide Pulse, Pulse Slide, Funky Square, Soft Pulse Pad, Buzz Square, Dirty South Lead.

Talkbox: Roger Talk, Talk Ah-Oh, Talk Ee-Oo, Wah Mouth, Robot Funk, Slow Vowel, Choir Talk, Whisper Box, Low Talker, Zapp Voice.

Funk Bass: Funk Slap, Sub Cruiser, G-Funk Bass, Pop Bass, Wobble Low, 808 Cali, Moog Bass, Dirty Funk, Round Bass, Slide Bass.

West Coast Keys: Rhodes Cali, Mellow Rhodes, Bell Rhodes, Tremolo Keys, Funk Clav, Clav Stab, Chrome Pluck, Wah Clav, Piano Funk, Dre Stab.

Lowrider Strings: Lowrider Strings, Sunset Pad, Velvet Strings, Smooth Ensemble, Palm Tree Pad, Hot Summer, Cali Night, Stab Strings, Low Ride Brass, Fog Pad.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.sapreset` file. The default folder is `DJBILBOX BEATS/SAN_ANDREAS_LEAD/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .sapreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Moog, Rhodes and Clav are trademarks of their owners. They are used here only to describe a sound style. DJBILBOX BEATS is not affiliated with the trademark owners.

Production tips

1. **G-funk whistle.** Start from **Compton Whistle** or **Dre Whine**. Keep GLIDE at 0.1 to 0.3 and play legato; raise WIDTH for a deeper vibrato.
2. **Moog-style leads.** The Moog Leads bank loads in Mono with glide. TONE blends the second saw and BODY adds the sub octave (see **Fat Funk Lead**).
3. **Talkbox.** TONE selects the vowel and WIDTH sweeps between vowels. Set LFO DESTINATION to Timbre for movement (see **Talk Ah-Oh**).
4. **Lowrider bass.** The Funk Bass bank loads in Mono. **Sub Cruiser** and **Slide Bass** use glide for 808-style slides.
5. **West Coast keys.** The West Coast Keys bank loads in Poly: Rhodes-style presets (**Rhodes Cali**, **Mellow Rhodes**) and clav presets (**Funk Clav**, **Clav Stab**).
6. **Layering.** Combine a whistle and a bass in two instances for a full G-funk arrangement.
7. **Delay in time with the beat.** TIME is in seconds. Use 60 / BPM for a quarter note.

MIDI, automation and performance

Notes and channels. SAN ANDREAS LEAD responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) returns the MIDI mod wheel to zero.

Other MIDI. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. Level, pitch, bend and cutoff changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples). It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. SAN ANDREAS LEAD uses no samples. Effects set to zero are bypassed and cost no CPU. The plugin works at 44.1, 48, 88.2 and 96 kHz.

FAQ

My chord only plays one note. Most lead, talkbox and bass presets load in Mono. Switch VOICE MODE to Poly (up to 16 voices).

Every note slides into the next one. GLIDE is above zero. Set GLIDE to 0, or automate it only where you want slides.

SAN ANDREAS LEAD does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **SAN ANDREAS LEAD** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

Is the delay tempo-synced? No. Delay time is in seconds (0.05 to 1 s), and the LFO runs in Hz (0.05 to 20 Hz).

SHAMAN

Tribal ritual synthesizer: didgeridoo, tribal drums, jaw harp, spirit flute, chant choir, fire pads, bone chimes and earth drones from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

SHAMAN is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Didgeridoo (a drone with moving formants and a growl), Tribal Drum (a sine with a pitch drop and a noise skin), Jaw Harp (pulses with a “boing” resonance), Spirit Flute (a reed with breath and vibrato), Chant Choir (five saws through vowel formants), Fire Pad (detuned saws with a sub and a breathing filter), Bone Chimes (a dry FM bell with a rattle) and Earth Drone (a fundamental, a fifth and an octave with a slow breathing).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The character is earthy and ritual.

SHAMAN targets tribal and world-music beats, cinematic and ritual scoring, Afro and Latin percussion layers and dark ambient intros. 46 presets load in Poly mode with up to 16 voices; 24 load in Mono mode for single-note lines.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **SHAMAN** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **SHAMAN - Init Patch**: the Didgeridoo engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 84 (C3 to C7 in FL Studio naming, where middle C is C5).
5. Shape the sound with the main controls:
   - **TONE, BODY, BRIGHT, WIDTH, TEXTURE**: the four small knobs at the upper left and the TEXTURE knob at the upper right, which reshape the selected engine.
   - **CUTOFF**: the cutoff of the filter.
   - **GLIDE**: slide time between notes.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJBILBOX BEATS name and the DB logo, in the right speaker area.

Center. The shaman artwork, the SHAMAN title and “By Humpire”.

Left speaker. Four small knobs: **TONE, BODY, BRIGHT, WIDTH**. Below them, the **LFO** group: **RATE, AMOUNT, TRANSPOSE** (the global transposition, -12 to +12 semitones; not an LFO control), then the **AMP ENVELOPE** sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Right speaker. Four small knobs: **TEXTURE, RES** (filter resonance), **ENV AMT** (filter envelope depth) and **DLY MIX** (delay level). Below them, **VOLUME, REVERB, CHORUS, DISTORTION**, then the **FILTER ENVELOPE** sliders: **ATK, DEC, SUS, REL** and **VELOCITY**.

Center knobs. The large **GLIDE** and **CUTOFF** knobs sit under the artwork. **DLY TIME** and **DLY FEEDBACK** are on the right edge.

Menu row. Five drop-down menus, each with a caption: **ENGINE** (Waveform), **LFO SHAPE**, **LFO DEST** (Destination), **FILTER TYPE** and **VOICE MODE**.

Wheels. Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard. Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

SHAMAN exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Didgeridoo, Tribal Drum, Jaw Harp, Spirit Flute, Chant Choir, Fire Pad, Bone Chimes, Earth Drone	Didgeridoo	Selects the synthesis engine.
TONE	0 to 1	50 %	Character control 1. Engine-dependent (see the table below).
BODY	0 to 1	50 %	Character control 2. Engine-dependent.

Parameter	Range	Default	Function
BRIGHT (Brightness)	0 to 1	50 %	Character control 3 (brightness). Engine-dependent.
WIDTH	0 to 1	30 %	Character control 4. Engine-dependent (detune, vibrato, sweep speed…). It is not a stereo width control.
TEXTURE	0 to 1	20 %	Character control 5. Engine-dependent (noise, click, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	15 %	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode (state-variable filter, 12 dB per octave). Band Pass gets a small level boost.
ENV AMT (Filter Env Amount)	0 to 1	0 %	Filter envelope depth. At 100 % the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0 %	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	50 %	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN	0 to 1	70 %	Amplitude envelope sustain level.
RELEASE	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME	0 to 1 (shown in dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.
GLIDE	0 to 2 s	0 s	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.

Parameter	Range	Default	Function
TRANSPOSE	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced. The LFO restarts at every new note.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 0.8 to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION	0 to 1	0 %	Saturation on the summed output, with automatic level compensation.
CHORUS	0 to 1	0 %	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0 %	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
DLY FEEDBACK (Delay Feedback)	0 to 0.9	35 %	Number of delay repeats (0 to 90% feedback).
REVERB	0 to 1	25 %	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Mod Wheel	0 to 1	0 %	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT; the larger of this wheel and MIDI CC1 applies.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Didgeridoo	Formant frequency	Formant level	Low-pass opening	Speed of the formant sweep (0.4 to 4.4 Hz)	Growl (depth and rate, 28 to 68 Hz)
Tribal Drum	Pitch-drop depth	Decay length	Frequency of the skin resonance (0.8 to 3.8 kHz)	Level of the skin	Attack click
Jaw Harp	Depth of the “boing” sweep	Speed of the sweep decay	Resonance frequency	Pulse width	Sharpness of the resonance
Spirit Flute	Breath filter frequency	Breath filter sharpness	Level of the harmonics	Vibrato depth	Breath noise level
Chant Choir	Vowel (a, o, u, i)	Formant level	Low-pass opening	Detune spread of the five saws	Noise
Fire Pad	No effect	Level of a sine one octave below	Breathing low-pass opening	Detune spread of the five saws	Breath noise
Bone Chimes	Modulator ratio (1.4 to 4.5)	Ring length	FM depth	Detune between the two carriers	Rattle (noise) level
Earth Drone	Level of the fifth	Level of the octave	Low-pass opening (breathes slowly)	Speed of the breathing and detune	Noise

Factory presets

SHAMAN includes 70 factory presets in 7 banks of 10. 46 presets load in Poly mode and 24 in Mono mode. Mono presets: Didgeridoo (all 10); Jaw Harp & Drone (5 of 10); Spirit Flute (8 of 10); Chant Choir (1 of 10). 3 presets load with a glide.

Didgeridoo: Earth Didge, Outback Drone, Growl Didge, Wobble Spirit, Deep Breath, Rhythm Didge, Sacred Hum, Bright Didge, Slide Didge, Storm Didge.

Tribal Drums: Tom Low, Tom Mid, Djembe Bass, Djembe Slap, Ritual Taiko, Skin Drum, War Drum, Bongo Hi, Cave Echo, Thunder Skin.

Jaw Harp & Drone: Jaw Harp, Twang Spirit, Mouth Bow, Buzz Rhythm, Cave Jaw, Earth Drone, Stone Circle, Root Pulse, Dark Hollow, Ancestor Hum.

Spirit Flute: Spirit Flute, Breath Flute, Bone Whistle, Shaman Pipe, Mist Flute, Eagle Cry, Hollow Reed, Dream Flute, Overblown, Canyon Wind.

Chant Choir: Chant Ah, Chant Oh, Chant Ee, Elder Voices, Tribe Gather, Whisper Rite, Low Throat, Vowel Sweep, Sky Choir, Ghost Chant.

Fire Pads: Fire Pad, Ember Glow, Campfire, Smoke Rise, Sacred Flame, Dusk Ritual, Sun Dance, Night Watch, Heat Haze, Spirit Smoke.

Bone Chimes: Bone Chimes, Shell Bells, Wood Block, Kalimba Tribe, Rain Stick, Ghost Bells, Marimba Wood, Ritual Gong, Tin Tribe, Dream Chimes.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.shpreset` file. The default folder is `DJBILBOX BEATS/SHAMAN/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .shpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Didgeridoo drones.** Start from **Earth Didge** (Mono). TEXTURE adds the growl and WIDTH sweeps the formant.
2. **Tribal drums.** The Tribal Drums bank loads in Poly. TONE sets the pitch drop and BODY the decay; layer several notes for a drum circle.
3. **Jaw harp.** TONE sets the depth of the “boing” and TEXTURE the sharpness of the resonance.
4. **Spirit flute.** Use **Spirit Flute** or **Eagle Cry**. WIDTH adds vibrato; keep GLIDE small for legato.
5. **Ritual pads.** The Chant Choir and Fire Pads banks are Poly pads. Raise REVERB and the ATTACK slider.
6. **Chimes.** On the Bone Chimes engine, TEXTURE adds a rattle. Use a high TRANSPOSE for small chimes.
7. **Tempo-matched delay.** DLY TIME is in seconds. Use 60 / BPM for a quarter note.

MIDI, automation and performance

Notes and channels. SHAMAN responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) returns the MIDI mod wheel to zero.

Other MIDI. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. Level, pitch, bend and cutoff changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples). It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. SHAMAN uses no samples. Effects set to zero are bypassed and cost no CPU. The plugin works at 44.1, 48, 88.2 and 96 kHz.

FAQ

Is the Tribal Drum a sample? No. It is synthesized: a sine with a pitch drop plus a filtered noise skin.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for the didgeridoo, jaw harp and flute presets. Switch it to Poly (up to 16 voices).

SHAMAN does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **SHAMAN** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

Is the delay tempo-synced? No. Delay time is in seconds (0.05 to 1 s), and the LFO runs in Hz (0.05 to 20 Hz).

STREETLIGHT TRAP

Dark trap synthesizer: 808 subs, trap bells, dark plucks, street keys, neon pads, trap choir, brass stabs and flutes from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

STREETLIGHT TRAP is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: 808 Sub (a sine with a pitch knock and saturation), Trap Bell (an FM bell), Dark Pluck (saws with a closing filter and a pitch dive), Street Keys (an electric-piano model), Neon Pad (detuned saws with a sub), Trap Choir (five saws through vowel formants), Brass Stab (saws with an opening filter) and Flute (a sine with harmonics, breath and vibrato).

Five character controls (TONE, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter with its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. The character is dark and nocturnal.

STREETLIGHT TRAP targets Trap and Drill 808s, bell and pluck melodies, dark pads and choirs, brass stabs and flute hooks. 52 presets load in Poly mode with up to 16 voices; 18 load in Mono mode for single-note lines.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **STREETLIGHT TRAP** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **STREETLIGHT TRAP - Init Patch**: the 808 Sub engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 36 to 84 (C3 to C7 in FL Studio naming, where middle C is C5).
5. Shape the sound with the main controls:
   - **TONE, BODY, BRIGHT, WIDTH, TEXTURE**: the small knobs, which reshape the selected engine.
   - **CUTOFF**: the cutoff of the filter.
   - **GLIDE**: slide time between notes (808 slides).
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (top left). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Logo (top right). The DJ BILBOX BEATS name and the DB logo.

Center. The artwork, the STREETLIGHT TRAP title and “By Humpire”. Two clusters of small knobs sit on each side: **TONE, BODY, BRIGHT, WIDTH** to the left of the artwork, and the large **GLIDE** and **CUTOFF** knobs below it.

LFO section (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, in the same row, is the global transposition (-12 to +12 semitones). It is not an LFO control.

FILTER ENVELOPE (left, below the LFO). Four sliders: **ATK, DEC, SUS, REL**. Next to them: **TEXTURE, RES** (filter resonance) and **ENV AMT** (filter envelope depth). **VELOCITY** (velocity sensitivity of the level) is a small knob, with **REVERB**, in the center-right column.

AMP ENVELOPE (top right). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

EFFECTS (right). CHORUS, DISTORTION, DLY MIX (delay level), **DLY TIME** and **DLY FDBK** (delay repeats) in a row. The **VOLUME** knob sits above the row at the right.

Menu row. Five drop-down menus, each with a caption: **ENGINE** (Waveform), **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**.

Wheels. Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard. Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

STREETLIGHT TRAP exposes 35 automatable parameters. The host name is shown in parentheses when it differs from the panel label.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	808 Sub, Trap Bell, Dark Pluck, Street Keys, Neon Pad, Trap Choir, Brass Stab, Flute	808 Sub	Selects the synthesis engine.
TONE	0 to 1	50 %	Character control 1. Engine-dependent (see the table below).
BODY	0 to 1	50 %	Character control 2. Engine-dependent.
BRIGHT (Brightness)	0 to 1	50 %	Character control 3 (brightness). Engine-dependent.

Parameter	Range	Default	Function
WIDTH	0 to 1	30 %	Character control 4. Engine-dependent (detune, vibrato, sweep speed…). It is not a stereo width control.
TEXTURE	0 to 1	20 %	Character control 5. Engine-dependent (noise, click, saturation…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
RES (Resonance)	0 to 1	15 %	Filter resonance.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode (state-variable filter, 12 dB per octave). Band Pass gets a small level boost.
ENV AMT (Filter Env Amount)	0 to 1	0 %	Filter envelope depth. At 100 % the envelope opens the cutoff up to 5 octaves. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.002 to 3 s	0.002 s	Filter envelope attack time.
DEC (Filter Decay)	0.02 to 4 s	0.3 s	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	0 %	Filter envelope sustain level.
REL (Filter Release)	0.02 to 4 s	0.3 s	Filter envelope release time.
VELOCITY (Velocity Sensitivity)	0 to 1	50 %	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK	0.001 to 5 s	0.01 s	Amplitude envelope attack time.
DECAY	0.01 to 5 s	0.4 s	Amplitude envelope decay time.
SUSTAIN	0 to 1	70 %	Amplitude envelope sustain level.
RELEASE	0.02 to 8 s	0.4 s	Amplitude envelope release time.
VOLUME	0 to 1 (shown in dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.
GLIDE	0 to 2 s	0 s	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE	-12 to +12 semitones	0	Global transposition in whole semitones.

Parameter	Range	Default	Function
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced. The LFO restarts at every new note.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 0.8 to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION	0 to 1	0 %	Saturation on the summed output, with automatic level compensation.
CHORUS	0 to 1	0 %	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0 %	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
DLY FDBK (Delay Feedback)	0 to 0.9	35 %	Number of delay repeats (0 to 90% feedback).
REVERB	0 to 1	25 %	Reverb amount. Higher values also enlarge the room.
Pitch Bend wheel (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
Mod Wheel	0 to 1	0 %	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT; the larger of this wheel and MIDI CC1 applies.

Character controls by engine

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
808 Sub	Pitch “knock” at the attack	Adds the octave harmonic	Attack click	No effect	Saturation

Engine	TONE	BODY	BRIGHT	WIDTH	TEXTURE
Trap Bell	Modulator ratio (1.4 to 4.5)	Ring length	FM depth (bell brightness)	Detune between the two carriers	Attack noise
Dark Pluck	Pitch-dive depth	Length of the filter closing	Initial opening of the filter	Detune between the two saws	Attack noise
Street Keys	No effect	Decay length	Bark: level of the upper partials, stronger with velocity	No effect	Attack noise
Neon Pad	No effect	Level of a sine one octave below	Low-pass opening	Detune spread of the five saws	Noise
Trap Choir	Vowel (a, o, u, i)	Formant level	Low-pass opening	Detune spread of the five saws	Noise
Brass Stab	Time for the filter to open	Output weight	How far the filter opens	Detune of the three saws	Noise
Flute	Breath filter frequency	Breath filter sharpness	Level of the harmonics	Vibrato depth	Breath noise level

Factory presets

STREETLIGHT TRAP includes 70 factory presets in 7 banks of 10. 52 presets load in Poly mode and 18 in Mono mode. Mono presets: 808 & Sub Bass (all 10); Trap Choir (1 of 10); Flutes & FX (7 of 10). 7 presets load with a glide.

808 & Sub Bass: Streetlight 808, Long Slide 808, Dirty 808, Boom Bap Sub, Hard Knock, Deep Cellar, Short 808, Distorted Rumble, Smooth Sub, Pitch Drop.

Trap Bells: Trap Bell, Music Box Trap, Glass Lead, Dark Chimes, Night Bells, Kalimba Trap, Icy Pluck, Haunted Box, Low Bell, Echo Bells.

Dark Plucks: Dark Pluck, Trap Arp, Zap Down, Muted Pluck, Soft Pluck, Pluck Wall, Street Harp, Dark Koto, Drill Pluck, Sad Pluck.

Street Keys: Street EP, Lofi Keys, Bark EP, Trap Soul Keys, Tremolo Keys, Midnight Rhodes, Wurly Bite, Bell Keys, Rooftop Chords, Dusty Piano.

Neon Pads & Brass: Streetlight Pad, Smoke Pad, Alley Strings, Slow Rise, Dream Pad, Dark Drone, Trap Brass, Horn Stab, Soft Brass, Heist Horns.

Trap Choir: Trap Choir, Ooo Voices, Ah Gospel, Ee Ghost, Vowel Drift, Whisper Crowd, Low Choir, Chopped Vox, Hymn In The Rain, Hollow Chant.

Flutes & FX: Trap Flute, Pan Flute, Breathy Flute, Sad Flute, High Whistle, Flute Echo, Wind Lead, Low Flute, Fog Flute, Siren Flute.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.slpreset` file. The default folder is `DJBILBOX BEATS/STREETLIGHT_TRAP/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .slpreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Trap and Drill 808s.** Start from **Streetlight 808** or **Long Slide 808**. Raise TONE for a harder knock on short notes. Raise TEXTURE or add DISTORTION so the 808 stays audible on phone speakers.
2. **808 slides.** With GLIDE above zero, every new note slides from the previous one. For slides on selected notes only, keep GLIDE at 0 and automate it before those notes.
3. **Bell melodies.** On the Trap Bell engine, TONE sets the bell ratio, BODY the ring length and BRIGHT the FM depth. Add DLY MIX for a classic trap bell.
4. **Dark plucks.** The Dark Pluck engine closes its filter after each note: BODY sets how long it takes, BRIGHT how open it starts.
5. **Keys and pads.** The Street Keys and Neon Pads & Brass banks load in Poly. Add CHORUS and REVERB for width.
6. **Brass stabs. Trap Brass** and **Heist Horns** use short ATTACK and SUSTAIN values; TONE sets how quickly the filter opens.
7. **Tempo-matched delay.** DLY TIME is in seconds. Use 60 / BPM for a quarter note.

MIDI, automation and performance

Notes and channels. STREETLIGHT TRAP responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) returns the MIDI mod wheel to zero.

Other MIDI. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 35 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. Level, pitch, bend and cutoff changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples). It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. STREETLIGHT TRAP uses no samples. Effects set to zero are bypassed and cost no CPU. The plugin works at 44.1, 48, 88.2 and 96 kHz.

FAQ

My 808 is not perfectly centered. Each note gets a slight random stereo offset. For a strictly centered sub, reduce the stereo separation of the mixer track in FL Studio, or insert a mono utility after the plugin.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for the 808 and flute presets. Switch it to Poly (up to 16 voices).

STREETLIGHT TRAP does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **STREETLIGHT TRAP** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

Is the delay tempo-synced? No. Delay time is in seconds (0.05 to 1 s), and the LFO runs in Hz (0.05 to 20 Hz).

VOODOO

World-instrument synthesizer: flutes, sitar, oud, kalimba, erhu and a voodoo choir from eight synthesis engines.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	70
Latency	0 samples

Overview

VOODOO is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time by one of eight engines: Flute, Pan Flute and Shakuhachi (three breathy flutes made of harmonics, band-filtered breath noise and an attack chiff), Sitar (a plucked-string model with a jawari buzz and sympathetic strings), Oud (a plucked-string model), Kalimba (four inharmonic modes, like a struck metal tine), Erhu (two detuned saws through formants) and Voodoo Choir (five detuned saws through formants).

Five timbre controls (BREATH, BODY, BRIGHT, WIDTH, TEXTURE) reshape each engine. The sound then goes through a multimode filter, a volume envelope, an LFO and an effects chain: distortion, chorus, ping-pong delay and reverb. VOODOO has no filter envelope, no resonance knob and no velocity-sensitivity control: BODY also sets the filter resonance, and velocity always affects the level of each note (from 35% at the softest to 100% at the hardest). The character is mystic and worldly.

VOODOO targets world-music melodies, Afrobeat and Latin hooks, Trap and Drill ethnic toplines and cinematic and ritual atmospheres. 62 presets load in Poly mode with up to 16 voices; 8 load in Mono mode (the Bass & Plucks bank) for single-note lines.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **VOODOO** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. The plugin opens on **VOODOO - Init Patch**: the Flute engine in Poly mode.
3. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows.
4. Play from your MIDI keyboard or draw notes in the **Piano roll**. The on-screen keyboard covers MIDI notes 48 to 96 (C4 to C8 in FL Studio naming, where middle C is C5).
5. Shape the sound with the main controls:
   - **BREATH, BODY, BRIGHT, WIDTH, TEXTURE**: the five TIMBRE sliders, which reshape the selected engine.
   - **CUTOFF**: the cutoff of the filter.
   - **REVERB**: space around the sound.
6. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first.

EXPANSION cassette (left, below the preset display). Clicking the cassette opens an information message about upcoming expansion packs. No expansion content is included with version 1.0.

Center. The artwork, the VOODOO title and “By Humpire”.

LFO group (left). Under the **LFO** caption, three rows of two knobs: **RATE** and **AMOUNT** (LFO speed and depth), then **TRANSPOSE** (global transposition, -12 to +12 semitones; not an LFO control) and **GLIDE**, then **CUTOFF** and **VOLUME**.

AMP ENVELOPE (center left). Four sliders: **ATK, DEC, SUS, REL**.

TIMBRE (center right). Five sliders: **BREATH, BODY, BRIGHT, WIDTH, TEXTURE**.

EFFECTS (right). REVERB and **CHORUS** on the first row, **DISTORTION** and **DLY MIX** (delay level) on the second row, **DLY TIME** and **DLY FDBK** (delay repeats) on the third row.

Menu row. Five drop-down menus, each with a caption: **ENGINE** (Waveform), **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels. Pitch Bend springs back to the center when you release it. **Modulation** stays where you leave it.

On-screen keyboard. Click a key to play it. Velocity follows the click position: click near the bottom of a key for a louder note. The keyboard covers MIDI notes 48 to 96 (four octaves plus one key). The key labels on screen run from C2 to C6, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C4 to C8. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. The mouse wheel also adjusts controls. A value bubble appears while you drag.

Parameters

Signal flow: engine, then filter, then amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb. A DC blocker and a soft limiter protect the output.

VOODOO exposes 28 automatable parameters. The host name is shown in parentheses when it differs from the panel label. VOODOO has no filter envelope, no filter resonance knob and no velocity-sensitivity control, so those parameters do not exist. The timbre sliders are the parameters named Breath / Vowel, Body / Resonance, Brightness, Width / Detune and Texture in the host.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Flute, Pan Flute, Shakuhachi, Sitar, Oud, Kalimba, Erhu, Voodoo Choir	Flute	Selects the synthesis engine.
BREATH slider (Breath / Vowel)	0 to 1	50 %	Timbre control 1. Engine-dependent: breath, vowel or formant position (see the table below).
BODY slider (Body / Resonance)	0 to 1	50 %	Timbre control 2. Engine-dependent. On every engine, BODY also sets the filter resonance (from a flat response at 0 to a gentle peak at 1).

Parameter	Range	Default	Function
BRIGHT slider (Brightness)	0 to 1	50 %	Timbre control 3: brightness. Engine-dependent.
WIDTH slider (Width / Detune)	0 to 1	30 %	Timbre control 4. Engine-dependent (detune, doubling, sympathetic strings…). It is not a stereo width control.
TEXTURE slider (Texture)	0 to 1	20 %	Timbre control 5. Engine-dependent (chiff, buzz, noise…).
CUTOFF (Filter)	40 to 18,000 Hz	9,000 Hz	Filter cutoff. The cutoff follows the keyboard by 25% around middle C.
FILTER TYPE (menu)	Low Pass, High Pass, Band Pass	Low Pass	Filter mode (state-variable filter, 12 dB per octave). Band Pass gets a small level boost.
ATK (Attack)	0.001 to 5 s	0.01 s	Volume envelope attack time.
DEC (Decay)	0.01 to 5 s	0.4 s	Volume envelope decay time.
SUS (Sustain)	0 to 1	70 %	Volume envelope sustain level.
REL (Release)	0.02 to 8 s	0.4 s	Volume envelope release time.
VOLUME	0 to 1 (shown in dB)	0.7 (-3.1 dB)	Output level of each voice, before the effects.
GLIDE	0 to 2 s	0 s	Portamento. The value is roughly the slide time in seconds. Each new note slides from the pitch of the previous note, in Mono and in Poly mode. 0 turns glide off.
TRANSPOSE	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	4 Hz	LFO speed. Not tempo-synced. The LFO restarts at every new note.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds up to 0.8 to this value.
LFO SHAPE (LFO Source menu)	Sine, Triangle, Saw, Square, Sample&Hold	Sine	LFO shape. Sample&Hold picks a new random value once per cycle.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amp, Timbre	Pitch	LFO target. Pitch: up to +/-1 semitone (vibrato). Filter: up to +/-3 octaves (wobble). Amp: up to 50% level dip (tremolo). Timbre: moves all five character controls by up to +/-0.5.

Parameter	Range	Default	Function
VOICE MODE (Mono/Poly menu)	Poly, Mono	Poly	Poly: up to 16 notes at once. Mono: one note at a time, last-note priority.
DISTORTION	0 to 1	0 %	Saturation on the summed output, with automatic level compensation.
CHORUS	0 to 1	0 %	Stereo chorus mix (slow, fixed rate).
DLY MIX (Delay Mix)	0 to 1	0 %	Level of the ping-pong delay.
DLY TIME (Delay Time)	0.05 to 1 s	0.35 s	Delay time in seconds. Not tempo-synced: for a quarter note, use 60 / BPM (0.5 s at 120 BPM); halve it for an eighth note.
DLY FDBK (Delay Feedback)	0 to 0.9	35 %	Number of delay repeats (0 to 90% feedback).
REVERB	0 to 1	25 %	Reverb amount. Higher values also enlarge the room.
PITCH BEND	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
MOD WHEEL	0 to 1	0 %	On-screen mod wheel. Adds up to +0.8 to the LFO AMOUNT; the larger of this wheel and MIDI CC1 applies.

Character controls by engine

Engine	BREATH	BODY	BRIGHT	WIDTH	TEXTURE
Flute	Balance of breath noise and tone (more breath, less tone)	Focus of the breath band (resonance of the air noise)	Level of the upper harmonics	Level of a second, slightly detuned oscillator	Chiff (attack noise)
Pan Flute	Balance of breath noise and tone (more breath, less tone)	Focus of the breath band (resonance of the air noise)	Level of the upper harmonics	Level of a second, slightly detuned oscillator	Chiff (attack noise)
Shakuhachi	Balance of breath noise and tone (more breath, less tone)	Focus of the breath band (resonance of the air noise)	Level of the upper harmonics	Level of a second, slightly detuned oscillator	Chiff (attack noise)
Sitar	No effect	String sustain	String brightness	Level of the sympathetic strings	Jawari buzz (saturation)
Oud	No effect	String sustain	String brightness	No effect	No effect
Kalimba	No effect	Ring length	Level of the upper partials	No effect	Attack noise

Engine	BREATH	BODY	BRIGHT	WIDTH	TEXTURE
Erhu	Frequency of the two formants	Formant level	Low-pass opening	Detune between the two saws	Noise
Voodoo Choir	Frequency of the two formants	Formant level	Low-pass opening	Detune spread of the five saws	Noise

Factory presets

VOODOO includes 70 factory presets in 7 banks of 10. 62 presets load in Poly mode and 8 in Mono mode. Mono presets: Bass & Plucks (8 of 10). 8 presets load with a glide.

Flutes: Mystic Reed, Moon Whistle, Shaman Breath, Jungle Dawn, Andean Mist, Quena Ghost, Bamboo Spirit, Silver Vibrato, Desert Ney, Temple Whisper.

Raga & Strings: Raga Dusk, Sitar Buzz, Oud Nights, Gypsy Oud, Tanpura Drone, Veena Glow, Erhu Tears, Sarangi Moan, Bazaar Pluck, Maqam Sunrise.

Afrique: Mbira Rain, Kalimba Fire, Savanna Thumb, Kora Dreams, Balafon Sun, Sanza Bells, Tribal Marimba, Griot Pluck, Zulu Chime, Nile Echo.

Amerique Latine: Charango Sun, Zampona Rain, Quena Mountain, Cumbia Pluck, Machu Dawn, Tango Bow, Rio Marimba, Cantina Oud, Andes Echo, Amazon Mist.

Pads Mystiques: Voodoo Choir, Swamp Spirits, Ghost Priestess, Candle Ritual, Bone Orchard, Mystic Dawn, Moon Chant, Veil of Smoke, Hollow Temple, Obsidian Hymn.

Bass & Plucks: Hex Bass, Root Doctor, Gris-Gris Sub, Cursed Pluck, Zombie Walk, Crossroads, Bayou Thump, Mojo Pluck, Skull Drone, Midnight Mojo.

Textures: Fog Over Bayou, Whispers in Smoke, Cauldron, Rain Dance, Ritual Fire, Spirit Wind, Dark Bazaar, Jinn Voices, Ancient Tape, Voodoo Doll.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.voodoopreset` file. The default folder is `DJBILBOX BEATS/VOODOO/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu. Use **Open a .voodoopreset file…** in the same menu to load a file from another location. The preset display shows the file name.

The host also sees the 70 factory presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Flutes.** Start from the Flutes bank. BREATH sets how airy the flute is, BRIGHT its harmonics and TEXTURE the chiff at the start of each note. Add a little vibrato with the LFO set to Pitch (RATE 5 Hz, AMOUNT 0.1) and the mod wheel.
2. **Raga and Arabic strings.** The Raga & Strings bank uses the Sitar, Oud and Erhu engines. On the Sitar engine, TEXTURE drives the jawari buzz and WIDTH the sympathetic strings (see **Sitar Buzz**).
3. **African and Latin hooks.** The Afrique and Amerique Latine banks use the Kalimba, Oud, flute and choir engines. Keep the notes short and add a dotted delay.
4. **Mystic pads.** The Pads Mystiques bank uses the Voodoo Choir engine. BREATH moves the formants; raise ATK and REL and add REVERB.

5. **Bass plucks.** The Bass & Plucks bank loads in Mono, mostly with glide: **Hex Bass** and **Root Doctor** make deep ethnic bass lines.
6. **Movement.** Set LFO DESTINATION to Timbre or Filter and raise the mod wheel (or AMOUNT) for slow evolving textures.
7. **Tempo-matched delay.** DLY TIME is in seconds. Use 60 / BPM for a quarter note.

MIDI, automation and performance

Notes and channels. VOODOO responds to all 128 MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY response (fixed: there is no velocity-sensitivity control).

Polyphony. Up to 16 voices in Poly mode. When you play a 17th note, a voice is taken over and cut immediately. In Mono mode, each new note stops the previous one (last-note priority). Releasing the newest note does not bring back an earlier note that you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen Pitch Bend wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen Modulation wheel. When both are used, the higher value wins. CC1 acts on the notes that are sounding when the message arrives, so move the wheel while you play. For repeatable results in a song, automate the on-screen **Mod Wheel** parameter instead. CC121 (reset all controllers) returns the MIDI mod wheel to zero.

Other MIDI. All Notes Off and All Sound Off messages stop the sound. Aftertouch is ignored.

Automation in FL Studio. All 28 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. Level, pitch, bend and cutoff changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples). It reports a 12-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. VOODOO uses no samples. Effects set to zero are bypassed and cost no CPU. The plugin works at 44.1, 48, 88.2 and 96 kHz.

FAQ

Is there a filter envelope or a resonance knob? No. Shape the sound over time with the volume envelope and the LFO. BODY raises the filter resonance gently while it shapes the engine.

Is there a velocity control? No. Velocity always changes the level of each note, from 35% at the softest to 100% at the hardest.

My chord only plays one note. The VOICE MODE menu is set to Mono, which is the default for the Bass & Plucks bank. Switch it to Poly (up to 16 voices).

VOODOO does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **VOODOO** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

Is the delay tempo-synced? No. Delay time is in seconds (0.05 to 1 s), and the LFO runs in Hz (0.05 to 20 Hz).

WARZONE808

808 bass synthesizer with five waveforms, 7-voice unison, a resonant filter with its own envelope, an LFO and four effects. 60 factory presets plus a 10-preset expansion.

Type	Synthesizer (instrument)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Presets	60 factory presets in 6 banks, plus 10 from the built-in Expansion Vol.1
Latency	0 samples

Overview

WARZONE808 is a synthesizer sold under the HUMPIRE brand by DJBILBOX BEATS. It uses no samples. Every sound is generated in real time from one of five waveforms (sine, square, sawtooth, triangle or noise). Each note can be stacked up to seven times in **unison**, detuned by up to 60 cents and spread across the stereo field. The sound then goes through a multimode filter (low pass, band pass or high pass) with a resonance up to Q 20 and its own envelope, an amplitude envelope, an LFO and an effects chain: distortion, chorus, delay and reverb.

WARZONE808 is built around the 808. It opens in **Mono** mode with last-note priority and legato: when you hold one note and play another, the pitch glides to the new note without retriggering the envelopes, and releasing the new note returns to the note you still hold. Switch **VOICE MODE** to **Poly** for chords (up to 16 voices).

It targets Trap, Drill and Hip-Hop 808s, reese and growl bass, leads, plucks, pads, risers and war-themed sound effects. WARZONE808 has no pitch-drop envelope: a classic 808 kick needs a layered kick or the filter envelope.

Quick start in FL Studio

1. In the **Channel rack**, click **+** and choose **WARZONE808** (vendor **DJBILBOX BEATS**). You can also drag it from the **Plugin database > Generators** browser.
2. Click the **folder icon** at the left of the preset display. Pick a bank, then a preset. You can also step through all 70 presets with the **<** and **>** arrows. Start with **808 Classic** in the 808 Subs bank.
3. Play from your MIDI keyboard or draw notes in the **Piano roll**. 808 notes sit best between MIDI notes 24 and 48 (C2 to C4 in FL Studio naming, where middle C is C5).
4. Shape the sound with the main controls:
   - **CUTOFF**: the cutoff of the filter. Turn it down for a rounder, darker 808.
   - **DISTORTION**: adds harmonics so the 808 stays audible on small speakers.
   - **GLIDE**: slide time between notes, in milliseconds.
5. Adjust **VOLUME** to set the level, then click the **disk icon** to save your own version.

Interface

The window opens at 1000 x 746 pixels. Drag the bottom-right corner to resize it from 50% to 200%. The proportions stay fixed.

Preset display (top center). From left to right: the folder icon (preset menu), the **<** arrow, the current preset name, the **>** arrow and the disk icon (save). The arrows wrap around from the last preset to the first. The preset menu lists the six factory banks (and any expansion pack) as submenus, then a **User** submenu with your saved presets.

EXPANSION cassette (top left). The cassette shows the name of the loaded expansion (Expansion Vol.1). Click it for a menu: **Load a .wz808exp pack…** loads another expansion pack from a file, and **Open the packs folder** opens the folder where packs are loaded automatically at start-up.

Logo (top right). The DJBILBOXBEATS name and the DB logo.

LFO group (left). RATE and **AMOUNT** set the LFO speed and depth. **TRANSPOSE**, in the same row, is the global transposition (-12 to +12 semitones). It is not an LFO control.

AMP ENVELOPE (left, below the LFO). Four sliders: **ATTACK, DECAY, SUSTAIN, RELEASE**.

Center row. From left to right: **RESO** (filter resonance) and **ENV AMT** (filter envelope depth), the large **GLIDE** and **CUTOFF** knobs, then **UNISON**, **DETUNE** and **DLY MIX** (delay level).

FILTER ENVELOPE (top right). Four vertical sliders: **ATK, DEC, SUS** and **VELOCITY** (velocity sensitivity of the level). The filter envelope shares its release time with the amp envelope.

Right panel. VOLUME, REVERB, CHORUS on the upper row, **DISTORTION, DLY TIME, DLY FDBK** on the lower row.

Menu row. Five drop-down menus, each with a caption: **ENGINE** (Waveform), **LFO SHAPE**, **LFO DESTINATION**, **FILTER TYPE** and **VOICE MODE**. Each menu shows its current value.

Wheels (bottom left). PITCH BEND springs back to the center when you release it. **MOD WHEEL** stays where you leave it.

On-screen keyboard (bottom). Click a key to play it. The keyboard covers MIDI notes 36 to 84 (four octaves plus one key). The key labels on screen run from C1 to C5, with middle C labeled C3; in FL Studio naming, where middle C is C5, the same range is C3 to C7. It does not scroll. For notes outside this range, use a MIDI controller or the Piano roll.

Mouse gestures. Drag a knob up or right to increase it. Drag sliders and wheels vertically. Double-click any knob or slider to return it to its default value. A value bubble appears while you drag.

Parameters

Signal flow: oscillator (with unison), filter, amplitude envelope (per voice). The voices are summed, then processed by Distortion, Chorus, Delay and Reverb, then by a soft saturation (tanh) on the output. A DC blocker protects the output.

WARZONE808 exposes 38 automatable parameters. The host name is shown in parentheses when it differs from the panel label. Seven of them have no knob on the panel but can be automated from your host: Distortion Tone, Chorus Rate, Chorus Depth, Reverb Room, Reverb Damping, Reverb Width and Unison Width.

Parameter	Range	Default	Function
ENGINE (Waveform menu)	Sine, Square, Sawtooth, Triangle, Noise	Sine	Oscillator waveform. Noise is used for explosions, gunshots, wind and percussion.
CUTOFF (Filter)	20 to 20,000 Hz	8,000 Hz	Filter cutoff.
RESO (Resonance)	0.5 to 20 Q	1 Q	Filter resonance.
FILTER TYPE (menu)	Low Pass, Band Pass, High Pass	Low Pass	Filter mode.

Parameter	Range	Default	Function
ENV AMT (Filter Env Depth)	0 to 8 octaves	0	How far the filter envelope opens the cutoff. At 0 the filter envelope has no effect.
ATK (Filter Attack)	0.5 to 3,000 ms	1 ms	Filter envelope attack time.
DEC (Filter Decay)	5 to 4,000 ms	300 ms	Filter envelope decay time.
SUS (Filter Sustain)	0 to 1	70 %	Filter envelope sustain level. The filter release is the amp RELEASE.
VELOCITY (Velocity Sensitivity)	0 to 1	40 %	How much note velocity changes the level. 0: all notes at the same level. 1: full velocity response.
ATTACK (Attack)	0.5 to 3,000 ms	2 ms	Amplitude envelope attack time.
DECAY (Decay)	5 to 4,000 ms	300 ms	Amplitude envelope decay time.
SUSTAIN (Sustain)	0 to 1	70 %	Amplitude envelope sustain level.
RELEASE (Release)	5 to 5,000 ms	250 ms	Amplitude envelope release time (also the filter envelope release).
VOLUME (Volume)	0 to 1.5 (shown in dB)	1.0 (0 dB)	Master level.
GLIDE (Glide)	0 to 1,000 ms	0	Portamento time. In Mono mode, glide is legato: the new note slides without retriggering. 0 turns glide off.
TRANSPOSE (Transpose)	-12 to +12 semitones	0	Global transposition in whole semitones.
RATE (LFO Rate)	0.05 to 20 Hz	2 Hz	LFO speed. Not tempo-synced.
AMOUNT (LFO Amount)	0 to 1	0 %	LFO depth. The mod wheel (on-screen or MIDI CC1) adds to this value.
LFO SHAPE (LFO Source menu)	Sine, Square, Sawtooth, Triangle, Noise	Sine	LFO shape.
LFO DESTINATION (Destination menu)	Pitch, Filter, Amplitude	Pitch	LFO target: vibrato, filter wobble or tremolo.
VOICE MODE (Mono/Poly menu)	Poly, Mono	Mono	Mono: one note at a time, last-note priority, legato glide. Poly: up to 16 voices; when all voices are busy, a voice in release is taken first.
UNISON (Unison)	1 to 7	1	Number of detuned copies of each note.

Parameter	Range	Default	Function
DETUNE (Unison Detune)	0 to 60 cents	0	Detune between the unison copies.
Unison Width (no knob)	0 to 1	50 %	Stereo spread of the unison copies.
DISTORTION (Distortion)	0 to 1	0 %	Distortion amount (drive up to 24 dB with an increasing mix).
Distortion Tone (no knob)	100 to 8,000 Hz	5,000 Hz	Tone of the distortion.
CHORUS (Chorus)	0 to 1	0 %	Chorus mix.
Chorus Rate (no knob)	0.1 to 8 Hz	1.5 Hz	Chorus modulation speed.
Chorus Depth (no knob)	0 to 1	50 %	Chorus modulation depth.
DLY MIX (Delay Mix)	0 to 1	0 %	Level of the delay.
DLY TIME (Delay Time)	50 to 1,000 ms	250 ms	Delay time in milliseconds. Not tempo-synced: for a quarter note, use 60,000 / BPM (500 ms at 120 BPM).
DLY FDBK (Delay Feedback)	0 to 0.9	30 %	Number of delay repeats.
REVERB (Reverb)	0 to 1	10 %	Reverb mix.
Reverb Room (no knob)	0 to 1	40 %	Room size.
Reverb Damping (no knob)	0 to 1	50 %	High-frequency damping of the reverb.
Reverb Width (no knob)	0 to 1	100 %	Stereo width of the reverb.
PITCH BEND (Pitch Bend)	-1 to +1	0	On-screen pitch bend, +/-2 semitones. Adds to MIDI pitch bend.
MOD WHEEL (Mod Wheel)	0 to 1	0	On-screen mod wheel. Adds to the LFO AMOUNT, together with MIDI CC1 (the larger of the two applies).

Factory presets

WARZONE808 includes 60 factory presets in 6 banks of 10, plus the 10 presets of the built-in **Expansion Vol.1**. Of the 60 factory presets, 34 load in Mono mode (808 Subs (all 10); Dirty & Reese (all 10); Leads (all 10); FX & Percussion (4 of 10)) and 26 in Poly mode. 9 load with a glide and 12 use unison.

808 Subs: 808 Classic, 808 Boom, 808 Short, 808 Slide, 808 Dirty, 808 Triangle, 808 Deep, 808 Tuned Down, 808 Punch, 808 Trap Long.

Dirty & Reese: Reese Bass, Warzone Growl, Grit Sub, Siren Bass, Detune War, Tank Bass, Mud Reese, Rumble, Subsonic Drift, Overdrive 808.

Leads: War Horn, Bunker Lead, Cavalry Charge, Mono Hero, Night Vision, Sniper, Siren Lead, Sci-Fi Comm, Trench Whistle, Combat Saw.

Plucks & Keys: Ammo Pluck, Boom Bap Keys, Dusty Keys, Saw Pluck, Metal Pluck, Soldier Bell, Dark Chord, Rust Keys, Radio Piano, Bunker Marimba.

Pads & Ambience: Foxhole Pad, Smoke Screen, Fallout, Radar Sweep, Dark Drone, Night Patrol, Ghost Radio, Cold War Strings, Wasteland, Evac Dawn.

FX & Percussion: Explosion, Gunshot, Helicopter, Air Raid, Radio Chatter, Tank Rumble, Laser, Impact, Static Burst, Kick 808.

Expansion Vol.1: Vol1 Sub Drop, Vol1 Grunt, Vol1 Convoy, Vol1 Signal Flare, Vol1 Command Keys, Vol1 Barracks Pad, Vol1 Drone Strike, Vol1 Pluck Squad, Vol1 Rust Lead, Vol1 Ghost Comm.

Loading a preset first resets every parameter to its default value, then applies the preset. The two wheels are not changed.

User presets. Click the disk icon to save the current sound as a `.wz808preset` file. The default folder is `DJBILBOX BEATS/WARZONE808/Presets` inside your Documents folder (Windows and macOS). Files in this folder appear in the **User** submenu of the preset menu.

Expansion packs. An expansion pack is a `.wz808exp` text file (JSON, format `warzone808-expansion`) that contains a name and a list of presets. Packs placed in `DJBILBOX BEATS/WARZONE808/Expansions` inside your Documents folder are loaded at start-up, and their presets appear in the preset menu under the pack name. The cassette menu also lets you load a pack from any location. An invalid file is refused with a message and does not change the plugin.

The host also sees the presets as a program list. Your project saves the full state of the plugin, including the preset name.

Production tips

1. **Trap and Drill 808s.** Start from **808 Classic** or **808 Trap Long**. The 808 presets use a sine, a long decay, no sustain and a low cutoff. Raise DISTORTION or open the CUTOFF a little so the 808 is audible on phone speakers.
2. **808 slides.** In Mono mode with GLIDE above zero, each new note slides from the previous one without retriggering (see **808 Slide**). For slides on selected notes only, keep GLIDE at 0 and automate it before the notes that should slide.
3. **Punch. 808 Punch** uses the filter envelope (ENV AMT at 3 octaves with a short decay) for a hard attack.
4. **Reese and growl. Reese Bass** and **Detune War** use sawtooth waves in unison. Move the filter with the LFO set to Filter for a wobble, as in **Warzone Growl**.
5. **Leads. War Horn** and **Combat Saw** use unison for width. Add a little DLY MIX with DLY TIME set from 60,000 / BPM.
6. **Pads and risers.** The Pads & Ambience bank loads in Poly with long ATTACK and RELEASE values. **Radar Sweep** uses the LFO on the filter and a delay. **Air Raid** (FX & Percussion bank) uses glide and the LFO on pitch for a siren.
7. **War effects.** The FX & Percussion bank uses the Noise waveform: **Explosion**, **Gunshot**, **Helicopter** and **Radio Chatter**. Layer them under your drops.
8. **Layering a kick.** There is no pitch-drop envelope. Layer a kick sample or use **Kick 808** (a sine with a fast filter envelope) in a second instance.

MIDI, automation and performance

Notes and channels. WARZONE808 responds to all MIDI notes on any MIDI channel. Velocity controls the level according to the VELOCITY slider.

Polyphony. In Poly mode, up to 16 voices. When all voices are in use, a voice that is already releasing is taken over first. In Mono mode, a list of held notes is kept: the most recent note plays, and releasing it returns to the note you still hold.

Pitch bend. MIDI pitch bend covers +/-2 semitones. The on-screen PITCH BEND wheel adds another +/-2 semitones.

Mod wheel (CC1). CC1 raises the LFO depth, like the on-screen MOD WHEEL. When both are used, the higher value wins. CC121 resets the MIDI wheels and the sustain pedal.

Sustain pedal. CC64 is supported. All Notes Off and All Sound Off messages stop the sound.

Automation in FL Studio. All 38 parameters can be automated. Move a control in the plugin, then use **Tools > Last tweaked > Create automation clip**. Use **Tools > Last tweaked > Link to controller** to assign a hardware knob. Volume, cutoff and transpose changes are smoothed to avoid clicks.

Latency and tail. The plugin adds no latency (0 samples). It reports an 8-second tail to the host so reverb and delay trails are not cut when rendering.

CPU. WARZONE808 uses no samples. Unison multiplies the number of oscillators per note: use fewer unison voices on dense Poly parts.

FAQ

WARZONE808 does not appear in FL Studio. Open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths, then click **Find installed plugins**. The plugin is listed as **WARZONE808** under **DJBILBOX BEATS**. It is an instrument: load it in the Channel rack, not in a Mixer insert slot.

My chord only plays one note. The plugin starts in Mono mode. Switch VOICE MODE to Poly (up to 16 voices).

Every note slides into the next one. GLIDE is above zero. Set GLIDE to 0, or automate it only where you want slides.

Does it have a pitch envelope for 808 kicks? No. There is no pitch-drop envelope. Use **Kick 808** for a short sine kick, or layer a kick.

How do I add more presets? Load a `.wz808exp` expansion pack with the cassette menu, or place it in the Expansions folder.

Where do I install it on macOS? Copy the VST3 to `/Library/Audio/Plug-Ins/VST3` and the Audio Unit to `/Library/Audio/Plug-Ins/Components`, then rescan plugins in your host. Both are universal builds.

Is the delay tempo-synced? No. Delay time is set in milliseconds (50 to 1,000 ms) and the LFO runs in Hz (0.05 to 20 Hz).