DJBILBOX BEATS / HUMPIRE

HUMPIRE RESPAWN

Algorithmic reverb with an eight-line feedback delay network, pre-delay, damping, low-cut and high-cut filters and ducking.

Version 1.0 - Windows (VST3) and macOS (VST3 / Audio Unit) - Royalty-free license

Contents

HUMPIRE RESPAWN

- Overview
- Quick start in FL Studio
- Interface
- Parameters
- Factory presets
- Production tips
- FAQ

HUMPIRE RESPAWN

Algorithmic reverb with an eight-line feedback delay network, pre-delay, damping, low-cut and high-cut filters and ducking.

Type	Audio effect (reverb)
Format	VST3 64-bit (Windows); VST3 + Audio Unit, universal (macOS)
Brand / developer	HUMPIRE by DJBILBOX BEATS
Version	1.0
Factory presets	12
Decay	0.2 to 20 s
Reported tail	21 seconds
Latency	0 samples

Overview

HUMPIRE RESPAWN is an algorithmic reverb built on an **eight-line feedback delay network** with a Householder feedback matrix. The signal first goes through a **pre-delay**, then through six **early reflections**, and then feeds the eight delay lines that create the tail. The **DECAY** knob sets the time for the tail to fall by 60 dB (0.2 to 20 seconds), **SIZE** scales the length of the delay lines, **DAMP** darkens the tail as it decays, and **MOD** adds a slow modulation for a smoother tail.

A **low cut** and a **high cut** filter shape the reverb itself, and **DUCK** lowers the reverb while the input signal is playing, so a vocal stays clear and the reverb blooms in the gaps. The **MIX** knob sets the dry and wet balance.

The screen shows rings that spread from a speaker cone: the number and speed of rings follow the decay time, and the cone pulses with the level of the reverb.

Quick start in FL Studio

1. Open the **Mixer**, select a track and click an empty slot in its effects chain. Choose **HUMPIRE RESPAWN** (vendor **HUMPIRE by Djbilbox BEATS**). If it is not listed, open **Options > Manage plugins**, check that `C:\Program Files\Common Files\VST3` is in the search paths and click **Find installed plugins**.
2. Click the **preset name** in the top bar and pick a preset, or step through them with **<** and **>**.
3. Start from a preset in the **Plate**, **Hall**, **Hammam** or **Cathedral** category.
4. Adjust **DECAY** and **SIZE** to the length and size of the space.
5. Add **PRE-DLY** (10 to 40 ms) to keep the source in front of the reverb.
6. Use **MIX** to place the sound. On a send track, set MIX to 100%.

Interface

Top bar (all HUMPIRE LOADOUT plugins). From left to right: the HUMPIRE logo and the plugin name, the **<** and **>** buttons (previous and next preset), the preset name (click it to open the preset menu, sorted by category), **SAVE**, **A/B**, **UNDO**, **REDO**, **BYPASS**, and the **IN** and **OUT** level meters. At the right end of the bar, the **SIMPLE** and **CLEAN** buttons change the display.

- **SAVE** asks for a name and stores the current settings as a user preset. User presets are listed in the **User** category of the preset menu.
- **A/B** switches between two settings: the first click stores the current settings in slot A and moves to slot B, and each following click swaps between the two.

- **UNDO** and **REDO** step through your recent control changes and preset loads.
- **BYPASS** passes the audio through untouched. The host also sees it as the plugin's bypass parameter.
- **SIMPLE** hides the advanced knobs and keeps the essential ones. **CLEAN** replaces the textured body with a flat, plain panel. These two choices are saved with your project and are not automatable.

The window opens at 820 x 560 pixels. Drag its bottom-right corner to resize it from 50% to 200%; the proportions stay fixed.

Mouse gestures. Drag a knob up or down. Shift + drag for fine control. Right-click a knob to type a value. Double-click to reset to the default (when supported by the host). Hover over a control to see its value.

Knobs. DECAY, **SIZE**, **PRE-DLY**, **DAMP**, **EARLY**, **MOD**, **LOW CUT**, **HIGH CUT**, **DUCK** and **MIX**. In SIMPLE mode, only **DECAY**, **SIZE**, **PRE-DLY**, **DAMP** and **MIX** remain visible.

Parameters

Control	Host name	Range	Default	Function
DECAY	Decay	0.2 to 20 s	2.0 s	Time for the tail to fall by 60 dB.
SIZE	Size	0.5 to 2	1.00	Scales the delay lines and the early reflections. Larger is a bigger space.
PRE-DLY	Pre-Delay	0 to 200 ms	15 ms	Delay before the reverb starts.
DAMP	Damping	0 to 1	0.40	High-frequency absorption of the tail (cutoff from 18 kHz down to 1.5 kHz).
EARLY	Early	0 to 1	0.50	Level of the early reflections.
MOD	Modulation	0 to 1	0.30	Depth of the slow modulation of the delay lines.
LOW CUT	Low Cut	20 Hz to 1 kHz	80 Hz	High-pass filter on the reverb signal.
HIGH CUT	High Cut	2 kHz to 20 kHz	12 kHz	Low-pass filter on the reverb signal.
DUCK	Ducking	0 to 1	0.00	Amount by which the reverb is lowered while the input is loud.
MIX	Mix	0 to 1	0.30	Dry/wet balance.
BYPASS	Bypass	Off / On	Off	Passes the audio through.

RESPAWN has 11 automatable parameters. The plugin reports a 21-second tail to the host, so reverb tails are not cut when you render.

Factory presets

RESPAWN includes 12 factory presets.

Plate: Plate Vocal, Plate Snare.

Hall: Hall Medium, Hall Large.

Hammam: Hammam Steam, Hammam Chant.

Cathedral: Cathedral Choir, Cathedral Abyss.

Trap Vocals: Trap Vocal Space.

808: 808 Room.

Oud: Oud Chamber.

Darbouka: Darbouka Courtyard.

User presets. SAVE writes an `.xml` file in `%APPDATA%\HUMPIRE\RESPAWN\Presets` on Windows (the `AppData\Roaming` folder of your user account) and in `~/Library/Application Support/HUMPIRE/RESPAWN/Presets` on macOS. Files in this folder appear in the **User** category. Loading a factory preset first resets every parameter to its default, then applies the preset.

Production tips

- **Vocals that stay clear. Trap Vocal Space** combines a medium decay with strong ducking (0.7).
- **Small rooms for 808s and drums. 808 Room** keeps the decay at 0.6 s with a high low cut (300 Hz) so the low end stays tight.
- **Oriental spaces. Hammam Steam** and **Hammam Chant** use heavy damping for a warm, steamy tail.
- **Huge spaces. Cathedral Abyss** reaches a 15-second decay: use it on a send and automate MIX.
- **CPU.** The reverb is lightweight, but very long decays keep the tail running: pause the track when you are not using it.

FAQ

Is there latency? No.

Why is nothing happening at MIX 0? MIX at 0 means 100% dry. Raise it.

How do I use it on a send? Set MIX to 100% and send the amount from each track.