


Lab - Configure VLANs and Trunking

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
S1	VLAN 1	192.168.1.11	255.255.255.0	N/A
S2	VLAN 1	192.168.1.12	255.255.255.0	N/A
PC-A	NIC	192.168.10.3	255.255.255.0	192.168.10.1
РС-В	NIC	192.168.10.4	255.255.255.0	192.168.10.1

Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Create VLANs and Assign Switch Ports

Part 3: Maintain VLAN Port Assignments and the VLAN Database

Part 4: Configure an 802.1Q Trunk between the Switches

Part 5: Delete the VLAN Database

Background / Scenario

Modern switches use virtual local-area networks (VLANs) to improve network performance by separating large Layer 2 broadcast domains into smaller ones. VLANs can also be used as a security measure by controlling which hosts can communicate. In general, VLANs make it easier to design a network to support the goals of an organization.

VLAN trunks are used to span VLANs across multiple devices. Trunks allow the traffic from multiple VLANS to travel over a single link, while keeping the VLAN identification and segmentation intact.

In this lab, you will create VLANs on both switches in the topology, assign VLANs to switch access ports, verify that VLANs are working as expected, and then create a VLAN trunk between the two switches to allow hosts in the same VLAN to communicate through the trunk, regardless of which switch the host is actually attached to.

Note: The switches used with CCNA hands-on labs are Cisco Catalyst 2960s with Cisco IOS Release 15.2(2) (lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and the output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of the lab for the correct interface identifiers.

Note: Ensure that the routers and switches have been erased and have no startup configurations. If you are unsure contact your instructor.

Required Resources

- 2 Switches (Cisco 2960 with Cisco IOS Release 15.2(2) lanbasek9 image or comparable)
- 2 PCs (Windows with a terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Instructions

Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings on the PC hosts and switches.

Step 1: Cable the network as shown in the topology.

Attach the devices as shown in the topology diagram, and cable as necessary.

Step 2: Configure basic settings for each switch.

a. Console into the switch and enable privileged EXEC mode.

```
switch> enable
```

b. Enter configuration mode.

```
switch# config terminal
```

c. Assign a device name to the switch.

```
switch(config) # hostname S1
switch(config) # hostname S2
```

d. Disable DNS lookup to prevent the router from attempting to translate incorrectly entered commands as though they were host names.

```
S1(config) # no ip domain-lookup
S2(config) # no ip domain-lookup
```

e. Assign class as the privileged EXEC encrypted password.

```
S1(config) # enable secret class
S2(config) # enable secret class
```

f. Assign **cisco** as the console password and enable login.

```
S1(config)# line console 0
S1(config-line)# password cisco
S1(config-line)# login

S2(config)# line console 0
S2(config-line)# password cisco
S2(config-line)# login
```

g. Assign **cisco** as the vty password and enable login.

```
S1(config)# line vty 0 4
```

```
S1(config-line) # password cisco
   S1(config-line) # login
   S2(config)# line vty 0 4
   S2(config-line) # password cisco
   S2(config-line)# login
h. Encrypt the plaintext passwords.
   S1(config)# service password-encryption
   S2(config)# service password-encryption

    Create a banner that warns anyone accessing the device that unauthorized access is prohibited.

   S1(config)# banner motd $ Authorized Users Only! $
   S2(config) # banner motd $ Authorized Users Only! $
j. Configure the IP address listed in the Addressing Table for VLAN 1 on the switch.
   S1(config)# interface vlan 1
   S1(config-if) # ip address 192.168.1.11 255.255.255.0
   S1(config-if) # no shutdown
   S1(config-if)# exit
   S2(config)# interface vlan 1
   S2(config-if) # ip address 192.168.1.12 255.255.255.0
   S2(config-if) # no shutdown
   S2(config-if)# exit
k. Shut down all interfaces that will not be used.
   S1(config) # interface range f0/2-5, f0/7-24, g0/1-2
   S1(config-if-range) # shutdown
   S2(config) # interface range f0/2-17, f0/18-24, g0/1-2
   S2(config-if-range) # shutdown
I. Set the clock on the switch.
   S1# clock set 15:30:00 19 September 2019
   S2# clock set 15:30:00 19 September 2019
m. Save the running configuration to the startup configuration file.
```

Step 3: Configure PC hosts.

Refer to the Addressing Table for PC host address information.

S1# copy running-config startup-config

S2# copy running-config startup-config

Step 4: Test connectivity.

Verify that the PC hosts can ping one another.

Note: It may be necessary to disable the PCs firewall to ping between PCs.

Can PC-A ping PC-B?

Yes

Can PC-A ping S1?

No

Can PC-B ping S2?

No

Can S1 ping S2?

Yes

If you answered no to any of the above questions, why were the pings unsuccessful?

Pings were unsuccessful when trying to ping a device on a different subnet. For those pings to be successful, a default gateway must exist to route traffic from one subnet to another.

Part 2: Create VLANs and Assign Switch Ports

In Part 2, you will create Management, Operations, Parking_Lot, and Native VLANs on both switches. You will then assign the VLANs to the appropriate interface. The **show vlan** command is used to verify your configuration settings.

Step 1: Create VLANs on the switches.

a. Create the VLANs on S1.

```
S1(config) # vlan 10
S1(config-vlan) # name Operations
S1(config-vlan) # vlan 20
S1(config-vlan) # name Parking_Lot
S1(config-vlan) # vlan 99
S1(config-vlan) # name Management
S1(config-vlan) # vlan 1000
S1(config-vlan) # name Native
S1(config-vlan) # end
```

- b. Create the same VLANs on S2.
- c. Issue the **show vian brief** command to view the list of VLANs on S1.

```
S1# show vlan brief
```

VLAN	1 Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24 Gi0/1, Gi0/2
10	Operations	active	
20	Parking_Lot	active	
Q Q	Management	agtimo	

20	Parking_Lot	active
99	Management	active
1000	Native	active
1002	fddi-default	act/unsup
1003	token-ring-default	act/unsup
1004	fddinet-default	act/unsup
1005	trnet-default	act/unsup

What is the default VLAN?

VLAN 1

What ports are assigned to the default VLAN?

All switch ports are assigned to VLAN 1 by default.

Step 2: Assign VLANs to the correct switch interfaces.

- a. Assign VLANs to the interfaces on S1.
 - 1) Assign PC-A to the Operation VLAN.

```
S1(config) # interface f0/6
S1(config-if) # switchport mode access
S1(config-if) # switchport access vlan 10
```

2) Move the switch IP address VLAN 99.

```
S1(config) # interface vlan 1
S1(config-if) # no ip address
S1(config-if) # interface vlan 99
S1(config-if) # ip address 192.168.1.11 255.255.255.0
S1(config-if) # end
```

b. Issue the **show vlan brief** command and verify that the VLANs are assigned to the correct interfaces.

```
S1# show vlan brief
```

VLAN	Name	Status	Ports			
1	default	active				
			Fa0/5,	Fa0/7,	Fa0/8,	Fa0/9

```
Fa0/10, Fa0/11, Fa0/12, Fa0/13
Fa0/14, Fa0/15, Fa0/16, Fa0/17
Fa0/18, Fa0/19, Fa0/20, Fa0/21
Fa0/22, Fa0/23, Fa0/24, Gi0/1
Gi0/2
```

10	Operations	active	Fa0/6
20	Faculty	active	
99	Management	active	
1002	fddi-default	act/unsup	
1003	token-ring-default	act/unsup	
1004	fddinet-default	act/unsup	
1005	trnet-default	act/unsup	

c. Issue the show ip interface brief command.

S1# show ip interface brief

Interface	IP-Address	OK? Method	d Status	Protocol
Vlan1	unassigned	YES unset	up	up
Vlan99	192.168.1.11	YES manual	up	down
FastEthernet0/1	unassigned	YES unset	up	up
FastEthernet0/2	unassigned	YES unset	administratively down	down
FastEthernet0/3	unassigned	YES unset	administratively down	down
FastEthernet0/4	unassigned	YES unset	administratively down	down
FastEthernet0/5	unassigned	YES unset	administratively down	down
FastEthernet0/6	unassigned	YES unset	up	up
FastEthernet0/7	unassigned	YES unset	administratively down	down
<pre><output omitted=""></output></pre>				

What is the status of VLAN 99? Explain.

The status of VLAN 99 is up/down, up because the VLAN exists in the database but down because the VLAN has not been assigned to an active port yet.

d. Assign PC-B to the Operations VLAN on S2.

```
S2(config) # interface f0/18
S2(config-if) # switchport mode access
S2(config-if) # switchport access vlan 10
```

e. Remove the IP address for VLAN 1 on S2.

```
S2(config)# interface vlan 1
S2(config-if)# no ip address
```

f. Configure an IP address for VLAN 99 on S2 according to the Addressing Table.

```
S2(config-if) # interface vlan 99
S2(config-if) # ip address 192.168.1.12 255.255.255.0
```

g. Use the **show vlan brief** command to verify that the VLANs are assigned to the correct interfaces.

```
S2# show vlan brief
```

VLAN Name Status Ports

```
active Fa0/1, Fa0/2, Fa0/3, Fa0/4
   default
                                               Fa0/5, Fa0/6, Fa0/7, Fa0/8
                                               Fa0/9, Fa0/10, Fa0/11, Fa0/12
                                               Fa0/13, Fa0/14, Fa0/15, Fa0/16
                                               Fa0/17, Fa0/19, Fa0/20, Fa0/21
                                               Fa0/22, Fa0/23, Fa0/24, Gi0/1
                                               Gi0/2
10 Operations
                                     active Fa0/18
20 Parking_Lot
                                     active
99 Management
                                     active
1000 Native
                                     active
1002 fddi-default
                                     act/unsup
1003 token-ring-default
                                     act/unsup
1004 fddinet-default
                                     act/unsup
1005 trnet-default
                                      act/unsup
Is S1 able to ping S2? Explain.
```

No. The IP addresses for the switches now reside in VLAN 99. VLAN 99 traffic will not be sent over interface F0/1.

Is PC-A able to ping PC-B? Explain.

No. Interface F0/1 is not assigned to VLAN 10, so VLAN 10 traffic will not be sent over it.

Part 3: Maintain VLAN Port Assignments and the VLAN Database

In Part 3, you will change VLAN assignments to ports and remove VLANs from the VLAN database.

Step 1: Assign a VLAN to multiple interfaces.

a. On S1, assign interfaces F0/11 – 24 to VLAN99.

```
S1(config)# interface range f0/11-24
S1(config-if-range)# switchport mode access
S1(config-if-range)# switchport access vlan 99
S1(config-if-range)# end
```

b. Issue the **show vlan brief** command to verify VLAN assignments.

S1# show vlan brief

VLAN	1 Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9
10	Operations	active	Fa0/10, Gi0/1, Gi0/2 Fa0/6
20	Parking_Lot	active	
99	Management	active	Fa0/11, Fa0/12, Fa0/13, Fa0/14

```
Fa0/15, Fa0/16, Fa0/17, Fa0/18
Fa0/19, Fa0/20, Fa0/21, Fa0/22
Fa0/23, Fa0/24

1000 Native active
1002 fddi-default act/unsup
1003 token-ring-default act/unsup
1004 fddinet-default act/unsup
1005 trnet-default act/unsup
```

c. Reassign F0/11 and F0/21 to VLAN 10.

```
S1(config) # interface range f0/11, f0/21
S1(config-if-range) # switchport access vlan 10
S1(config-if-range) # end
```

d. Verify that VLAN assignments are correct.

S1# show vlan brief

VLAN Name	Status Ports
1 default	active Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Gi0/1, Gi0/2
10 Operations	active Fa0/6, Fa0/11, Fa0/21
20 Parking_Lot	active
99 Management	active Fa0/12, Fa0/13, Fa0/14, Fa0/15
	Fa0/16, Fa0/17, Fa0/18, Fa0/19
	Fa0/20, Fa0/22, Fa0/23, Fa0/24
1000 Native	active
1002 fddi-default	act/unsup
1003 token-ring-default	act/unsup
1004 fddinet-default	act/unsup
1005 trnet-default	act/unsup

Step 2: Remove a VLAN assignment from an interface.

a. Use the no switchport access vlan command to remove the VLAN 99 assignment to F0/24.

```
S1(config)# interface f0/24
S1(config-if)# no switchport access vlan
S1(config-if)# end
```

b. Verify that the VLAN change was made.

Which VLAN is F0/24 now associated with?

VLAN 1, the default VLAN.

S1# show vlan brief

VLAN	Name	Status	Ports				
1	default	active	Fa0/1, F	Ta0/2,	Fa0/3,	Fa0/4	

```
Fa0/5, Fa0/7, Fa0/8, Fa0/9
                                               Fa0/10, Fa0/24, Gi0/1, Gi0/2
                                               Fa0/6, Fa0/11, Fa0/21
10 Operations
                                     active
20 Parking Lot
                                     active
99 Management
                                              Fa0/12, Fa0/13, Fa0/14, Fa0/15
                                     active
                                               Fa0/16, Fa0/17, Fa0/18, Fa0/19
                                               Fa0/20, Fa0/22, Fa0/23
1000 Native
                                     active
1002 fddi-default
                                     act/unsup
1003 token-ring-default
                                     act/unsup
1004 fddinet-default
                                     act/unsup
1005 trnet-default
                                     act/unsup
```

Step 3: Remove a VLAN ID from the VLAN database.

a. Add VLAN 30 to interface F0/24 without issuing the global VLAN command.

```
S1(config) # interface f0/24
S1(config-if) # switchport access vlan 30
% Access VLAN does not exist. Creating vlan 30
```

Note: Current switch technology no longer requires that the **vlan** command be issued to add a VLAN to the database. By assigning an unknown VLAN to a port, the VLAN will be created and added to the VLAN database.

b. Verify that the new VLAN is displayed in the VLAN table.

S1# show vlan brief

VLA	N Name	Status	Ports
1	default	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4
			Fa0/5, Fa0/7, Fa0/8, Fa0/9
			Fa0/10, Gi0/1, Gi0/2
10	Operations	active	Fa0/6, Fa0/11, Fa0/21
20	Parking_Lot	active	
30	VLAN0030	active	Fa0/24
99	Management	active	Fa0/12, Fa0/13, Fa0/14, Fa0/15
			Fa0/16, Fa0/17, Fa0/18, Fa0/19
			Fa0/20, Fa0/22, Fa0/23
100	0 Native	active	
100	2 fddi-default	act/unsup	
100	3 token-ring-default	act/unsup	
100	4 fddinet-default	act/unsup	
100	5 trnet-default	act/unsup	

What is the default name of VLAN 30?

VLAN0030

c. Use the **no vlan 30** command to remove VLAN 30 from the VLAN database.

```
S1(config) # no vlan 30
S1(config) # end
```

d. Issue the **show vlan brief** command. F0/24 was assigned to VLAN 30.

After deleting VLAN 30 from the VLAN database, what VLAN is port F0/24 assigned to? What happens to the traffic destined to the host attached to F0/24?

When you delete a VLAN, any ports assigned to that VLAN become inactive. So Port F0/24 is still-associated to VLAN 30. However, VLAN 30 is now inactive because it does not exist in the VLAN database. Additionally, the port will not transfer any traffic.

S1# show vlan brief

VLAN Na	ame	Status	Ports
1 de	efault	active	Fa0/1, Fa0/2, Fa0/3, Fa0/4 Fa0/5, Fa0/7, Fa0/8, Fa0/9 Fa0/10, Gi0/1, Gi0/2
20 Pa	perations arking_Lot anagement	active active active	Fa0/6, Fa0/11, Fa0/21 Fa0/12, Fa0/13, Fa0/14, Fa0/15 Fa0/16, Fa0/17, Fa0/18, Fa0/19 Fa0/20, Fa0/22, Fa0/23
1003 to	ative ddi-default oken-ring-default ddinet-default cnet-default	active act/unsup act/unsup act/unsup	

e. Issue the **no switchport access vlan** command on interface F0/24.

```
S1(config)# interface f0/24
S1(config-if)# no switchport access vlan
S1(config-if)# end
```

f. Issue the **show vlan brief** command to determine the VLAN assignment for F0/24.

To which VLAN is F0/24 assigned?

The default VLAN, VLAN 1

S1# show vlan brief

VLAN Name	Status Ports	
1 default	active Fa0/1, Fa0/2, Fa0/5, Fa0/7, Fa0/10, Fa0/2	•
10 Operations	active Fa0/6, Fa0/11	, Fa0/21
20 Parking_Lot	active	
99 Management	active Fa0/12, Fa0/13	3, Fa0/14, Fa0/15
	Fa0/16, Fa0/1	7, Fa0/18, Fa0/19
	Fa0/20, Fa0/2	2, Fa0/23
1000 Native	active	

1002	fddi-default	act/unsup
1003	token-ring-default	act/unsup
1004	fddinet-default	act/unsup
1005	trnet-default	act/unsup

Note: Before removing a VLAN from the database, it is recommended that you reassign all the ports assigned to that VLAN.

Why should you reassign a port to another VLAN before removing the VLAN from the VLAN database?

The interfaces assigned to a VLAN that is the removed from the VLAN database become inactive and are unavailable for use until they are reassigned to another VLAN. This can be a tricky thing to troubleshoot as trunked interfaces do not show up in the port list as well (Part 4 contains more information about trunked interfaces).

Part 4: Configure an 802.1Q Trunk Between the Switches

In Part 4, you will configure interface F0/1 to use the Dynamic Trunking Protocol (DTP) to allow it to negotiate the trunk mode. After this has been accomplished and verified, you will disable DTP on interface F0/1 and manually configure it as a trunk.

Step 1: Use DTP to initiate trunking on F0/1.

The default DTP mode of a 2960 switch port is dynamic auto. This allows the interface to convert the link to a trunk if the neighboring interface is set to trunk or dynamic desirable mode.

a. Set F0/1 on S1 to negotiate trunk mode.

```
S1(config)# interface f0/1
S1(config-if)# switchport mode dynamic desirable
Sep 19 02:51:47.257: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
Sep 19 02:51:47.291: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan99, changed state to up
```

You should also receive link status messages on S2.

```
S2#
Sep 19 02:42:19.424: %LINK-3-UPDOWN: Interface FastEthernet0/1, changed state to up
Sep 19 02:42:21.454: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan99, changed state to up
Sep 19 02:42:22.419: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
```

b. Issue the **show vlan brief** command on S1 and S2. Interface F0/1 is no longer assigned to VLAN 1. Trunked interfaces are not listed in the VLAN table.

```
S1# show vlan brief
```

```
VLAN Name Status Ports

1 default active Fa0/2, Fa0/3, Fa0/4, Fa0/5
Fa0/7, Fa0/8, Fa0/9, Fa0/10
Fa0/24, Gi0/1, Gi0/2
```

Lab - Configure VLANs and Trunking

```
10
    Operations
                                     active
                                              Fa0/6, Fa0/11, Fa0/21
20 Parking Lot
                                     active
99 Management
                                     active Fa0/12, Fa0/13, Fa0/14, Fa0/15
                                               Fa0/16, Fa0/17, Fa0/18, Fa0/19
                                               Fa0/20, Fa0/22, Fa0/23
1000 Native
                                     active
1002 fddi-default
                                     act/unsup
1003 token-ring-default
                                     act/unsup
1004 fddinet-default
                                     act/unsup
1005 trnet-default
                                     act/unsup
```

c. Issue the **show interfaces trunk** command to view trunked interfaces. Notice that the mode on S1 is set to desirable, and the mode on S2 is set to auto.

S1# show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	desirable	802.1q	trunking	1
Port	Vlans allowed on	trunk		
Fa0/1	1-4094			
.	**1			
Port	Vlans allowed an	d active in man	agement domain	1
Fa0/1	1,10,20,99,1000			
Port	Vlans in spannin	g tree forwardi	ng state and n	ot pruned
Fa0/1	1,10,20,99,1000			

S2# show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	auto	802.1q	trunking	1
Port	Vlans allowed on	trunk		
Fa0/1	1-4094			
Port	Vlans allowed an	d active in man	agement domain	l
Fa0/1	1,10,20,99,1000			
Port	Vlans in spannin	g tree forwardi	ng state and n	ot pruned
Fa0/1	1,10,20,99,1000			

Note: By default, all VLANs are allowed on a trunk. The **switchport trunk** command allows you to control what VLANs have access to the trunk. For this lab, keep the default settings which allows all VLANs to traverse F0/1.

d. Verify that VLAN traffic is traveling over trunk interface F0/1.

Can S1 ping S2?



Can PC-A ping PC-B?

Yes

Can PC-A ping S1?

No

Can PC-B ping S2?

No

If you answered no to any of the above questions, explain below.

The switches are in VLAN 99 and the PCs are in VLAN 10; therefore, the pings between VLANs were unsuccessful.

Step 2: Manually configure trunk interface F0/1.

The **switchport mode trunk** command is used to manually configure a port as a trunk. This command should be issued on both ends of the link.

a. Change the switchport mode on interface F0/1 to force trunking. Make sure to do this on both switches.

```
S1(config) # interface f0/1
S1(config-if) # switchport mode trunk
S2(config) # interface f0/1
S2(config-if) # switchport mode trunk
```

 Issue the show interfaces trunk command to view the trunk mode. Notice that the mode changed from desirable to on.

S2# show interfaces trunk

```
Encapsulation Status Native vlan
Port
         Mode
Fa0/1
                          802.1q trunking
         on
Port
         Vlans allowed on trunk
          1-4094
Fa0/1
          Vlans allowed and active in management domain
Port
          1,10,20,99,1000
Fa0/1
Port
          Vlans in spanning tree forwarding state and not pruned
Fa0/1
          1,10,20,99,1000
```

 Modify the trunk configuration on both switches by changing the native VLAN from VLAN 1 to VLAN 1000.

```
S1(config) # interface f0/1
S1(config-if) # switchport trunk native vlan 1000
```

```
S2(config) # interface f0/1
S2(config-if) # switchport trunk native vlan 1000
```

d. Issue the show interfaces trunk command to view the trunk. Notice the Native VLAN information is updated.

S2# show interfaces trunk

Port	Mode	Encapsulation	Status	Native vlan
Fa0/1	on	802.1q	trunking	1000
Port	Vlans allowed or	n trunk		
Fa0/1	1-4094			
Port	Vlans allowed ar	nd active in man	agement domair	n
Fa0/1	1,10,20,99,1000			
Port	Vlans in spannir	ng tree forwardi	ng state and r	not pruned
Fa0/1	1,10,20,99,1000			

Why might you want to manually configure an interface to trunk mode instead of using DTP?

Not all equipment uses DTP. Using the switchport mode trunk command ensures that the port will become a trunk no matter what type of equipment is connected to the other end of the link.

Why might you want to change the native VLAN on a trunk?

Using VLAN 1, the default VLAN, as the native VLAN is a security risk. All the different control protocols that are exchanged between switches are exchanged via the native VLAN 1 untagged, and that information could be exposed if default settings are used on ports that users connect to.

Part 5: Delete the VLAN Database

In Part 5, you will delete the VLAN Database from the switch. It is necessary to do this when initializing a switch back to its default settings.

Step 1: Determine if the VLAN database exists.

Issue the **show flash** command to determine if a **vlan.dat** file exists in flash.

S1# show flash:

```
Directory of flash:/

2 -rwx 59416 Mar 1 1993 01:20:12 +00:00 multiple-fs
3 -rwx 15186645 Mar 1 1993 00:19:23 +00:00 c2960-lanbasek9-mz.152-4.E8.bin
5 -rwx 796 Sep 19 2019 02:48:04 +00:00 vlan.dat

61028352 bytes total (33762304 bytes free)
```

Note: If there is a **vlan.dat** file located in flash, then the VLAN database does not contain its default settings.

Step 2: Delete the VLAN database.

a. Issue the **delete vlan.dat** command to delete the vlan.dat file from flash and reset the VLAN database back to its default settings. You will be prompted twice to confirm that you want to delete the vlan.dat file. Press Enter both times.

```
S1# delete vlan.dat
Delete filename [vlan.dat]?
Delete flash:/vlan.dat? [confirm]
```

b. Issue the **show flash** command to verify that the vlan.dat file has been deleted.

```
S1# show flash:
```

```
Directory of flash:/

2 -rwx 59416 Mar 1 1993 01:20:12 +00:00 multiple-fs
3 -rwx 15186645 Mar 1 1993 00:19:23 +00:00 c2960-lanbasek9-mz.152-4.E8.bin
61028352 bytes total (33763840 bytes free)
```

To initialize a switch back to its default settings, what other commands are needed?

To get a switch back to its default settings, the erase startup-config and reload commands need to be issued after the delete vlan.dat command.

Reflection Questions

1. What is needed to allow hosts on VLAN 10 to communicate to hosts on VLAN 99?

Answers will vary, but to allow Inter-VLAN routing requires a Layer 3 device is needed to route traffic between VLANs.

2. What are some primary benefits that an organization can receive through effective use of VLANs?

Answers will vary, but VLAN benefits include: better security, cost savings (efficient use of bandwidth and uplinks), higher performance (smaller broadcast domains), broadcast storm mitigation, improved IT staff efficiency, simpler project and application management.

Device Configs - Final

Switch S1

Building configuration...

```
Current configuration: 2571 bytes
version 15.2
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
service password-encryption
hostname S1
boot-start-marker
boot-end-marker
enable secret 5 $1$GCQG$N33u/asvJfEWsnrIHRWjM1
no aaa new-model
system mtu routing 1500
no ip domain-lookup
spanning-tree mode pvst
spanning-tree extend system-id
vlan internal allocation policy ascending
interface FastEthernet0/1
switchport trunk native vlan 1000
switchport mode trunk
interface FastEthernet0/2
shutdown
interface FastEthernet0/3
shutdown
interface FastEthernet0/4
shutdown
interface FastEthernet0/5
shutdown
interface FastEthernet0/6
switchport access vlan 10
switchport mode access
interface FastEthernet0/7
shutdown
interface FastEthernet0/8
shutdown
```

```
interface FastEthernet0/9
shutdown
interface FastEthernet0/10
shutdown
interface FastEthernet0/11
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/12
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/13
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/14
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/15
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/16
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/17
switchport access vlan 99
switchport mode access
shutdown
!
interface FastEthernet0/18
switchport access vlan 99
switchport mode access
shutdown
!
interface FastEthernet0/19
switchport access vlan 99
switchport mode access
```

```
shutdown
interface FastEthernet0/20
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/21
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/22
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/23
switchport access vlan 99
switchport mode access
shutdown
interface FastEthernet0/24
switchport mode access
shutdown
interface GigabitEthernet0/1
shutdown
interface GigabitEthernet0/2
shutdown
interface Vlan1
no ip address
interface Vlan99
ip address 192.168.1.11 255.255.255.0
ip http server
ip http secure-server
banner motd ^C Authorized Users Only! ^C
line con 0
password cisco
logging synchronous
login
line vty 0 4
password cisco
login
```

```
line vty 5 15
password cisco
login
!
end
```

Switch S2

```
Building configuration...
Current configuration: 1875 bytes
version 15.2
no service pad
service timestamps debug datetime msec
service timestamps log datetime msec
service password-encryption
hostname S2
boot-start-marker
boot-end-marker
enable secret 5 $1$jTd.$1rhSHu68akU70GYYyc4Dy1
no aaa new-model
system mtu routing 1500
no ip domain-lookup
spanning-tree mode pvst
spanning-tree extend system-id
vlan internal allocation policy ascending
interface FastEthernet0/1
 switchport trunk native vlan 1000
switchport mode trunk
interface FastEthernet0/2
shutdown
interface FastEthernet0/3
shutdown
interface FastEthernet0/4
shutdown
interface FastEthernet0/5
shutdown
```

```
interface FastEthernet0/6
shutdown
interface FastEthernet0/7
shutdown
interface FastEthernet0/8
shutdown
interface FastEthernet0/9
shutdown
interface FastEthernet0/10
shutdown
interface FastEthernet0/11
shutdown
interface FastEthernet0/12
shutdown
interface FastEthernet0/13
shutdown
interface FastEthernet0/14
shutdown
interface FastEthernet0/15
shutdown
interface FastEthernet0/16
shutdown
interface FastEthernet0/17
shutdown
interface FastEthernet0/18
switchport access vlan 10
switchport mode access
interface FastEthernet0/19
shutdown
interface FastEthernet0/20
shutdown
interface FastEthernet0/21
shutdown
```

```
interface FastEthernet0/22
shutdown
interface FastEthernet0/23
shutdown
interface FastEthernet0/24
shutdown
interface GigabitEthernet0/1
shutdown
Interface GigabitEthernet0/2
shutdown
interface Vlan1
no ip address
interface Vlan99
ip address 192.168.1.12 255.255.255.0
ip http server
ip http secure-server
banner motd ^C Authorized Users Only! ^C
line con 0
password cisco
logging synchronous
login
line vty 0 4
password cisco
login
line vty 5 15
password cisco
login
end
```