Table Of Contents

Table Of Contents	. 1
Install psad under Debian / Ubuntu Linux	2
Configure psad	
Update iptables rules	
How do I view port scan report?	. 4
How do I remove automatically blocked ips?	. 5
How do I view detailed log for each IP address?	. 5
Further readings:	. 5

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format http://www.cyberciti.biz/


Home > Faq > CentOS

psad: Linux Detect And Block Port Scan Attacks In Real Time

Posted by Vivek Gite <vivek@nixcraft.com>

Q. How do I detect port scan attacks by analyzing Debian Linux firewall log files and block port scans in real time? How do I detect suspicious network traffic under Linux?

A. A port scanner (such as nmap) is a piece of software designed to search a network host for open ports. Cracker can use nmap to scan your network before starting attack. You can always see scan patterns by visiting /var/log/messages. But, I recommend the automated tool called psad - the port scan attack detector under Linux which is a collection of lightweight system daemons that run on Linux machines and analyze iptables log messages to detect port scans and other suspicious traffic.



[1]

psad makes use of Netfilter log messages to detect, alert, and (optionally) block port scans and other suspect traffic. For tcp scans psad analyzes tcp flags to determine the scan type (syn, fin, xmas, etc.) and corresponding command line options that could be supplied to nmap to generate such a scan. In addition, psad makes use of many tcp, udp, and icmp signatures contained within the Snort intrusion detection system.

Install psad under Debian / Ubuntu Linux

Type the following command to install psad, enter:

```
$ sudo apt-get update
$ sudo apt-get install psad
```

Configure psad

Open /etc/syslog.conf file, enter:

```
# vi /etc/syslog.conf
```

Append following code

```
kern.info |/var/lib/psad/psadfifo
```

Alternatively, you can type the following command to update syslog.conf:

```
echo -e 'kern.info\t|/var/lib/psad/psadfifo' >> /etc/syslog.conf
```

psad Syslog needs to be configured to write all kern.info messages to a named pipe /var/lib/psad/psadfifo. Close and save the file. Restart syslog:

```
# /etc/init.d/sysklogd restart
# /etc/init.d/klogd
```

The default psad file is located at /etc/psad/psad.conf:

```
# vi /etc/psad/psad.conf
```

You need to setup correct email ID to get port scan detections messages and other settings as follows:

```
EMAIL_ADDRESSES vivek@nixcraft.in;
```

Set machine hostname (FQDN):

```
HOSTNAME server.nixcraft.in;
```

If you have only one interface on box (such as colo web server or mail server), sent HOME_NET to none:

```
HOME_NET NOT_USED; ### only one interface on box
```

You may also need to adjust danger levels as per your setup. You can also define a set of ports to ignore, for example to have psad ignore udp ports 53 and 5000, use:

```
IGNORE_PORTS udp/53, udp/5000;
```

You can also enable real time iptables blocking, by setting following two variables:

```
ENABLE_AUTO_IDS Y;
IPTABLES_BLOCK_METHOD Y;
```

psad has many more options, please read man pages for further information. Save and close the file. Restart psad:

```
# /etc/init.d/psad restart
```

Update iptables rules

psad need following two rules with logging enabled:

```
iptables -A INPUT -j LOG
iptables -A FORWARD -j LOG
```

Here is my sample Debian Linux desktop firewall script with logging enabled at the end:

```
#!/bin/bash
IPT="/sbin/iptables"
echo "Starting IPv4 Wall..."
$IPT -F
$IPT -X
$IPT -t nat -F
$IPT -t nat -X
$IPT -t mangle -F
$IPT -t mangle -X
modprobe ip_conntrack
BADIPS=$(egrep -v -E "^#|^$" /root/scripts/blocked.fw)
PUB_IF="eth0"
#unlimited
$IPT -A INPUT -i lo -j ACCEPT
$IPT -A OUTPUT -o lo -j ACCEPT
# DROP all incomming traffic
$IPT -P INPUT DROP
$IPT -P OUTPUT DROP
$IPT -P FORWARD DROP
# block all bad ips
for ip in $BADIPS
    $IPT -A INPUT -s $ip -j DROP
    $IPT -A OUTPUT -d $ip -j DROP
done
# sync
$IPT -A INPUT -i ${PUB_IF} -p tcp ! --syn -m state --state NEW -m limit --limit 5/m --limi
$IPT -A INPUT -i ${PUB_IF} -p tcp ! --syn -m state --state NEW -j DROP
# Fragments
$IPT -A INPUT -i ${PUB_IF} -f -m limit --limit 5/m --limit-burst 7 -j LOG --log-level 4 --
$IPT -A INPUT -i ${PUB_IF} -f -j DROP
```

```
# block bad stuff
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags ALL FIN, URG, PSH -j DROP
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags ALL ALL -j DROP
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags ALL NONE -m limit --limit 5/m --limit-burst
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags ALL NONE -j DROP # NULL packets
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags SYN,RST SYN,RST -j DROP
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags SYN,FIN SYN,FIN -m limit --limit 5/m --limit
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags SYN,FIN SYN,FIN -j DROP #XMAS
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags FIN, ACK FIN -m limit --limit 5/m --limit-bur
      -A INPUT -i ${PUB_IF} -p tcp --tcp-flags FIN,ACK FIN -j DROP # FIN packet scans
 $IPT -A INPUT -i ${PUB_IF} -p tcp --tcp-flags ALL SYN,RST,ACK,FIN,URG -j DROP
 # Allow full outgoing connection but no incomming stuff
 $IPT -A INPUT -i eth0 -m state --state ESTABLISHED, RELATED -j ACCEPT
 $IPT -A OUTPUT -o eth0 -m state --state NEW, ESTABLISHED, RELATED -j ACCEPT
 # allow ssh only
 $IPT -A INPUT -p tcp --destination-port 22 -j ACCEPT
 $IPT -A OUTPUT -p tcp --sport 22 -j ACCEPT
 # allow incoming ICMP ping pong stuff
 $IPT -A INPUT -p icmp --icmp-type 8 -m state --state NEW, ESTABLISHED, RELATED -j ACCEPT
 $IPT -A OUTPUT -p icmp --icmp-type 0 -m state --state ESTABLISHED, RELATED -j ACCEPT
 # No smb/windows sharing packets - too much logging
 $IPT -A INPUT -p tcp -i eth0 --dport 137:139 -j REJECT
 $IPT -A INPUT -p udp -i eth0 --dport 137:139 -j REJECT
 # Log everything else
 # *** Required for psad ****
 $IPT -A INPUT -j LOG
 $IPT -A FORWARD -j LOG
 $IPT -A INPUT -j DROP
 # Start ipv6 firewall
 # echo "Starting IPv6 Wall..."
 /root/scripts/start6.fw
 exit 0
4
```

How do I view port scan report?

Simply type the following command:

```
# psad -S
```

Sample output (some of the sensitive / personally identified parts have been removed):

```
[+] psadwatchd (pid: 2540) %CPU: 0.0 %MEM: 0.0
   Running since: Sun Jul 27 07:14:56 2008
[+] kmsgsd (pid: 2528) %CPU: 0.0 %MEM: 0.0
   Running since: Sun Jul 27 07:14:55 2008
[+] psad (pid: 2524) %CPU: 0.0 %MEM: 0.8
   Running since: Sun Jul 27 07:14:55 2008
   Command line arguments: -c /etc/psad/psad.conf
   Alert email address(es): radhika.xyz@xxxxxxxx.co.in
                   dst:
                                  chain: intf: tcp: udp: icmp: dl: alerts: os_gues
   src:
   117.32.xxx.149 xx.22.zz.121
                                   INPUT
                                          eth0
                                                 1
                                                       0
                                                             0
                                                                    2
                                                                         2
   118.167.xxx.219 xx.22.zz.121 INPUT eth0
                                                 1
                                                       0
                                                             0
```

Further readings: 5/6

```
118.167.xxx.250 xx.22.zz.121
                                     INPUT
                                             eth0
                                                          0
                                                                0
                                                                           2
     118.167.xxx.5 xx.22.zz.121
                                    INPUT
                                            eth0
                                                          0
     122.167.xx.11
                    xx.22.zz.121
                                    INPUT
                                            eth0
                                                   4642
                                                         0
                                                               0
                                                                      4
                                                                           50
                   xx.22.zz.121
     122.167.xx.80
                                    INPUT
                                            eth0
                                                   0
                                                         11
                                                               0
                                                                      1
                                                                           2
     123.134.xx.34
                    xx.22.zz.121
                                    INPUT
                                            eth0
                                                   20
                                                         0
                                                               0
                                                                      2
                                                                           9
                    xx.22.zz.121
                                  INPUT
                                                         9
     125.161.xx.3
                                                   0
                                                               0
                                                                      1
                                                                           4
                                            eth0
     125.67.xx.7
                   xx.22.zz.121 INPUT
                                            eth0
                                                   1
                                                        0
                                                               0
                                                                      2
                                                                           2
     190.159.xxx.220 xx.22.zz.121 INPUT
                                           eth0
                                                   0
                                                               0
                                                                      1
                                                                           3
     193.140.xxx.210 xx.22.zz.121 INPUT
                                                        10
                                                               0
                                                                      1
                                                                           2
                                            eth0
                                                   0
     202.xx.23x.196 xx.22.zz.121 INPUT
                                            eth0
                                                   0
                                                         13
                                                               0
                                                                      1
                                                                           10
     202.xx.2x8.197 xx.22.zz.121 INPUT
                                                               0
                                                                      2
                                            eth0
                                                   0
                                                         20
                                                                           17
                                            eth0
     202.97.xxx.198 xx.22.zz.121
                                                   0
                                                         17
                                                               0
                                                                      2
                                    INPUT
                                                                           12
     202.97.xxx.199 xx.22.zz.121
                                            eth0
                                                   0
                                                         18
                                                               0
                                                                      2
                                                                           15
                                    INPUT
     202.97.xxx.200 xx.22.zz.121
                                    INPUT
                                            eth0
                                                   0
                                                         17
                                                               0
                                                                      2
                                                                           14
     202.97.xxx.201
                    xx.22.zz.121
                                    INPUT
                                            eth0
                                                   0
                                                         15
                                                               0
                                                                      2
                                                                           12
     202.97.xxx.202 xx.22.zz.121
                                    INPUT
                                             eth0
                                                   0
                                                         21
                                                               0
                                                                      2
                                                                           16
     203.xxx.128.65 xx.22.zz.121
                                                                      2
                                    INPUT
                                            eth0
                                                   12
                                                         0
                                                               0
                                                                           6
                                                                                    Windows
     211.90.xx.14
                    xx.22.zz.121
                                                         0
                                                                      2
                                    INPUT
                                            et.h0
                                                   1
                                                               0
                                                                           2
     213.163.xxx.9 xx.22.zz.121
                                  INPUT
                                            eth0
                                                   0
                                                         0
                                                                      2
                                                                           2.
                                                               1
     221.130.xxx.124 xx.22.zz.121 INPUT
                                            eth0
                                                   0
                                                         35
                                                               0
                                                                      2
                                                                           31
     221.206.xxx.10 xx.22.zz.121 INPUT
                                                   0
                                                         33
                                                               0
                                                                      2
                                            eth0
                                                                           21
     221.206.xxx.53 xx.22.zz.121 INPUT
                                            eth0
                                                   0
                                                         33
                                                               0
                                                                      2.
                                                                           27
     221.206.xxx.54 xx.22.zz.121 INPUT
                                            eth0
                                                   0
                                                         39
                                                               0
                                                                      2
                                                                           26
     221.206.xxx.57 xx.22.zz.121
                                                  0
                                    INPUT
                                            eth0
                                                         33
                                                               0
                                                                      2
                                                                           19
                                                  0
     60.222.xxx.146 xx.22.zz.121
                                    INPUT
                                            eth0
                                                         40
                                                               0
                                                                           33
     60.222.xxx.153 xx.22.zz.121
60.222.xxx.154 xx.22.zz.121
                                    INPUT
                                            eth0
                                                   0
                                                         14
                                                               0
                                                                           11
                                    INPUT
                                            eth0
                                                   0
                                                         18
                                                               0
                                                                      2
                                                                           15
     Netfilter prefix counters:
         "SPAM DROP Block": 161519
         "Drop Syn Attacks": 136
     Total scan sources: 95
     Total scan destinations: 1
     Total packet counters:
         tcp: 5868
         udp: 164012
         icmp: 2
4
```

How do I remove automatically blocked ips?

Simply type the following command to remove any auto-generated firewall block

```
# psad -F
```

How do I view detailed log for each IP address?

Go to /var/log/psad/ip.address/ directory. For example, view log for IP address 11.22.22.33, enter:

```
# cd /var/log/psad/11.22.22.33
# ls -1
```

Sample output:

```
-rw------ 1 root root 2623 2008-07-30 13:02 xx.22.zz.121_email_alert
-rw------ 1 root root 32 2008-07-30 13:02 xx.22.zz.121_packet_ctr
-rw------ 1 root root 0 2008-07-29 00:27 xx.22.zz.121_signatures
-rw------ 1 root root 11 2008-07-30 13:02 xx.22.zz.121_start_time
-rw------ 1 root root 2 2008-07-30 13:02 danger_level
-rw------ 1 root root 2 2008-07-30 13:02 email_count
-rw------ 1 root root 1798 2008-07-29 00:27 whois
```

Use cat/more or less command to view rest of the information.

Further readings:

Further readings: 6/6

- man pages psad, syslog.conf
- psad project home page [2]
- I highly recommend <u>Linux Firewalls: Attack Detection and Response with iptables, psad, and fwsnort</u> [3] for further information.

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/linux-detect-port-scan-attacks/

URLs in this post:

- [1] Image: http://www.cyberciti.biz/faq/faq/category/iptables/
- [2] psad project home page: http://cipherdyne.org/psad/
- [3] Linux Firewalls: Attack Detection and Response with iptables, psad, and fwsnort:

http://www.amazon.com/gp/redirect.html? ie=UTF8 & location=http%3A%2F%2Fwww.amazon.com%2FL inux-Firewalls-Detection-Response-

iptables % 2Fdp% 2F1593271417% 3Fie% 3DUTF8% 26s% 3Dbooks% 26qid% 3D1218020190% 26sr% 3D8-1&tag=cyberciti-20& linkCode=ur2& camp=1789& creative=9325

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details http://www.cyberciti.biz/tips/copyright.